Jont Allen

An Invitation to Mathematical Physics and Its History



An Invitation to Mathematical Physics and Its History



Preface

Science has evolved over thousands of years. It began out of curiosity about how the world around us works as well as a need to know how to make things work better. From water management to space travel, science is essential for success.

The evolution of science is layered: Early science depended mostly on critical observation, thus the early scientist was considered a philosopher, who created a theory. Soon experiments were designed to test these theories. This process is successful when a new principle is established, leading to a deeper and reproducible experimental observation. This typically takes years. A key component of science is making and testing models that are designed to evaluate the results of experiments quantitatively in a mathematical framework. Good science is observation and experimentation. Great science is the art of making models that explain experimental results. This always results in a deeper question, suggesting new experiments. Each generation has its geniuses. One of these was Galileo, who was a philosopher, experimentalist, and mathematician.

An understanding of physics requires a knowledge of mathematics. The converse is not true. By definition, pure mathematics contains no physics. Yet historically, mathematics has a rich history filled with physical applications. Mathematics was developed by individuals who intend to make things work. As an engineer, I see these creators of early mathematics as budding engineers. This book is an attempt to tell the story of the development of mathematical physics as viewed by an engineer.

There are two distinct ways to learn mathematics: by learning definitions and relationships or by associating each mathematical concept with its physical counterpart. Students of physics and engineering best learn mathematics based on the underlying physical concepts. Students of pure mathematics are taught via definitions of abstract structures, not from the history of mathematical physics. These two teaching methods result in very different understandings of the material.

There is a deep common thread between physics and mathematics: the chronological development or the history of mathematics. This is because much of mathematics was developed to solve physical problems. Most early mathematics evolved from attempts to understand the world, with the goal of navigating it. Pure mathematics followed as generalizations of these physical concepts.

vi Preface

Around 1638 Galileo stated that, based on his experiments with balls rolling down inclined planes and pendulums, the height of a falling object is given by

$$h(t) = \frac{1}{2}Gt^2,\tag{1}$$

where t is time and G is a constant. This formula leads to a constant acceleration a(t) of the object since

$$a(t) = \frac{d^2}{dt^2}h(t) = G$$

is independent of time. It follows that the force on a body is proportional to its acceleration a defined as G, namely, $F = a \equiv G$. Thus G must be the object's mass, which must be a constant. If the object has a constant forward velocity, then the object will have a parabolic trajectory. The relative mass may be measured using a balance scale. I believe Galileo understood all this.

Years later, following up on the observations from Galileo's study of pendulums and falling objects, Newton showed that differential equations were necessary to explain gravity, and that the force of gravity is proportional to the masses of the two objects, divided by the square of the reciprocal of the distance between them:

$$\frac{d^2}{dt^2}r(t) = G\frac{mM}{r^2(t)}.$$

To find r(t) we must integrate this equation. For an object at height h(t) above the surface of the earth, $r(t) = R_e + h(t) \approx R_e$, where R_e is the radius of earth. In this case, the force is effectively constant, since $h \ll R_e$. Newton's equation says the acceleration is constant,

$$\frac{d^2h(t)}{dt^2} = G\frac{mM}{R_a^2},$$

but different from Galileo's G (a simple mass). Yet it seems clear that the physics behind Newton's formula for the acceleration a(t) of two large masses (Sun and Earth or Earth and Moon) and Galileo's physics for balls rolling down inclined planes are the same. The difference is that Newton's proportionality constant is a significant generalization of Galileo's. But, other than the constant, which defines the acceleration, the two formulas are the same.

This is not a typical mathematics book; rather, it is about the relationship between math and physics, presented roughly in chronological order via their history. To teach mathematical physics in an orderly way, our treatment requires a step backward in terms of the mathematics, but a step forward in terms of the physics.

https://physicstoday.scitation.org/do/10.1063/PT.6.3.20191002a/full/.

Preface vii

Historically speaking, mathematics was created by individuals such as Galileo who, by modern standards, may be viewed as engineers. This book contains the basic information that well-informed engineers need to know, as best I can provide.

Let the reader beware that engineering and physics texts do not intend to be rigorous, in the mathematical sense. In some ways, mathematics cleans up the mess by proving theorems, which frequently start with speculations in physics and even engineering. The cleanup is a slow, tedious process. Just because something seems obvious based on the known physical facts does not make it a fundamental theorem of mathematics.

Although there are similarities between this book and that of Graham et al. (1994), the differences are notable. First, Graham's *Concrete Mathematics* presents an impossible standard to be measured against. Second, it is clearly a math book, brilliantly written and targeted at computer science students. This book is not just a math book—it is a mathematical physics text, which depends much on underlying math. I would like to believe there are similarities in (1) the broad range of topics, (2) the in-depth discussion, and (3) the use of historical context.

Organization: As discussed in Sect. 1.2.2 and Fig. 1.6 (p. xx), the book is divided into three mathematical themes, called streams, presented as five chapters: Introduction, Number Systems, Algebraic Equations, Scalar Calculus, and Vector Calculus. Appendices are used to isolate complex self-contained topics and large tables, such a those for Laplace transforms.

Chapter 2, Number Systems, introduces two key concepts, the greatest common divisor (GCD) and the continued fraction algorithm (CFA). When we deal with simple electrical networks composed of inductors, resistors, and capacitors (Fig. 3. 8), or mechanical networks consisting of masses, dashpots, and springs, or their equivalent, pendulums, as used by Galileo in his studies of gravity (Figs. 1.3, and 3. 11), the system may be modeled as a Brune impedance, defined as the ratio of polynomials of the Laplace frequency $s = \sigma + \omega j$ (see Sect. 3.2.3, and Sect. 4.4.2). Of special importance is the development of ordinary differential equations (Sect. 3. 4.2, and Eq. 3.4.4) which under generalized symmetry conditions, called postulates (Sect. 3.10.2), characterize the Brune impedances (Brune, 1931a).

Using the CFA (Sect. 2.4.4), we can generalize the Brune impedance. This generalization results in a transmission line, that describes wave propagation in horns, dealt with in Chaps. 4 and 5 (Cauer et al. 1958a, Cauer 1958). This topic is both physically and mathematically important (Cauer, 1932).

The material is delivered in numbered sections (e.g., Sect. 1.1) spread out over a semester of 15 weeks, three lectures per week, with a three-lecture time-out for administrative duties. Eleven problem sets are provided for weekly assignments.

Many students have rated these assignments as the most important part of the course. There is a built-in interplay between these assignments and the lectures. When a student returns an assignment or exam, the full solution is provided while it is still fresh in their mind (a teaching moment).

Ed:

viii Preface

Author's Personal Statement

An expert is someone who has made all possible mistakes in a small field. I don't know if I would be called an expert, but I certainly have made my share of mistakes. I openly state that I love making mistakes because I learn so much from them. One might call that the "expert's corollary."

This book has been written out of my love for the topic of mathematical physics, a topic that provides many insights that lead to a deep understanding of important physical concepts. Over the years I have developed a *physical sense* of math along with a related *mathematical sense* of physics. While doing my research,² I believe that math can be physics and physics math. I have come across what I feel are certain conceptual holes that need filling, and I sense many deep relationships between math and physics that remain unidentified. What we presently teach is not wrong, but it is missing these relationships. What is lacking is an intuition for how math "works." Good scientists "listen" to their data. In the same way, we need to start listening to the language of mathematics. We need to let mathematics guide us toward our engineering goals.

As summarized in Fig. 1, this union of math, engineering, and physics (MEP)³ helps us make progress in understanding the physical world. We must turn to mathematics and physics when trying to understand the universe. My views follow from a lifelong attempt to understand human communication—that is, the perception and decoding of human speech sounds. This research arose from my 32 years at Bell Labs in the Acoustics Research Department. There such lifelong pursuits not only were possible but also were openly encouraged. The idea was that if you are successful at something, take it as far as you can, but, on the other hand, you should not do something well that's not worth doing. People got fired for the latter. I should have left for a university after a mere 20 years at Bell Labs,⁴ but the job was just too cushy.

In this text, it is my goal to clarify conceptual errors while telling the story of physics and mathematics. My views have been inspired by classic works, as documented in the Bibliography. This book was inspired by my reading of Stillwell (2002) through his Chap. 21. Somewhere in Chap. 22. I switched to the third edition (Stillwell 2010), at which point I realized I had much more to master. It became clear that by teaching this material to first-year engineers, I could absorb the advanced material at a reasonable pace. This book soon followed.

²https://auditorymodels.org/index.php/Main/Publications.

³MEP is a focused alternative to STEM.

⁴I started around December 1970, fresh out of graduate school, and retired on December 5, 2002.




Fig. 1 There is a natural symbiotic relationship among mathematics, engineering, and physics (MEP), depicted in the Venn diagram. Mathematics provides the method and rigor. Engineering transforms the method into technology. Physics explores the boundaries. While these three disciplines work well together, there is poor communication, in part due to the vastly different vocabularies. But style may be more at issue. For example, mathematics rarely uses a system of units, whereas physics and engineering depend critically on them. Mathematics strives to abstract the ideas into proofs. Physics rarely uses a proof. When they attempt rigor, physicists and engineers typically get into difficulty. An important observation by Felix Klein about pure mathematicians, regarding the unavoidable inaccuracies in physics: "It may be said that the idea [of inaccuracy] is usually so repulsive to [mathematicians] that its recognition sooner or later spoils their interest in natural science" [Condon and Morse, 1929, p. 19]

Summary

This is foremost a math book, but not the typical math book. *First*, this book is for the engineering minded, for those who need to understand math to do engineering, to learn how things work. In that sense, the book is more about physics and engineering than mathematics. Math skills are essential for making progress in building things, be it pyramids or computers, as clearly shown by the great civilizations of the Chinese, Egyptians, Mesopotamians, Greeks, and Romans.

Second, this is a book about the math that developed to explain physics, to enable people to engineer complex things. To sail around the world, one needs to know how to navigate. This requires a model of the planets and stars. You can know where you are on the Earth once you understand where the Earth is relative to the Sun, planets, Milky Way, and distant stars. The answer to such a cosmic question depends on whom you ask. Who is qualified to answer such a question? It

x Preface

is best answered by those who study mathematics applied to the physical world. The utility and accuracy of that answer depend critically on the depth of understanding of the physics of the cosmic clock.

The English astronomer Edmond Halley (1656–1742) asked Isaac Newton (1643–1727) for the equation that describes the orbit of the planets. Halley was obviously interested in comets. Newton immediately answered, "an ellipse." It is said that Halley was stunned by the response (Stillwell, 2010, p. xxx), as this was what had been experimentally observed by Kepler (ca. 1619), and he knew that Newton must have some deeper insight. Both were eventually knighted.

When Halley asked Newton to explain how he knew, Newton responded, "I calculated it." But when challenged to show the calculation, Newton was unable to reproduce it. This open challenge eventually led to Newton's grand treatise, *Philosophiae Naturalis Principia Mathematica* (July 5, 1687). It had a humble beginning, as a letter to Halley explaining how to calculate the orbits of the planets. To do this Newton needed mathematics, a tool he had mastered. It is widely accepted that Newton and Gottfried Leibniz invented calculus. But the early record shows that perhaps Bhaskara II (1114–1185 CE) had mastered the art well before Newton.⁵

Third, the main goal of this book is to teach mathematics to motivated engineers, in a way that it can be understood, mastered, and remembered. How can this impossible goal be achieved? The answer is to fill in the gaps with *Who did what, and when?* Compared with the math, the historical record is easily mastered.

To be an expert in a field, one must know its history. This includes who the people were, what they did, and the credibility of their story. Do you believe the Pope or Galileo on the roles of the Sun and the Earth? The observables provided by science are clearly on Galileo's side. Who were those first engineers? They are names we all know: Archimedes, Pythagoras, Leonardo da Vinci, Galileo, Newton, and so on. All of these individuals had mastered mathematics. This book presents the tools taught to every engineer. Rather than memorizing complex formulas, make the relationships "obvious" by mastering each simple underlying concept.

Fourth, when most educators look at this book, their immediate reactions are: Each lecture is a topic we spend a week on (in our math/physics/engineering class) and You have too much material crammed into one semester. The first sentence is correct, the second is not. Tracking the students who have taken the course, looking at their grades, and interviewing them personally demonstrate that the material presented here is appropriate for one semester.

To write this book I had to master the language of mathematics. I had already mastered the language of engineering and a good part of physics. One of my secondary goals was to build this scientific Tower of Babel by unifying the terminology and removing the jargon.

⁵https://www-history.mcs.st-and.ac.uk/Projects/Pearce/Chapters/Ch8 5.html.

Preface xi

Acknowledgments

I would like to acknowledge John Stillwell for his brilliant and constructive historical summary of mathematics as well as my close friend and long-time (40 years) colleague Steve Levinson, who somehow drew me into this project without my even knowing it. Next, my brilliant graduate student Sarah Robinson was constantly at my side, first repairing blunders in my first-draft homeworks and then grading these and the exams and tutoring the students. Without her, I would never have survived the first semester. Her proofreading skills are amazing. Thank you, Sarah, for your infinite help. Without Kevin Pitts, this work never could have been started, as he provided early funding when the project was a germ of an idea. Matt Ando's (math) and Michael Stone's (physics) encouragement was psychologically important in helping me think I might actually write a book. Finally, I would like to thank John D'Angelo for his highly critical comments, in response to my thousands of silly math questions. When it comes to the heavy hitting, John was always there to provide a brilliant explanation that I could easily translate into engineerese (matheering?) (i.e., engineer language).

My delightful friend Robert Fossum Emeritus Professor of Mathematics from the University of Illinois kindly pointed out flawed mathematical terminology. Jerome Colburn and James (Jamie) Hutchinson's precise use of the English language dramatically raised the bar on my more than occasionally casual writing style. To each of you, thank you! Swati Meherishi of the Springer staff was perpetually positive about this project and always steered me in the right directions regarding the details of making a manuscript into a book (they are not the same thing).

Finally, I would like to thank my wife, Sheau Feng Jeng (Patricia Allen), for her unbelievable support and love. She delivered constant peace of mind, without which this project could never have been started, much less finished. Many others, including the many students who took courses based on this book, played important roles, but given their large numbers, sadly they must remain anonymous.⁶

C'est par la logique qu'on démontre, c'est par l'intuition qu'on invente. It is by logic that we prove, but by intuition that we discover

—Henri Poincaré

Mahomet, IL, USA March 2020 Jont Allen

⁶https://www.istem.illinois.edu/news/jont.allen.html.

Contents

1	Intro	duction		1
	1.1		Science and Mathematics	2
		1.1.1	The Pythagorean Theorem	3
		1.1.2	What Is Science?	5
		1.1.3	What Is Mathematics?	5
		1.1.4	Early Physics as Mathematics: Back to Pythagoras	7
	1.2	Moder	n Mathematics	8
		1.2.1	Science Meets Mathematics	9
		1.2.2	Three Streams from the Pythagorean Theorem	16
2	Strea	ım 1: Nı	umber Systems	19
	2.1	The Ta	axonomy of Numbers: $\mathbb{P}, \mathbb{N}, \mathbb{Z}, \mathbb{Q}, \mathbb{F}, \mathbb{I}, \mathbb{R}, \mathbb{C}$	20
		2.1.1	Numerical Taxonomy	25
		2.1.2	Applications of Integers	26
	2.2	Proble	ms NS-1	31
		2.2.1	Topic of This Homework	31
		2.2.2	Plotting Complex Quantities in Octave/MATLAB	31
		2.2.3	Prime Numbers, Infinity, and Special Functions	
			in Octave/MATLAB	31
	2.3	The Ro	ole of Physics in Mathematics	33
		2.3.1	The Three Streams of Mathematics	34
		2.3.2	Stream 1: Prime Number Theorems	35
		2.3.3	Stream 2: Fundamental Theorem of Algebra	37
		2.3.4	Stream 3: Fundamental Theorems of Calculus	37
		2.3.5	Other Key Mathematical Theorems	38
	2.4	Applic	ations of Prime Numbers	39
		2.4.1	The Importance of Prime Numbers	39
		2.4.2	Two Fundamental Theorems of Primes	41
		2.4.3	Greatest Common Divisor (Euclidean Algorithm)	42
		2.4.4	Continued Fraction Algorithm	46

xiv Contents

	2.5	Proble	ms NS-2	51
		2.5.1	Topic of This Homework	51
		2.5.2	Prime Numbers	51
		2.5.3	Greatest Common Divisors	52
		2.5.4	Algebraic Generalization of the GCD (Euclidean)	
			Algorithm	53
		2.5.5	Continued Fractions	54
		2.5.6	Continued Fraction Algorithm (CFA)	55
	2.6	Numbe	er Theory Applications	56
3		2.6.1	Pythagorean Triplets (Euclid's Formula)	56
		2.6.2	Pell's Equation	57
		2.6.3	Fibonacci Sequence	60
		2.6.4	Diagonalization of a Matrix (Eigenvalue/Eigenvector	
			Decomposition)	62
		2.6.5	Finding the Eigenvalues	63
		2.6.6	Finding the Eigenvectors	64
	2.7	Proble	ms NS-3	64
		2.7.1	Topic of This Homework	64
		2.7.2	Pythagorean Triplets	64
		2.7.3	Pell's Equation	65
		2.7.4	The Fibonacci Sequence	66
		2.7.5	CFA as a Matrix Recursion	68
3	Algel	raic Fo	quations: Stream 2	69
5	3.1		ra and Geometry as Physics	69
	3.1	3.1.1	The First Algebra	73
		3.1.2	Finding Roots of Polynomials	74
		3.1.3	Matrix Formulation of the Polynomial	84
		3.1.4	Working with Polynomials in MATLAB/Octave	86
	3.2		nalysis	88
	3.2	3.2.1	Eigenvalues of a Matrix	88
		3.2.2	Cauchy's Theorem and Eigenmodes	90
		3.2.3	Taylor Series	93
		3.2.4	Analytic Functions	98
		3.2.5	Brune Impedances	100
		3.2.6	Complex Analytic Functions	101
	3.3		ms AE-1	103
	3.3	3.3.1	Polynomials and the Fundamental Theorem	103
		3.3.1	of Algebra (FTA)	103
		3.3.2	Analytic Functions	103
		3.3.3	Inverse Analytic Functions and Composition	104
		3.3.4	Convolution	106
		0.0.1	Composition of the contract of	100

Contents xv

	3.3.5	Newton's Root-Finding Method	107
	3.3.6	Riemann Zeta Function $\zeta(s)$	107
3.4	Root C	lassification by Convolution	108
	3.4.1	Convolution of Monomials	109
	3.4.2	Residue Expansions of Rational Functions	112
3.5	Introdu	ction to Analytic Geometry	114
	3.5.1	Merging the Concepts	115
	3.5.2	Generalized Scalar Product	120
	3.5.3	Development of Analytic Geometry	121
	3.5.4	Applications of Scalar Products	123
	3.5.5	Gaussian Elimination	125
3.6		Algebra: Systems	128
	3.6.1	Vectors	128
	3.6.2	Vector Products	129
	3.6.3	Norms of Vectors	130
	3.6.4	Matrices	132
	3.6.5	$N \times M$ Complex Matrices	132
	3.6.6	Inverse of the 2×2 Matrix	135
3.7	Problen	ns AE-2	135
	3.7.1	Topics of This Homework	135
	3.7.2	Gaussian Elimination	136
	3.7.3	Two Linear Equations	136
	3.7.4	Integer Equations: Applications and Solutions	137
	3.7.5	Vector Algebra in \mathbb{R}^3	138
	3.7.6	Ohm's Law	140
	3.7.7	Nonlinear (Quadratic) to Linear Equations	141
	3.7.8	Nonlinear Intersection in Analytic Geometry	141
3.8	Transm	ission (ABCD) Matrix Composition Method	143
	3.8.1	Thévenin Parameters of a Source	144
	3.8.2	The Impedance Matrix	145
	3.8.3	Network Power Relationships	147
	3.8.4	Ohm's Law and Impedance	148
3.9	Signals	: Fourier Transforms	152
	3.9.1	Properties of the Fourier Transform	154
3.10	System	s: Laplace Transforms	157
	3.10.1	Properties of the Laplace Transform	158
	3.10.2	System Postulates	162
	3.10.3	Probability	165
3.11	Comple	ex Analytic Mappings (Domain-Coloring)	167
	3.11.1	The Riemann Sphere	170
	3.11.2	Bilinear Transformation	172

xvi Contents

	3.12	Probler	ns AE-3	173
		3.12.1	Topics of This Homework	173
		3.12.2	Two-Port Network Analysis	173
		3.12.3	Algebra	174
		3.12.4	Algebra with Complex Variables	174
		3.12.5	Schwarz Inequality	175
		3.12.6	Probability	176
4	Strea	m 3A: S	Scalar Calculus	177
	4.1		eginning of Modern Mathematics	178
	4.2		nental Theorem of Scalar Calculus	180
		4.2.1	Fundamental Theorem of Real Calculus	180
		4.2.2	The Fundamental Theorem of Complex Calculus	181
		4.2.3	Cauchy–Riemann Conditions	182
	4.3	Probler	ns DE-1	184
		4.3.1	Topics of This Homework	184
		4.3.2	Complex Power Series	184
		4.3.3	Cauchy–Riemann Equations	185
		4.3.4	Branch Cuts and Riemann Sheets	186
		4.3.5	A Cauer Synthesis of any Brune Impedance	187
	4.4	Comple	ex Analytic Brune Admittance	187
		4.4.1	Generalized Admittance/Impedance	189
		4.4.2	Complex Analytic Impedance	190
		4.4.3	Multivalued Functions	195
	4.5	Three C	Cauchy Integral Theorems	203
		4.5.1	Cauchy's Theorems for Integration in the Complex	
			Plane	203
		4.5.2	Cauchy Integral Formula and Residue Theorem	204
	4.6	Probler	ns DE-2	206
		4.6.1	Topics of This Homework	206
		4.6.2	Two Fundamental Theorems of Calculus	206
		4.6.3	Cauchy's Theorems CT-1, CT-2, CT-3	208
		4.6.4	Integration of Analytic Functions	210
		4.6.5	Laplace Transform Applications	211
		4.6.6	Computer Exercises with Matlab/Octave	212
		4.6.7	Inverse of Riemann $\zeta(s)$ Function	214
		4.6.8	Quadratic Forms	216
	4.7	The La	place Transform and Its Inverse	216
		4.7.1	Case for Negative Time $(t < 0)$ and Causality	218
		4.7.2	Case for Zero Time $(t = 0)$	218
		4.7.3	Case for Positive Time $(t > 0)$	218
		4.7.4	Properties of the $\mathcal{L}T$	220
		4.7.5	Solving Differential Equations	222

Contents xvii

	4.8	Problen	ns DE-3	223
		4.8.1	Topics of This Homework: Brune Impedance	223
		4.8.2	Brune Impedance	223
		4.8.3	Transmission Line Analysis	224
5	Strea	m 3B: V	Vector Calculus	227
	5.1	Properti	ies of Fields and Potentials	227
		5.1.1	Scalar and Vector Fields	227
		5.1.2	Gradient ∇ , Divergence ∇ ., Curl ∇ x,	
			and Laplacian ∇^2	229
		5.1.3	Scalar Laplacian Operator in N Dimensions	234
	5.2	Partial 1	Differential Equations and Field Evolution	242
		5.2.1	The Laplacian ∇^2	242
		5.2.2	Scalar Wave Equation (Acoustics)	246
		5.2.3	The Webster Horn Equation (WHEN)	248
		5.2.4	Matrix Formulation of the WHEN	250
	5.3	Problen	ns VC-1	252
		5.3.1	Topics of This Homework	252
		5.3.2	Scalar Fields and the ∇ Operator	252
		5.3.3	Vector Fields and the ∇ Operator	253
		5.3.4	Vector and Scalar Field Identities	254
		5.3.5	Integral Theorems	254
		5.3.6	System Classification	255
	5.4	Three E	Examples of Finite-Length Horns	256
		5.4.1	Uniform Horn	257
		5.4.2	Conical Horn	259
		5.4.3	Exponential Horn	260
	5.5	Solution	n Methods	261
		5.5.1	Eigenfunctions $\varrho^{\pm}(r,t)$ of the WHEN	263
	5.6	Integral	Definitions of $\nabla()$, $\nabla \cdot ()$, $\nabla \times ()$, and $\nabla \wedge ()$	265
		5.6.1	Gradient: $\boldsymbol{E} = -\nabla \phi(\boldsymbol{x})$	265
		5.6.2	Divergence: $\nabla \cdot \mathbf{D} = \rho \left[C/m^3 \right] \dots$	266
		5.6.3	Integral Definition of the Curl: $\nabla \times \mathbf{H} = \mathbf{C} \dots \dots$	268
		5.6.4	Summary	269
		5.6.5	Helmholtz's Decomposition Theorem	270
		5.6.6	Second-Order Operators	274
	5.7	The Un	ification of Electricity and Magnetism	276
		5.7.1	Field Strength E, H	277
		5.7.2	Flux D , B	277
		5.7.3	Maxwell's Equations	277
		574	Derivation of the Vector Wave Equation	280

xviii Contents

5.8	Potenti	al Solutions of Maxwell's Equations	282
	5.8.1	Use of Helmholtz's Theorem on Potential Solutions	283
	5.8.2	ME for $E(x,t)$	283
	5.8.3	ME for $H(x,t)$	284
	5.8.4	Summary	284
5.9	Probler	ms VC-2	285
	5.9.1	Topics of This Homework	285
	5.9.2	Partial Differential Equations (PDEs): Wave	
		Equation	285
	5.9.3	Helmholtz's Formula	286
	5.9.4	Maxwell's Equations	288
	5.9.5	Second-Order Differentials	289
	5.9.6	Capacitor Analysis	289
7.10	5.9.7	Webster Horn Equation	290
5.10	Further	Readings	290
Appendi	x A: No	tation	291
Appendi	x B: Eig	genanalysis	305
Appendi	x C: La	place Transforms \mathcal{LT}	313
Appendi	x D: Vis	sco-Thermal Losses	323
Appendi	x E: The	ermodynamic Systems	329
Appendi	x F: Nu	mber Theory Applications	335
Appendi	x G: Ele	even Postulates of Systems of Algebraic Networks	339
Appendi	x H: We	ebster Horn Equation Derivation	347
Appendi	x I: Qua	antum Mechanics and the WHEN	353
Referenc	es		365
Index			371

Chapter 1 Introduction



Much of early mathematics, say before 1600 BCE, involved the love of art and music, the sensations of light and sound. Our psychological senses of color and pitch are determined by the frequencies (i.e., wavelengths) of light and sound. The Chinese and later the Pythagoreans are well known for their early contributions to music theory.

We are largely ignorant of exactly what Chinese scholars knew. The best record of early mathematics comes from Euclid, who lived in the fourth century BCE, after Pythagoras. Thus we can trace early mathematics back to the Pythagoreans in the sixth century (580–500 BCE), who focused on the Pythagorean theorem and early music theory.

Pythagoras strongly believed that "all is number," meaning that every number, and every mathematical and physical concept, could be explained by integral (integer) relationships, mostly based on either ratios or the Pythagorean theorem. It is likely that his belief was based on Chinese mathematics from thousands of years earlier. It is also believed that his ideas about the importance of integers followed from music theory. The musical notes (pitches) obey natural integral ratio relationships based on the octave (a factor of two in frequency). The western 12-tone scale breaks the octave into 12 ratios called *semitones*. Today this has been rationalized to be the 12th root of 2, which is approximately equal to $18/17 \approx 1.06$ or 0.0833 [octave]. Our innate sense of frequency ratios comes from the physiology of the auditory organ (the cochlea), with a fixed distance along the organ of Corti, the sensory organ of the inner ear.

As acknowledged by Stillwell (2010, p. 16), the Pythagorean view is still relevant today:

With the digital computer, digital audio, and digital video coding everything, at least approximately, into sequences of whole numbers, we are closer than ever to a world in which "all is number."

1 Introduction




Fig. 1.1 Timeline between 1500 BCE and 1650 CE. The European renaissance is considered to have occurred between the fifteenth and seventeenth centuries CE

1.1 Early Science and Mathematics

Although early Asian mathematics has been lost, it clearly defined its course for at least several millennia. The first recorded mathematics was from the Chinese (5000–1200 BCE) and the Egyptians (3300 BCE). Some of the best early records were left by the people of Mesopotamia (Iraq, 1800 BCE). While the first 5000 years of math are not well documented, the basic timeline is clear, as shown in Fig. 1.1.

Thanks to Euclid, and later Diophantus (ca. 250 CE), we have some basic (but vague) understanding of Chinese mathematics. For example, Euclid's formula (Eq. 2.6.6) provides a method for computing Pythagorean triplets, a formula believed to be due to the Chinese.²

Chinese bells and stringed musical instruments were exquisitely developed with tonal quality, as documented by ancient physical artifacts (Fletcher and Rossing 2008). In fact this development was so rich that one must ask why the Chinese failed to initiate the Industrial Revolution. Specifically, why did European innovation eventually dominate when it was the Chinese who were responsible for such extensive early invention?

Our best insight into the scientific history of China came from Joseph Needham, an American chemist and scholar from Cambridge, England. Needham learned Chinese from a colleague³ and ended up researching early Chinese science and technology for the U.S. government (Winchester 2009).

According to Lin (1995), the Needham question is:

Why did modern science, the mathematization of hypotheses about Nature, with all its implications for advanced technology, take its meteoric rise only in the West at the time of Galileo[, but] had not developed in Chinese civilization or Indian civilization?

As discussed by Lin (1995) and Apte (2009), Needham cites the many developments in China:

Gunpowder, the magnetic compass, and paper and printing, which Francis Bacon considered as the three most important inventions facilitating the West's transformation from the Dark Ages to the modern world, were invented in China.

¹See Fig. 2.8

²One might reasonably view Euclid's role as that of a mathematical messenger.

³Whom he later fell in love with Winchester (2009).

Needham's works attribute significant weight to the impact of Confucianism and Taoism on the pace of Chinese scientific discovery, and emphasize what it describes as the "diffusionist" approach of Chinese science as opposed to a perceived independent inventiveness in the western world. Needham held that the notion that the Chinese script had inhibited scientific thought was "grossly overrated." (Grosswiler 2004)

Lin (1995) focused on military applications, missing the importance of nonmilitary contributions. A large fraction of mathematics was developed to better understand the solar system, acoustics, musical instruments, and the theory of sound and light. Eventually the universe became a popular topic, as it still is today.

Regarding the Needham question, I suspect the answer is now clear. In the end, China withdrew from its several earlier expansions because of internal politics (Menzies 2004, 2008).

History of Mathematics to the Sixteenth Century CE 20th Chinese (primes; quadratic equation; Euclidean algorithm (GCD)) 18th Babylonians (Mesopotamia/Iraq) (quadratic solution) 6th Thales of Miletus (first Greek geometry) (624) 5th Pythagoras and the Pythagorean "tribe" (570) 4th Euclid; Archimedes 3rd Eratosthenes (276–194) **BCE** 3rd Diophantus (ca. 250) CE 4th Library of Alexandria destroyed by fire (391) 7th Brahmagupta (negative numbers; quadratic equation) (598–670) 10th al-Khwarizmi (algebra) (830); Hasan Ibn al-Haytham (Alhazen) (965-1040)14th Bhaskara (calculus) (1114–1183) 15th Leonardo da Vinci (452–1519); Michelangelo (1475–1564); Copernicus (1473–1543) 16th Tartaglia (cubic solution); Bombelli (1526–1572); Galileo Galilei

1.1.1 The Pythagorean Theorem

(1564-1642)

Thanks to Euclid's *Elements* (written ca. 323 BCE) we have a historical record tracing the progress in geometry as established by the Pythagorean theorem, which states that *for any right triangle* having sides of lengths $(a, b, c) \in \mathbb{R}$ that are either positive-real numbers or, more interesting, integers $c > [a, b] \in \mathbb{N}$ such that a + b > c,

$$c^2 = a^2 + b^2. (1.1)$$

Early integer solutions were likely found by trial and error rather than by an algorithm. If a, b, c are lengths, then a^2 , b^2 , c^2 are each the area of a square. Equation 1.1 says that the area a^2 plus the area b^2 equals the area c^2 . Today a simple way to prove

4 1 Introduction

this is to compute the magnitude of the complex number c = a + bj, which forces the right angle

 $|c|^2 = (a+b_1)(a-b_1) = a^2 + b^2.$ (1.2)

However, complex arithmetic was not an option for the Greek mathematicians, since complex numbers and algebra had yet to be discovered.

Almost 700 years after Euclid's *Elements*, the Library of Alexandria was destroyed by fire (391 CE), taking with it much of the accumulated Greek knowledge. As a result, one of the best technical records remaining is Euclid's *Elements*, along with some sparse mathematics due to Archimedes (ca. 300 BCE) on geometrical series, the volume of a sphere, the area of a parabola, and elementary hydrostatics. In about 1572 a copy Diophantus's *Arithmetic* was discovered by Bombelli in the Vatican library (Burton 1985; Stillwell 2010, p. 51). This book became an inspiration for Galileo, Descartes, Fermat, and Newton.

Early number theory: Well before Pythagoras, the Babylonians (ca. 1,800 BCE) had tables of triplets of integers [a, b, c] that obey Eq. 1.1, such as [3, 4, 5]. However, the triplets from the Babylonians were larger numbers, the largest being a = 12,709 and c = 18,541. A clay tablet (Plimpton-322) dating back to 1800 BCE was found with integers for [a, c]. Given such sets of two numbers, which determined a third positive integer b = 13,500 such that $b = \sqrt{c^2 - a^2}$, this table is more than convincing that the Babylonians were well aware of Pythagorean triplets (PTs), but less convincing that they had access to Euclid's formula, a formula for PTs (Eq. 2.6.6).

It seems likely that Euclid's *Elements* was largely the source of the fruitful era of the Greek mathematician Diophantus (215–285) (see Fig. 1.1), who developed the field of discrete mathematics, now known as *Diophantine analysis*. The term means that the solution, not the equation, is integer. The work of Diophantus was followed by fundamental changes in mathematics, possibly leading to the development of algebra but at least including these discoveries:

- 1. Negative numbers
- 2. Quadratic equations (Brahmagupta, seventh century)
- 3. Algebra (al-Khwarizmi, nineth century)
- 4. Complex arithmetic (Bombelli, fifteenth century)

These discoveries overlapped with the European Middle Ages (also known as the Dark Ages). Although Europe went "dark," presumably European intellectuals did not stop working during these many centuries.⁴

⁴It would be interesting to search the archives of the monasteries, where the records were kept, to determine exactly what happened during this religious blackout.

1.1.2 What Is Science?

Science is a process that quantifies hypotheses to build truths. 5 It has evolved from early Greek philosophers, Plato and Aristotle, into a method that uses statistical tests to either validate or prove wrong the null hypothesis. Scientists use the term *null hypothesis* to describe the supposition that there is no difference between two intervention groups or no effect of a treatment on some measured outcome. The measure of the likelihood that an outcome occurred by chance is called the p-value. From the p-value we can have some confidence that the null hypothesis is either true (the treatment causes no difference between two groups) or false (the probability p of a difference is greater than chance). The p-value is the present standard of scientific truth, but it is not ironclad and must be used with care. For example, not all experimental questions may be reduced to a single binary test. Does the Sun revolve around the Moon or around the Earth? There is no test of this question, as it is nonsense. To even say that the Earth revolves around the Sun is, in some sense, nonsense because all the planets are involved in the orbital motion.

Yet science works quite well. Thanks to mathematics, we have learned many deep secrets regarding the universe over the last 5000 years.

1.1.3 What Is Mathematics?

It seems strange when people complain that they "can't learn math" but then claim to be good at languages. Before high school, students tend to confuse arithmetic with math. One does not need to be good at arithmetic to be good at math (but it doesn't hurt).

Math is a language with symbols taken from various languages—not so different from other languages. Today's mathematics is a written language with an emphasis on symbols and glyphs, primarily Greek letters, obviously due to the popularity of Euclid's *Elements*. The specific evolution of these symbols is interesting (Mazur 2014). Each symbol is assigned a meaning appropriate for the problem being described. These symbols are then assembled to make sentences. In the Chinese language, the spoken and written versions are different across dialects. Similarly, mathematical sentences may be read out loud in any language (dialect), but the symbols (like Chinese characters) are universal.

Learning languages is an advanced social skill. However, the social outcomes of learning a language and learning math are very different. Learning a new language is fun because it opens doors to other cultures. Math is different due to the rigor of the grammar (rules of the language) as well as the way it is taught (i.e., not as a language). A third difference between math and language is that math evolved from physics and has important technical applications.

⁵https://physicstoday.scitation.org/do/10.1063/PT.6.3.20191018a/full/.

^{6&}quot;It looks like Greek to me."

6 1 Introduction

As with any language, the more mathematics you learn, the easier it is to understand, because mathematics is built from the bottom up. It's a continuous set of concepts, much like the construction of a house. If you try to learn calculus and differential equations but skip simple number theory, the lessons will be more difficult to understand. You will end up memorizing instead of understanding, and as a result you will likely soon forget it. When you truly understand something, it can never be forgotten. A nice example is the solution to a quadratic equation: If you learn how to complete the square (see Sect. 3.1.1), you don't need to know the quadratic formula.

Mathematical topics need to be learned in order, just as in the case of building the house. You can't build a house if you don't know about screws or cement (plaster). Likewise in mathematics, you can't learn to integrate if you have failed to understand the difference between integers, complex numbers, polynomials, and their roots.

A short list of topics in mathematics includes numbers $(\mathbb{N}, \mathbb{Z}, \mathbb{Q}, \mathbb{I}, \mathbb{C})$, algebra, derivatives, antiderivatives (i.e., integration), differential equations, vectors and the spaces they define, matrices, matrix algebra, eigenvalues and vectors, solutions of systems of equations, and matrix differential equations and their eigensolutions. Learning is about understanding, not memorizing.

The rules of mathematics are formally defined by algebra. For example, the sentence a=b means that the number a has the same value as the number b. The sentence is read as "a equals b." The numbers are nouns and the equal sign says they are equivalent; it plays the role of a verb or action symbol. Following the rules of algebra, this sentence may be rewritten as a-b=0. Here the symbols for minus and equal indicate two types of actions (verbs).

Sentences can become arbitrarily complex, such as the definition of the integral of a function or a differential equation. But in each case, the mathematical sentence is written down, may be read out loud, has a well-defined meaning, and may be manipulated into equivalent forms following the rules of algebra and calculus. This language of mathematics is powerful, with deep consequences, first known as algorithms but eventually as theorems.

The writer of an equation should always translate (explicitly summarize the meaning of the expression), so the reader will not miss the main point. This is a simple matter of clear writing.

Just as math is a language, so language may be thought of as mathematics. To properly write correct English it is necessary to understand the construction of the sentence. It is important to identify the subject, verb, object, and various types of modifying phrases. For example, look up the interesting distinction between *that* and *which*. Thus, like math, language has rules. Most individuals use language that "sounds right," but if you're learning English as a second language, you must understand the rules, which are arguably easier to master than its foreign speech sounds.

Context can be critical, and the most important context for mathematics is physics. Without a physical problem to solve, there can be no engineering mathematics. People needed to navigate the Earth and weigh things, which required an understanding of

⁷https://en.oxforddictionaries.com/usage/that-or-which.




Fig. 1.2 Timeline covering the two centuries from 1596CE to 1855CE, including the development of modern theories of analytic geometry, calculus, differential equations, and linear algebra. Newton was born about one year after Galileo died and thus was heavily influenced by his many discoveries. The vertical red lines indicate mentor–student relationships. Note the significant overlap among Newton, the Bernoullis, and Euler, a nucleation point for modern mathematics. Lagrange had a key role in the development of linear algebra. Gauss had the advantage of input from Newton, Euler, d'Alembert, and Lagrange. Likely Cauchy had a significant contemporary influence on Gauss as well. Finally, note that Fig. 1.1 ends with Bombelli while this figure begins with him. He famously discovered a copy of Diophantus's book in the Vatican library. This was the same book where Fermat noted that the margin was too small to hold the "proof" of his "last theorem"

gravity. Many questions about gravity were deep, such as Where is the center of the universe? But church dogma goes only so far. Mathematics along with a heavy dose of physics finally answered this huge question. Someone needed to perfect the telescope, put satellites into space, and view the cosmos. Without mathematics none of this would have happened.

1.1.4 Early Physics as Mathematics: Back to Pythagoras

We have established that math is the language of science. There is an additional answer to the question What is mathematics? The answer, the creation of algorithms and theorems, comes from studying its history, beginning with the earliest records. This chronological view starts, of course, with the study of numbers. First there is the taxonomy of numbers. It took thousands of years to realize that numbers are more than the counting numbers $\mathbb N$, to create a symbol for nothing (i.e., zero), and to invent negative numbers. With the invention of the abacus, a memory aid for manipulating complex sets of real integers, one could do very detailed calculations. But this required the discovery of algorithms (procedures) to add, subtract, multiply (many additions of the same number), and divide (many subtractions of the same number), such as the Euclidean algorithm for the greatest common divisor (GCD). Eventually it became clear to the experts (early mathematicians) that there were

 $^{^8}$ Actually this answer is simple: Ask the Pope and he will tell you. (I apologize for this inappropriate joke.).

8 1 Introduction

natural rules to be discovered; thus books (e.g., Euclid's *Elements*) were written to summarize this knowledge.

The role of mathematics is to summarize algorithms (i.e., sets of rules) and formalize an idea as a theorem. Pythagoras and his followers, the Pythagoreans, believed that there was a fundamental relationship between mathematics and the physical world. The Asian civilizations were the first to capitalize on the relationship between science and mathematics, to use mathematics to design things for profit. This may have been the beginning of capitalizing technology (i.e., engineering), based on the relationship between physics and math. This influenced commerce in many ways—map making, tools, implements of war (the wheel, gunpowder), art (music), water transport, sanitation, secure communication, food, namely, all aspects of human existence. Of course it was the Asian cultures to first to master many of these early technologies.

The Pythagorean theorem (Eq. 1.1) did not begin with Euclid or Pythagoras; rather they appreciated its importance and documented its proof. Why is Eq. 1.1 called a *theorem*? Theorems require a proof. What exactly needs to be proved? We do not need to prove that (a, b, c) obeys this relationship, since this condition is observed. We do not need to prove that a^2 is the area of a square, as this is the definition of an area. What needs to be proved is that the relationship $c^2 = a^2 + b^2$ holds *if*, and only if, the angle between the two shorter sides is 90° .

In the end, because they instilled fear in the neighbor, the Pythagoreans were burned out and murdered, likely the result of mixing technology with politics:

[It is] said that when the Pythagoreans tried to extend their influence into politics they met with popular resistance. Pythagoras fled, but he was murdered in nearby Mesopotamia in 497 BCE. (Stillwell 2010, p. 16)

1.2 Modern Mathematics

Modern mathematics (what we practice today) was born in the fifteenth and sixteenth centuries in the minds of Leonardo da Vinci, Bombelli, Galileo, Descartes, Fermat, and many others (Burton 1985). Many of these early masters were, like the Pythagoreans, extremely secretive about how they solved problems. This soon changed with Galileo, Mersenne, Descartes, and Newton, which caused mathematics to blossom. Developments during this time may seem hectic and disconnected, but this is a wrong impression. The developments were dependent on new technologies, such as the telescope (optics) and more accurate time and frequency measurements, due to Galileo's studies of the pendulum, and a better understanding of the relationship $f\lambda = c_o$ among frequency f, wavelength λ , and wave speed c_o .

1.2 Modern Mathematics 9

1.2.1 Science Meets Mathematics

Early studies of vision and hearing: Since light and sound (music) played such a key role in the development of the early science, it was important to understand fully the mechanism of our perception of light and sound. There are many outstanding examples where physiology impacted mathematics. Leonardo da Vinci (1452–1519) is well known for his early studies of human anatomy, the knowledge of which was key when it came to drawing and painting the human form.


Galileo: In 1589 Galileo Galilei (1564–1642) famously conceptualized an experiment in which he suggested dropping two different masses from the Leaning Tower of Pisa. He suggested that both must take the same time to hit the ground.

Conceptually this is a mathematically sophisticated experiment, driven by a mathematical argument in which Galileo considered the two masses to be connected by an elastic cord (a spring) or rolling down a frictionless inclined plane (see Fig. 1.3). His studies resulted in the concept of conservation of energy, one of the cornerstones of physical theory since that time.

Being joined with an elastic cord, the masses become one. If the velocity were proportional to the mass, as Archimedes believed, the sum of the two masses would necessarily fall even faster. This results in a logical fallacy: How can two masses fall faster than either mass alone? This also violates the concept of conservation of energy, as the total energy of the two masses would be greater than that of the parts. In fact, Galileo's argument may have been the first time that the principle of conservation of energy was clearly stated.

It seems likely that Galileo was attracted to this model of two masses connected by a spring because he was also interested in planetary motion, which consists of masses (Sun, Earth, Moon) also mutually attracted by gravity (i.e., the spring).

Fig. 1.3 Depiction of Galileo's argument (from his unpublished book of 1638) as to why objects of different masses (i.e., weights) must fall with the same velocity, contrary to what Archimedes had proposed in about 250 BCE



10 1 Introduction

Galileo performed related experiments on pendulums, where he varied the length l, mass m, and angle θ of the swing. By measuring the period he was able to formulate precise relationships between the variables. This experiment also measured the force exerted by gravity, so the experiments were related, but in very different ways. The pendulum served as the ideal clock, as it needed very little energy to keep it going, due to its very low friction (energy loss).

In a related experiment, Galileo measured the length of a day by counting the number of swings of the pendulum in 24 h, measured precisely by the daily period of a star as it crossed the tip of a church steeple. The number of seconds in a day is $24 \cdot 60 \cdot 60 = 86,400 = 2^7 3^3 5^2$ [s/day]. Since 86,400 is the product of the first three primes, it is highly composite and thus may be expressed in many equivalent ways. For example, the day can be divided evenly into 2, 3, 4, or 5 parts and remain the same in terms of the number of seconds that transpire. It would be interesting to know who was responsible for this highly composite number of seconds per day.

Factoring the number of days in a year $(365 = 5 \cdot 73)$ is a poor choice, since it may not be decomposed into many small primes. For example, if the year were taken as $364 = 2^2 \cdot 7 \cdot 13$ days, it would make for shorter years (by 1 day), 13 months per year, perfect quarters, $28 = 4 \cdot 13$ day months, and $52 = 4 \cdot 13$ weeks. Every holiday would always fall on the same day, every year. It would be a calendar that humans could better understand. As with second per day, it would be fascinating to know why the number of days per year was so poorly chosen.

Galileo also studied on the relationship between the wavelength and frequency of a sound wave in musical instruments. Galileo also greatly improved the telescope, which he needed for his observations of the planets and their Moons.

Many of Galileo's contributions resulted in new mathematics, leading to Newton's discovery of the wave equation (1687), followed 60 years later by its one-dimensional general solution by d'Alembert (1747).

Mersenne: Marin Mersenne (1588–1648) contributed to our understanding of the relationship between the wavelength and the dimensions of musical instruments and is said to be the first to measure the speed of sound. At first Mersenne strongly rejected Galileo's views, partially due to errors in Galileo's reports of his results. But once Mersenne saw the significance of Galileo's conclusion, he became Galileo's strongest advocate, helping to spread the word (Palmerino 1999).

Consider the development of an important theorem of nature. Are data more like bread or wine? The answer depends on the data. Galileo's original experiments on pendulums and rolling masses down slopes were flawed by inaccurate data. This is likely because he didn't have good clocks. But he soon solved that problem and the data became more accurate. We don't know whether Mersenne repeated Galileo's experiments and then appreciated his theory, or whether he communicated with Galileo. But the final resolution was that the early data were like bread (it rots), but when the experimental method was improved with a better clock, the corrected data were like wine (it improves with age). Galileo claimed that the distance to reach

⁹The term *period* refers to the duration in units of time of a periodic function. For example, the periods of the Moon and the Sun are 28 days and 1 year, respectively.

1.2 Modern Mathematics 11

the ground is proportional to the square of the time. This expression is equivalent to $F = m_0 a$ assuming constant mass m_0 .

Mersenne was also a decent mathematician, inventing in 1644 the Mersenne prime (MP) π_m of the form

$$\pi_m = 2^{\pi_k} - 1,$$

where π_k (k < m) denotes the kth prime (see Sect. 2.1). As of December 2018, 51 MPs are known. The first MP is $3 = \pi_2 = 2^{\pi_1} - 1$, and the largest known prime is an MP, which is $\pi_{12251} = 2^{\pi_7} - 1$.

Newton: With the closure of Cambridge University due to the plague of 1665, Isaac Newton (1642–1726) returned home to Woolsthorpe-by-Colsterworth (95 miles north of London) to work by himself for over a year. ¹¹ It was during this solitary time that he did his most creative work.

Exploring our physiological senses requires a scientific understanding of the physical processes of vision and hearing, first considered by Newton, but researched later in much greater detail by Helmholtz (Stillwell 2010, p. 261). While Newton may be best known for his studies on light and gravity, he was the first to predict the speed of sound. However, his theory was in error by $\sqrt{c_p/c_v} = \sqrt{1.4} = 1.183.^{12}$ This famous issue would not be corrected for 129 years, awaiting the formulation of thermodynamics and the equipartition theorem by Laplace in 1816 (Britannica 2004).

Just 11 years prior to Newton's 1687 *Principia*, there was a basic understanding that sound and light traveled at very different speeds, due to the experiments of Ole Rømer (Feynman 1968, 2019, *Google for Feynman videos*).

Ole Rømer first demonstrated in 1676 that light travels at a finite speed (as opposed to instantaneously) by studying the apparent motion of Jupiter's moon Io. In 1865, James Clerk Maxwell proposed that light was an electromagnetic wave, and therefore traveled at the speed c_o appearing in his theory of electromagnetism. (Wikipedia: Speed of Light 2019)

The idea behind Rømer's discovery was that due to the large distance between Earth and Io, there was a difference between the period (phase) of the Moon when Jupiter was closest to Earth and when it was farthest from Earth. This difference in distance caused a delay or advance in the observed eclipse of Io as it went behind Jupiter, delayed by the difference in time due to the difference in distance. This is like watching a video of a clock's motion. When the video is delayed or slowed down, the time will be inaccurate (it will indicate an earlier time).

The amazing Bernoulli family: The first individual who seems to have openly recognized the importance of mathematics, enough to actually teach it, was Jacob Bernoulli (Fig. 1.4). Jacob worked on what is now viewed as the standard package

¹⁰https://mathworld.wolfram.com/MersennePrime.html.

¹¹Because the calendar was modified during Newton's lifetime, his birth date is no longer given as Christmas 1642 (Stillwell 2010, p. 175).

¹²The square root of the ratio of the specific heat capacity at constant pressure c_p to that at constant volume c_p .

12 1 Introduction









Fig. 1.4 Above left: Jacob (1655–1705) and right: Johann (1667–1748) Bernoulli, both painted by their portrait painter brother, Nicolaus. Below left: Leonhard Euler (1707–1783) and right: Jean le Rond d'Alembert (1717–1783). Euler was blind in his right eye, hence the left portrait view




Fig. 1.5 Timeline for the sixteenth through twentieth centuries covering Bombelli to Einstein. As noted in the caption for Fig. 1.2, it seems likely that Bombelli's discovery of Diophantus's book *Arithmetic* in the Vatican library triggered many of the ideas presented by Galileo, Descartes, and Fermat, followed by others (i.e., Newton). Thus Bombelli's discovery might be considered a magic moment in mathematics. The vertical red lines indicate mentor–student relationships. For orientation Mozart is indicated along the bottom and Napoleon at the top. Napoleon hired Fourier, Lagrange, and Laplace to help with his many bloody military campaigns. See Figs. 1.1, 1.2, and 3.1 for additional timelines

of analytic "circular" (i.e., periodic) functions: $\sin(x)$, $\cos(x)$, $\exp(x_J)$, $\log(x)$. Eventually the full details were developed (for real variables) by Euler (Sect. 3.2.5).

From Fig. 1.5 we may conclude that Jacob (1654–1705), the oldest brother, would have been strongly influenced by Newton. We newton would have been influenced by Fermat, Descartes, and Galileo, who died 1 year before Newton was born (White 1999).

Jacob Bernoulli, like all successful mathematicians of the day, was largely self-taught. Yet Jacob was in a new category of mathematicians because he was an effective teacher. Jacob taught his sibling Johann, who then taught his son Daniel. But most important, Johann taught Euler, the most prolific (thus influential) of all mathematicians, including Gauss. It is most significant that all four mathematicians published their methods and findings. Much later, Jacob studied with students of Descartes (Stillwell 2010, pp. 268–69).

Euler: Leonhard Euler's mathematical talent went far beyond that of the Bernoulli family (Burton 1985). Another special strength of Euler was his large number of publications. First he would master a topic, and then he would publish. Once the tools of mathematics were openly published, largely by Euler, mathematics grew exponentially.¹⁷ His papers continued to appear long after his death (Calinger 2015). It is also interesting that Euler was a contemporary of Mozart (see Fig. 1.5).

¹³The log and tan functions are related by Eq. 4.1.2.

¹⁴For a similar timeline see https://www.famousscientists.org/joseph-louis-lagrange/.

¹⁵https://www-history.mcs.st-andrews.ac.uk/Biographies/Newton.html.

¹⁶It seems clear that Descartes was also a teacher.

¹⁷There are at least three useful exponential scales: factors of 2, factors of $e \approx 2.7$, and factors of 10. The octave and decibel use factors of 2 (6 [dB]) and 10 (20 [dB]). Information theory uses factors of 2 (1 [bit]), 4 (2 [bits]). Circuit theory uses all three scales.

14 1 Introduction

D'Alembert: Another individual of that time who also published extensively was Jean la Rond d'Alembert (Fig. 1.4). Some of the most innovative ideas were first proposed by d'Alembert. Unfortunately, and perhaps somewhat unfairly, his rigor was criticized by Euler and later by Gauss (Stillwell 2010).

Gauss: Figures 1.2 and 1.4 show timelines of the most famous mathematicians. This was one of the most creative times in mathematics. Carl Friedrich Gauss was born at the end of Euler's long and productive life. I suspect that Gauss owed a great debt to Euler; surely he must have been a scholar of Euler. One of Gauss's most important achievements may have been his contribution to solving the open question about the density of prime numbers, and his use of least-squares.¹⁸

Cauchy: Augustin-Louis Cauchy (1789–1857) was the son of a well-to-do family but had the misfortune of being born during the time of of the French Revolution, which likely had its origins in the Seven Years' War, around 1756. Today the French still celebrate Bastille Day (July 14, 1789), which is viewed as a celebration of the revolution. The French Revolution left Cauchy with a lifelong scorn for French politics that deeply influenced his life. But Cauchy had an unmatched intellect for mathematics. His most obvious achievement was complex analysis, for which he proved many key theorems.

Helmholtz: Hermann von Helmholtz (1821–1894) was educated and experienced as a military surgeon. He also mastered classical music, acoustics, physiology, vision, hearing (Helmholtz 1863b), and, most important of all, mathematics. He was the first person to measure the speed of a neural spike in a patch of neuron, which he correctly found to be 27 [m/s]. Gustav Kirchhoff frequently expanded on Helmholtz's acoustic contributions. It is reported that Lord Rayleigh learned German so he could read Helmholtz's great works, which he amplified in his famous treatise on acoustics (Rayleigh 1896).

Helmholtz's studies and theories of music and perception of sound are fundamental scientific contributions (Helmholtz 1863a). His best known mathematical contribution is known as the fundamental theorem of vector calculus or simply "Helmholtz theorem" (Sect. 5.6.3).

Lord Kelvin: Lord Kelvin (William Thompson, 1824–1907) was one of the first true engineer-scientists, equally acknowledged as a mathematical physicist, well known for his interdisciplinary research, and knighted by Queen Victoria in 1866.¹⁹ Lord Kelvin coined the term *thermodynamics*, a science more fully developed by Maxwell (the same Maxwell of electrodynamics).²⁰

The history during this time is complex. For example, in 1850 Lord Kelvin wrote a letter to George Stokes, suggesting that Stokes try to prove what is today known as "Stokes's theorem." As a result, Stokes posted a reward (Smith's Prize), searching for a proof of "Lord Kelvin's theorem," which was finally achieved by Hermann

¹⁸https://www-history.mcs.st-andrews.ac.uk/Biographies/Gauss.html.

¹⁹Lord Kelvin was one of a half dozen interdisciplinary mathematical physicists, all working about the same time, who made a fundamental change in our scientific understanding. Others include Helmholtz, Stokes, Green, Heaviside, Rayleigh, and Maxwell.

²⁰Thermodynamics is another topic that warrants an analysis along historical lines Kuhn (1978).

Hankel (1839–1873).²¹ Many new concepts were being proved and appreciated over this productive period. Maxwell had published his famous equations, which were later reformatted in modern vector notation by Oliver Heaviside, J. Willard Gibbs, and Heinrich Hertz. Figure 1.5 should put to rest the myth that one's best work is done in the early years. Many of these scientists were fully productive in old age. Those who were not died early due to poor health or accidents.

James Clerk Maxwell (1831–1879) In 1869 a Cambridge senate committee was formed to create the Cambridge Physics Laboratory and "the founding of a special Professorship." The Chancellor of Cambridge was the seventh Duke of Devonshire and a distant relative of Henry Cavendish, his family name. Thus the new laboratory became known as the Cavendish.

There was, naturally, much speculation about the choice of the new Professor of Experimental Physics. [Lord] Kelvin was the most likely candidate, but on being approached in private, refused in order to stay in Glasgow. Another likely candidate was Lord Rayleigh, a brilliant mathematician and physicist who had left Cambridge to work in his private laboratory at his country seat in Essex. When the appointment was eventually announced, the reaction was, if anything, one of disappointment. The new Professor, James Clerk Maxwell, was relatively unknown.

He was a much respected mathematician, but he had not since made any great name for himself — his major and astounding books on Electricity and Kinetic Theory had yet to be published. Moreover, the six years before his appointment had been spent in isolation at his Scottish home.

His appointment was announced on March 8th 1871, and in spite of the initial disappointment, his inaugural lecture was looked forward to by his likely students as much as by the rest of the Cambridge scientists.

When, a few days later, Maxwell began his first course with a lecture on Heat, his students had the delight of seeing the lecture room packed with their tutors, lecturers, professors and all the important personages of the University. Thinking that this was his first public appearance they sat, in their formal academic dress, while Maxwell, "with a perceptible twinkle in his eye," gravely expounded the difference between Fahrenheit and Centigrade, and the principle of the air thermometer.

It was felt afterward that Maxwell had done it on purpose, perhaps out of modesty, perhaps out of his later well-known sense of humor, or perhaps because he knew of the still considerable opposition his new laboratory had to face. As he had written to his friend Lord Rayleigh, "if we succeed too well, and corrupt the minds of youth till they observe vibrations and deflections and become Senior Ops. instead of Wranglers, we may bring the whole University and all the parents about our ears.

However, Maxwell made only a casual announcement of his inaugural lecture which was not to be in the Senate House, as expected, but in an out-of-the-way lecture room. Consequently only his students got to hear of it and it was to them, rather than a general gathering, that he delivered an exciting and interesting lecture, mapping out his plans for the future of Cambridge physics. "²²

Lord Rayleigh (William Strutt): Lord Rayleigh (1842–1919) wrote a classic text (1896) that is widely read even today by those who study acoustics. In 1904 he received the Nobel Prize in Physics for his investigations of the densities of the most important gases and for his discovery of argon in connection with these studies.

²¹https://en.wikipedia.org/wiki/Hermann_Hankel.

²²https://www.phy.cam.ac.uk/history/years/firstten, Moralee (1995).

1 Introduction

1.2.2 Three Streams from the Pythagorean Theorem

From the outset of his presentation, Stillwell (2010, p. 1) defines "three great *streams* of mathematical thought: *Numbers, Geometry and Infinity*" that flow from the Pythagorean theorem, as summarized in Fig. 1.6. This is a useful concept, based on reasoning not as obvious as one might think. Many factors are in play here. One of these is the strongly held opinion of Pythagoras that all mathematics should be based on integers. The rest is tied up in the long, necessarily complex history of mathematics, as best summarized by the fundamental theorems (see Sect. 2.3.1), each of which is discussed in detail in a later chapter.

As shown in Fig. 1.6, Stillwell's concept of three streams, following from the Pythagorean theorem, is the organizing principle behind this book.

This chapter: The *Introduction* is a historical survey of pre-college mathematical physics, presented in terms of the three main Pythagorean streams (stream 1–stream 3), leading to the book's five chapters. Stream 3 is split into 3 A and 3B.

Chapter 2: *Number systems* presents some important ideas from number theory, starting with prime numbers, complex numbers, vectors, and matrices. Five classic number theory problems are discussed: the Euclidean algorithm (GCD), continued fractions (CFA), Euclid's formula, Pell's equation, and the Fibonacci difference equation. The general solution of these problems leads to the concept of the eigenfunction analysis, which is introduced in Sect. 2.6.2.

Chapter 3: *Algebraic equations* discusses Algebra and its development, as we know it today. The chapter presents the theory of real and complex equations and functions of real and complex variables. Newton's method for finding complex roots of polynomials, poles vs. zeros, and the Gauss–Lucas theorem (bounds on the root locations of the derivative of a polynomial). Complex impedance Z(s) of complex frequency $s = \sigma + \omega_J$ is covered with some care, developing the topic that is needed for engineering mathematics.

While the algebra of real and complex functions is identical, the calculus is fundamentally different. This leads to the concepts of complex analytic functions, complex

1. Numbers

- $\mathbb N$ counting numbers, $\mathbb Q$ rationals, $\mathbb P$ primes (6th century BCE)
- Z common integers, I irrationals (5th century BCE)
- $zero \in \mathbb{Z}$ (7th century CE)
- 2. Geometry (e.g., lines, circles, spheres, toroids, other shapes)
 - · Composition of polynomials (Descartes, Fermat),
 - Euclid's geometry and algebra ⇒ analytic geometry (17th century CE)
 - Fundamental theorem of algebra (18th century CE)

3. Infinity $(\infty \to sets)$

- Taylor series, functions, calculus (Newton, Leibniz) (17th and 18th century CE)
- R real, C complex (19th century CE)
- Set theory (20th century CE)

Fig. 1.6 Three streams that follow from the Pythagorean theorem: numbers, geometry, and infinity

2.2 Problems NS-1 31

2.2 Problems NS-1

2.2.1 Topic of This Homework

Introduction to MATLAB/Octave (see the MATLAB or Octave tutorial for help)
Deliverables: Report with charts and answers to questions. Hint: Use LATEX. 14

2.2.2 Plotting Complex Quantities in Octave/MATLAB

Problem #1 Consider the functions $f(s) = s^2 + 6s + 25$ and $g(s) = s^2 + 6s + 5$.

- -1.1: Find the zeros of functions f(s) and g(s) using the command roots ().
- -1.2: Show the roots of f(s) as red circles and of g(s) as blue plus signs. The x-axis should display the real part of each root, and the y-axis should display the imaginary part. Use hold on and grid on when plotting the roots.
- -1.3 Give your figure the title "Complex Roots of f(s) and g(s)." Label the x- and y-axes "Real Part" and "Imaginary Part." Hint: Use xlabel, ylabel, ylim([-10 10]), and xlim([-10 10]) to expand the axes.

Problem #2 Consider the function $h(t) = e^{j2\pi ft}$ for f = 5 and t = [0:0.01:2].

- -2.1: Use subplot to show the real and imaginary parts of h(t). Make two graphs in one figure. Label the x-axes "Time (s)" and the y-axes "Real Part" and "Imaginary Part."
- -2.2: Use subplot to plot the magnitude and phase parts of h(t). Use the command angle or unwrap (angle ()) to plot the phase. Label the x-axes "Time (s)" and the y-axes "Magnitude" and "Phase (radians)."

2.2.3 Prime Numbers, Infinity, and Special Functions in Octave/MATLAB

Problem #3 *Prime numbers, infinity, and special functions.*

- -3.1: Use the MATLAB/Octave function factor to find the prime factors of 123, 248, 1767, and 999,999.
- -3.2: Use the MATLAB/Octave function isprime to determine whether 2, 3, and 4 are prime numbers. What does the function isprime return when a number is prime or not prime? Why?

¹⁴ https://www.overleaf.com.

- -3.3: Use the MATLAB/Octave function primes to generate prime numbers between 1 and 10^6 . Save them in a vector x. Plot this result using the command hist(x).
- -3.4: Now try [n, bincenters] = hist(x). Use length(n) to find the number of bins.
- -3.5: Set the number of bins to 100 by using an extra input argument to the function hist. Show the resulting figure, give it a title, and label the axes. Hint: help hist and doc hist.

Problem #4 Inf, NaN, and logarithms in Octave/MATLAB.

- -4.1: Try 1/0 and 0/0 in the Octave/MATLAB command window. What are the results? What do these "numbers" mean in Octave/MATLAB?
- -4.2: Try $\log(0)$, $\log(10)$, and $\log(2)$ in the command window.] In MATLAB/Octave, the natural logarithm $\ln(\cdot)$ is computed using the function $\log(1)$. Functions $\log(1)$ and $\log(2)$ are computed using $\log(1)$ and $\log(2)$.
- -4.3: Try $\log(1)$ in the command window. What do you expect for $\log(1)$ and $\log(2)$?
- -4.4: Try $\log(-1)$ in the command window. What do you expect for $\log(10)$ and $\log(2)$
- -4.5: Explain how MATLAB/Octave arrives at the answer in problem 4.4. Hint: $-1 = e^{i\pi}$.
- -4.6: Try log(exp(j*sqrt(pi))) (i.e., log $e^{J\sqrt{\pi}}$) in the command window. What do you expect?
 - -4.7: What does inverse mean in this context? What is the inverse of $\ln f(x)$?
 - -4.8: What is a decibel? (Look up decibels on the Internet.)

Problem #5 Very large primes on Intel computers. Find the largest prime number that can be stored on an Intel 64-bit computer, which we call \mathfrak{B}_{max} . Hint: As explained in the MATLAB/Octave command $help\ flintmax$, the largest positive integer is 2^{53} ; however, the largest integer that can be factored is $2^{32}=2^{54}-6$. Explain the logic of your answer. Hint: $help\ isprime()$.

Problem #6 We are interested in primes that are greater than \mathbb{B}_{\max} . How can you find them on an Intel computer (i.e., one using IEEE floating point)? Hint: Consider a sieve that contains only odd numbers, starting from 3 (not 2). Since every prime number greater than 2 is odd, there is no reason to check the even numbers. $n_{odd} \in \mathbb{N}/2$ contain all the primes other than 2.

Problem #7 *The following identity is interesting. Can you find a proof?*

2.2 Problems NS-1 33

$$1 = 1^{2}$$

$$1 + 3 = 2^{2}$$

$$1 + 3 + 5 = 3^{2}$$

$$1 + 3 + 5 + 7 = 4^{2}$$

$$1 + 3 + 5 + 7 + 9 = 5^{2}$$

$$\vdots$$

$$\sum_{n=0}^{N-1} 2n + 1 = N^{2}.$$

2.3 The Role of Physics in Mathematics

Integers arose naturally in art, music, and science. Examples include the relationships between musical notes, the natural eigenmodes (tones) of strings, and other musical instruments. These relationships were so common that Pythagoras believed that to explain the physical world (the universe), one needed to understand integers. As discussed on Sect. 1.1, "all is number" was a seductive song.

As we will discuss on Sect. 3.1, it is best to view the relationships among acoustics, music, and mathematics as historical, since these topics inspired the development of mathematics. Today integers play a key role in quantum mechanics, again based on eigenmodes, but in this case, eigenmodes follow from solutions of the Schrödinger equation, with the roots of the characteristic equation being purely imaginary numbers $\in \mathbb{N}$. If there were a real part (i.e., damping), the modes would not be integers.

As discussed by Vincent Salmon (1946, p. 201), Schrödinger's equation follows directly from the Webster horn equation. While Philip Morse (1948, p. 281) (a student of Arnold Sommerfeld) fails to make the direct link, he comes close to the same view when he shows that the real part of the horn resistance goes exactly to zero below a cutoff frequency. He also discusses the trapped modes inside musical instruments created by the horn flare. One may assume Morse read Salmon's paper on horns, since he cites Salmon (Morse 1948, footnote 1, p. 271).

Engineers are so accustomed to working with real (vs. complex) numbers that they rarely acknowledge the distinction between real (i.e., irrational) and fractional numbers. Integers arise in many contexts. One cannot master computer programming without understanding integer, hexadecimal, octal, and binary representations, since all numbers in a computer are represented in numerical computations in terms of rationals ($\mathbb{Q} = \mathbb{Z} \cup \mathbb{F}$).

The primary reason integers are so important is their absolute precision. Every integer $n \in \mathbb{Z}$ is unique¹⁵ and has the indexing property, which is essential for making lists that are ordered, so that one can quickly look things up. The alphabet also has this property (e.g., a book's index).

Because of the integer's absolute precision, the digital computer quickly overtook the analog computer once it was practical to make logic circuits that were fast. From 1946 the first digital computer was thought to be the University of Pennsylvania's ENIAC. We now know that the code-breaking effort in Bletchley Park, England, under the guidance of Alan Turing, created the first digital computer (the Colossus), which was used to break the World War II German Enigma code. Due to the high secrecy of this war effort, the credit was acknowledged only in the 1970s when the project was finally declassified.

There is zero possibility of analog computing displacing digital computing because of the importance of precision (and speed). But even with binary representation, there is a nonzero probability of error—for example, on a hard-drive—due to physical noise. To deal with this, error-correcting codes have been developed, reducing the error by many orders of magnitude. Today error correction is a science, and billions of dollars are invested to increase the density of bits per area to increasingly larger factors. A few years ago the terabyte drive was unheard of; today it is standard. In a few years petabyte drives will certainly become available. It is hard to comprehend how these will be used by individuals, yet they are essential for online (cloud) computing.

2.3.1 The Three Streams of Mathematics

Modern mathematics is built on a hierarchical construct of fundamental theorems, as summarized in the following boxed material on this section. The importance of such theorems cannot be overemphasized.

Gauss's and Stokes's laws play a major role in understanding and manipulating Maxwell's equations. Every engineering student needs to fully appreciate the significance of these key theorems. If necessary, memorize them. But memorization will not do over the long run, as each and every theorem must be fully understood. Fortunately most students already know several of these theorems, but perhaps not by name. In such cases, it is a matter of mastering the vocabulary.

¹⁵Check out the history of $1729 = 1^3 + 12^3 = 9^3 + 10^3$.

is exponentially tightened. The results of this calculation are shown in Fig. 2.2. For reference, when k = 9, 592, $\pi_k = 99$, 991, $\pi_{k-1} = 99$, 989, $\pi_{k+1} = 100$, 003, thus $P(k+1)/P(k-1) - 1 = 1.4 \times 10^{-4}$.

2.3.3 Stream 2: Fundamental Theorem of Algebra

This theorem states that every polynomial in x of degree N,

$$P_N(x) = \sum_{k=0}^{N} a_k x^k,$$
 (2.3.1)

has at least one root (see Sect. 3.4). When a common root is factored out, the degree of the polynomial is reduced by 1. Applied recursively, a polynomial of degree N has N roots. Note there are N+1 coefficients (i.e., $[a_N, a_{N-1}, \ldots, a_0]$). If we are interested only in the roots of $P_N(x)$, it is best to define $a_N=1$, which defines the monic polynomial. If the roots are fractional numbers ($\in \mathbb{F}$), this might be possible. However, when the roots are irrational numbers (likely), a perfect factorization is at least unlikely, if not impossible.

2.3.4 Stream 3: Fundamental Theorems of Calculus

In Sects. 5.6 and 5.6.6 we will deal with each of the theorems for Stream 3. We consider the several fundamental theorems of integration, starting with Leibniz's formula for integration on the real line (\mathbb{R}), then progressing to complex integration in the complex plane (\mathbb{C}) (Cauchy's theorem), which is required for computing the inverse Laplace transform. Gauss's and Stokes's laws for \mathbb{R}^2 require closed and open surfaces, respectively. One cannot manipulate Maxwell's equations, fluid flow, or acoustics without understanding these theorems. Any problem that deals with the wave equation in more than one dimension requires an understanding of these theorems. They are the basis of the derivation of the Kirchhoff voltage and current laws, as first proposed by Newton for mechanics and acoustics.

Finally we define three vector operations based on the gradient operator,

$$\nabla \equiv \hat{\mathbf{x}} \frac{\partial}{\partial x} + \hat{\mathbf{y}} \frac{\partial}{\partial y} + \hat{\mathbf{z}} \frac{\partial}{\partial z}, \qquad (2.3.2)$$

pronounced "del" (preferred) or "nabla," which are the gradient $\nabla()$, divergence $\nabla \cdot ()$, and curl $\nabla \times ()$.

Second-order operators such as the scalar Laplacian $\nabla \cdot \nabla () = \nabla^2 ()$, the divergence of the gradient (**DoG**), may be constructed from first-order operators. The

most important of these is the vector Laplacian ∇^2 (), the gradient of the divergence (**gOd**) which is required when working with Maxwell's wave equations. ¹⁶

The first three operations are defined in terms of integral operations on a surface in one, two, or three dimensions by taking the limit as that surface, or the volume contained within, goes to zero. These three differential operators are essential to fully understand Maxwell's equations, the crown jewel of mathematical physics. Hence mathematics plays a key role in physics, as does physics in math.

2.3.5 Other Key Mathematical Theorems

In addition to the widely recognized fundamental theorems, there are a number of equally important theorems that have not yet been labeled "fundamental." ¹⁷

The widely recognized Cauchy integral theorem is an excellent example, since it is a steppingstone to Green's theorem and the fundamental theorem of complex calculus. In Sect. 4.5 we clarify the contributions of each of these special theorems.

Once these fundamental theorems of integration (Stream 3) have been mastered, the student is ready for the complex frequency domain, which takes us back to Stream 2 and the complex frequency plane ($s = \sigma + \omega j \in \mathbb{C}$). While the Fourier and Laplace transforms are taught in mathematics courses, the concept of complex frequency is rarely mentioned. The complex frequency domain (see Sect. 3.10) and causality are fundamentally related (see Sects. 4.5.2–4.7.3), and are critical for the analysis of signals and systems, especially when dealing with the concept of impedance (see Sect. 4.4).

Without the concept of time and frequency, we cannot develop an intuition for the Fourier and Laplace transforms, especially within the context of engineering and mathematical physics. The Fourier transform covers signals, while the Laplace transform LT describes systems. Separating these two concepts, based on their representations as Fourier and Laplace transforms, is an important starting place for understanding physics and the role of mathematics. However, these methods, by themselves, do not provide the insight into physical systems that we need to be productive or, better, creative with these tools. We need to master the tools of differential equations and then partial differential equations to fully appreciate the world that they describe. Electrical networks composed of inductors, capacitors, and resistors are isomorphic to mechanical systems composed of masses, springs, and dashpots. Newton's laws are analogous to those of Kirchhoff, which are the rules needed to analyze simple physical systems composed of linear (and nonlinear) subcomponents. When lumped-element systems are taken to the limit in several dimensions, we obtain Maxwell's partial differential equations, the laws of continuum mechanics, and beyond.

¹⁶See Sect. 5.6.6 for the definitions of **DoG** and **gOd**.

¹⁷It is not clear what it takes to reach this more official sounding category.

2.6 Number Theory Applications

2.6.1 Pythagorean Triplets (Euclid's Formula)

Euclid's formula is a method for finding three integer lengths $[a, b, c] \in \mathbb{N}$ that satisfy Eq. 1.1. It is important to ask Which set are the lengths [a, b, c] drawn from? There is a huge difference, both practical and theoretical, whether they are from the real numbers \mathbb{R} or from the counting numbers \mathbb{N} . Given $p, q \in \mathbb{N}$ with p > q, the three lengths $[a, b, c] \in \mathbb{N}$ of Eq. 1.1 are given by

$$a = p^2 - q^2$$
, $b = 2pq$, $c = p^2 + q^2$. (2.6.6)

This result may be directly verified, since

$$[p^2 + q^2]^2 = [p^2 - q^2]^2 + [2pq]^2$$

or

$$p^4 + q^4 + 2p^2q^2 = p^4 + q^4 - 2p^2q^2 + 4p^2q^2$$
.

Thus, Eqs. 2.6.6 are easily proved once given. Deriving Euclid's formula (see AE-2, problem #1) is obviously much more difficult and is similar to the proof of Pell's equation as shown in Table 2.1.

A well-known example is the right triangle depicted in Fig. 2.7, defined by the integer lengths [3, 4, 5] that have angles [0.54, 0.65, $\pi/2$] [rad], which satisfies Eq. 1.1. As quantified by Euclid's formula (Eq. 2.6.6), there are an infinite number of Pythagorean triplets (PTs). Furthermore, the seemingly simple triangle that has angles of [30, 60, 90] $\in N$ [deg] (i.e., $[\pi/6, \pi/3, \pi/2] \in \mathbb{I}$ [rad]) has one irrational (\mathbb{I}) length ($[1, \sqrt{3}, 2]$).

The set from which the lengths [a, b, c] are drawn was not missed by the early Asians and was documented by the Greeks. Any equation whose solution is based on integers is called a *Diophantine equation*, named for the Greek mathematician Diophantus of Alexandria (ca. 250 CE) (see Fig. 1.1).

Table 2.1 Table of Pythagorean triplets computed from Euclid's formula, Eq. 2.6.6, for various [p,q]. The last three columns are the first, fourth, and penultimate values of Plimpton-322, along with their corresponding [p,q]. In all cases $c^2 = a^2 + b^2$ and p = q + l, where $l = \sqrt{c - b} \in \mathbb{N}$

		1	0 11 7 1						1 ' ' '		•	
q	1	1	1	2	2	2	3	3	3	5	54	27
1	1	2	3	1	2	3	1	2	3	7	71	23
p	2	3	4	3	4	5	4	5	6	12	125	50
a	3	8	15	5	12	21	7	16	27	119	12709	1771
b	4	6	8	12	16	20	24	30	36	120	13500	2700
c	5	10	17	13	20	29	25	34	45	169	18541	3229




Fig. 2.7 Beads on a string form perfect right triangles when the number of unit lengths between beads on each side satisfies Eq. 1.1. For example, when p = 2, q = 1, the sides are [3, 4, 5]

A clay tablet from the nineteenth century BCE with the numbers engraved on it, as shown in Fig. 2.8, was discovered in Mesopotamia, and cataloged in 1922 by George A. Plimpton. These numbers are a and c pairs from PTs [a, b, c]. Given this discovery, it is clear that the Pythagoreans were following those who came long before them. Recently a second tablet, dating between 350 and 50 BCE, has been reported, that indicates calculations of the apparent motion of Jupiter based on a trapezoidal graph of the rate. 23

It is of interest that PTs play a role on atomic physics, as discussed in Appendix I.

2.6.2 Pell's Equation

Pell's equation,

$$x_n^2 - Ny_n^2 = (x_n - \sqrt{N}y_n)(x_n + \sqrt{N}y_n) = 1,$$
 (2.6.7)

with non-square $N \in \mathbb{N}$ specified and $x, y \in \mathbb{N}$ unknown, has a venerable history in both physics (see Sect. 2.1) and mathematics. Given its factored form, it is obvious that every solution x_n, y_n has the asymptotic property

$$\frac{x_n}{y_n}\Big|_{n\to\infty} \to \pm \sqrt{N}.$$
 (2.6.8)

It is believed that Pell's equation is directly related to the Pythagorean theorem, since both are simple binomials that have integer coefficients (Stillwell 2010, p. 48), with Pell's equation being the hyperbolic version of Eq. 1.1. For example, with N = 2, a solution is x = 17, y = 12 (i.e., $17^2 - 2 \cdot 12^2 = 1$).

²²https://www.nytimes.com/2010/11/27/arts/design/27tablets.html.

 $^{^{23} \}rm https://www.nytimes.com/2016/01/29/science/babylonians-clay-tablets-geometry-astronomy-jupiter.html.$

a	c
119	169
3367	4825
4601	6649
12709	18541
65	97
319	481
2291	3541
799	1249
481	769
4961	8161
45	75
1679	2929
161	289
1771	3229
56	106

Fig. 2.8 Plimpton-322, a clay tablet from 1800 BCE that displays a and c values of the Pythagorean triplets [a, b, c], with the property $b = \sqrt{c^2 - a^2} \in \mathbb{N}$. Several of the c values are primes, but not the a values. The clay is item 322 (item 3 from 1922) from the collection of George A. Plimpton

A 2 \times 2 matrix recursion algorithm, likely due to the Chinese and used by the Pythagoreans to investigate \sqrt{N} , is

$$\begin{bmatrix} x \\ y \end{bmatrix}_{n+1} = \begin{bmatrix} 1 & N \\ 1 & 1 \end{bmatrix} \begin{bmatrix} x \\ y \end{bmatrix}_{n}, \tag{2.6.9}$$

where we indicate the index outside the vectors.

Starting with the trivial solution $[x_o, y_o]^T = [1, 0]^T$ (i.e., $x_o^2 - Ny_o^2 = 1$), additional solutions of Pell's equations are determined, having the property $\mathbf{x}_n/y_n \to \sqrt{N} \in \mathbb{F}$, motivated by Euclid's formula for Pythagorean triplets (Stillwell 2010, p. 44).

Note that Eq. 2.6.9 is a 2×2 linear matrix composition method (see Sect. 3.4.2), since the output of one matrix multiplication is the input to the next.

Asian solutions: The first solution of Pell's equation was published in about 628 CE by Brahmagupta, who first discovered the equation (Stillwell 2010, p. 46). Brahmagupta's novel solution also used the composition method, but in a different way from Eq. 2.6.9. Then in 1150 CE, Bhaskara II independently obtained solutions using Eq. 2.6.9 (Stillwell 2010, p.69). This is the composition method we shall explore here, as summarized in Appendix B, Table B.1.

The best way to see how this recursion results in solutions to Pell's equation is by example. Initializing the recursion with the trivial solution $[x_0, y_0]^T = [1, 0]^T$ gives

$$\begin{bmatrix} x_1 \\ y_1 \end{bmatrix} = \begin{bmatrix} 1 \\ 1 \end{bmatrix}_1 = \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 1 \\ 0 \end{bmatrix}_0$$

$$1^2 - 2 \cdot 1^2 = -1$$

$$\begin{bmatrix} x \\ y \end{bmatrix}_2 = \begin{bmatrix} 3 \\ 2 \end{bmatrix} = \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 1 \\ 1 \end{bmatrix}_1$$

$$3^2 - 2 \cdot 2^2 = 1$$

$$\begin{bmatrix} x \\ y \end{bmatrix}_3 = \begin{bmatrix} 7 \\ 5 \end{bmatrix} = \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 3 \\ 2 \end{bmatrix}_2$$

$$(7)^2 - 2 \cdot (5)^2 = -1$$

$$\begin{bmatrix} x \\ y \end{bmatrix}_4 = \begin{bmatrix} 17 \\ 12 \end{bmatrix} = \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 7 \\ 5 \end{bmatrix}_3$$

$$17^2 - 2 \cdot 12^2 = 1$$

$$\begin{bmatrix} x \\ y \end{bmatrix}_5 = \begin{bmatrix} 41 \\ 29 \end{bmatrix} = \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 17 \\ 12 \end{bmatrix}_4$$

$$(41)^2 - 2 \cdot (29)^2 = -1.$$

Thus the recursion results in a modified version of Pell's equation,

$$x_n^2 - 2y_n^2 = (-1)^n,$$
 (2.6.10)

where only even values of n are solutions. This sign change had no effect on the Pythagoreans' goal, since they cared about only the ratio $y_n/x_n \to \pm \sqrt{2}$.

Modified recursion: We may restore the solution of Pell's equation for N=2 using a slightly modified linear matrix recursion. To fix the $(-1)^n$ problem, we multiply the 2×2 matrix by $1j = \sqrt{-1}$, which gives

$$\begin{bmatrix} x \\ y \end{bmatrix}_{1} = J \begin{bmatrix} 1 \\ 1 \end{bmatrix}_{1} = J \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 1 \\ 0 \end{bmatrix}_{0}$$

$$J^{2} - 2 \cdot J^{2} = 1$$

$$\begin{bmatrix} x \\ y \end{bmatrix}_{2} = J^{2} \begin{bmatrix} 3 \\ 2 \end{bmatrix}_{2} = J \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} J \begin{bmatrix} 1 \\ 1 \end{bmatrix}_{1}$$

$$3^{2} - 2 \cdot 2^{2} = 1$$

$$\begin{bmatrix} x \\ y \end{bmatrix}_{3} = J^{3} \begin{bmatrix} 7 \\ 5 \end{bmatrix}_{3} = J \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} J^{2} \begin{bmatrix} 3 \\ 2 \end{bmatrix}_{2}$$

$$(7J)^{2} - 2 \cdot (5J)^{2} = 1$$

$$\begin{bmatrix} x \\ y \end{bmatrix}_{4} = \begin{bmatrix} 17 \\ 12 \end{bmatrix}_{4} = J \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} J^{3} \begin{bmatrix} 7 \\ 5 \end{bmatrix}_{3}$$

$$17^{2} - 2 \cdot 12^{2} = 1$$

$$\begin{bmatrix} x \\ y \end{bmatrix}_{5} = J \begin{bmatrix} 41 \\ 29 \end{bmatrix}_{5} = J \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 17 \\ 12 \end{bmatrix}_{4}$$

$$(41J)^{2} - 2 \cdot (29J)^{2} = 1.$$

Solution to Pell's equation: By multiplying the matrix by 1_J , all the solutions ($x_k \in \mathbb{C}$) to Pell's equation are determined. The 1_J factor corrects the alternation in sign, so every iteration yields a solution. For N = 2, n = 0 (the initial solution), $[x_0, y_0]$ is $[1, 0]_0$, $[x_1, y_1] = J[1, 1]_1$, and $[x_2, y_2] = -[3, 2]_2$. These are easily checked using this recursion.

The solution for N=3 is given in Appendix B.2.2. Table B.1 shows that every output of this slightly modified matrix recursion gives solutions to Pell's equation: $[1,0], [1,1], [4,2], [10,6], \ldots, [76,44], \ldots$

At each iteration, the ratio x_n/y_n approaches $\sqrt{2}$ with increasing accuracy, coupling it to the CFA, which may also be used to find approximations to \sqrt{N} . The value of $41/29 \approx \sqrt{2}$, with a relative error of <0.03%.

2.6.3 Fibonacci Sequence

Another classic problem, also formulated by the Chinese, is the Fibonacci sequence, generated by the relationship

$$f_{n+1} = f_n + f_{n-1}. (2.6.11)$$

Here the next number $f_{n+1} \in \mathbb{N}$ is the sum of the previous two. If we start from [0, 1], this linear recursion equation leads to the Fibonacci sequence $f_n = [0, 1, 1, 2, 3, 5, 8, 13, 21, 34, \ldots]$. Alternatively, if we define $y_{n+1} = x_n$, then Eq. 2.6.11 may be compactly represented by a 2×2 companion matrix recursion (see the Fibonacci exercises in NS-3).

$$\begin{bmatrix} x \\ y \end{bmatrix}_{n+1} = \begin{bmatrix} 1 & 1 \\ 1 & 0 \end{bmatrix} \begin{bmatrix} x \\ y \end{bmatrix}_n, \tag{2.6.12}$$

which has eigenvalues $(1 \pm \sqrt{5})/2$.

The correspondence of Eqs. 2.6.11 and 2.6.12 is easily verified. Starting with $[x, y]_0^T = [0, 1]^T$, we obtain for the first few steps:

$$\begin{bmatrix}1\\0\end{bmatrix}_1 = \begin{bmatrix}1&1\\1&0\end{bmatrix}\begin{bmatrix}0\\1\end{bmatrix}_0, \quad \begin{bmatrix}1\\1\end{bmatrix}_2 = \begin{bmatrix}1&1\\1&0\end{bmatrix}\begin{bmatrix}1\\0\end{bmatrix}_1, \quad \begin{bmatrix}2\\1\end{bmatrix}_3 = \begin{bmatrix}1&1\\1&0\end{bmatrix}\begin{bmatrix}1\\1\end{bmatrix}_2, \quad \begin{bmatrix}3\\2\end{bmatrix}_4 = \begin{bmatrix}1&1\\1&0\end{bmatrix}\begin{bmatrix}2\\1\end{bmatrix}_3, \quad \dots$$

From the above, $x_n = [0, 1, 1, 2, 3, 5, ...]$ is the Fibonacci sequence, since the next x_n is the sum of the previous two, and the next y_n is x_n , as shown in Fig. 2.9.




Fig. 2.9 A construction called the Fibonacci spiral. Note how it is constructed of squares that have areas given by the squares of the Fibonacci numbers. In this way, the spiral is smooth and the radius increases as the Fibonacci numbers (e.g., 8 = 3 + 5, 13 = 5 + 8, etc.) (Adapted from https://en. wikipedia.org/wiki/Golden_spiral)

Exercise #24 Use the Octave/MATLAB command compan(c) to find the companion matrix of the polynomial coefficients defined by Eq. 2.6.11.

Sol: Using MATLAB/Octave: f = [1, -1, -1]; C = compan(f);

$$C = \begin{bmatrix} 1 & 1 \\ 1 & 0 \end{bmatrix} \tag{2.6.13}$$

Exercise #25 Find the eigenvalues of matrix C.

Sol: The characteristic equation is

$$\det\begin{bmatrix} 1 - \lambda & 1 \\ 1 & -\lambda \end{bmatrix} = 0$$

or
$$\lambda^2 - \lambda - 1 = (\lambda - 1/2)^2 - 1/4 - 1 = 0$$
, which has roots $\lambda_{\pm} = (1 \pm \sqrt{5})/2 \approx \{1.618, -0.618\}$.

The mean-Fibonacci sequence: Suppose that the Fibonacci sequence recursion is replaced by the mean of the last two values—namely, let

$$f_{n+1} = \frac{f_n + f_{n-1}}{2}. (2.6.14)$$

This seems like a small change. But how does the solution differ? To answer this question it is helpful to look at the corresponding 2×2 matrix.

Exercise #26 Find the 2×2 matrix corresponding to Eq. 2.6.14. The 2×2 matrix may be found using the *companion matrix* method (see Sect. 3.1.3).

Sol: Using MATLAB/Octave code, we have

$$f = [1, -1/2, -1/2];$$

C=compan(f);

which returns

$$C = \frac{1}{2} \begin{bmatrix} 1 & 1 \\ 2 & 0 \end{bmatrix}. \tag{2.6.15}$$

Exercise #27 Find the steady-state solution for the mean-Fibonacci, starting from $[1, 0]_0$. State the nature of both solutions.

Sol: By inspection one steady-state solution is $[1, 1]_{\infty}^{T}$ or $f_n = 1$. To find the full solution, we need to find the two eigenvalues, defined by

$$\det \begin{bmatrix} 1/2 - \lambda & 1/2 \\ 1 & -\lambda \end{bmatrix} = \lambda^2 - \lambda/2 - 1/2 = (\lambda - 1/4)^2 - (1/4)^2 - 1/2 = 0.$$

Thus $\lambda_{\pm} = (1 \pm 3)/4 = [1, -0.5]$. The first solution converges to 1 while the second solution is $(-1/2)^n$, which changes sign at each time step and quickly converges to zero. The full solution is given by $E\Lambda^n E^{-1}[1, 0]^T$ (see Appendix B).

Relationships to digital signal processing: Today we recognize Eq. 2.6.11 as a discrete difference equation, which is a pre-limit (pre–Stream 3) recursive form of a differential equation. The 2×2 matrix form of Eq. 2.6.11 is an early precursor to seventeenth- and eighteenth-century developments in linear algebra. Thus the Greeks' recursive solution for the $\sqrt{2}$ and Bhaskara's solution of Pell's equation are early precursors to discrete-time signal processing as well as to calculus.

There are strong similarities between Pell's equation and the Pythagorean theorem. As we shall see, Pell's equation is related to the geometry of a hyperbola, just as the Pythagorean equation is related to the geometry of a circle. We shall show, as one might assume, that there is a counterpart to Euclid's formula for the case of Pell's equations, since these are all conic sections with closely related conic geometry. As we have seen, the solutions involve $\sqrt{-1}$. The derivation is a trivial extension of that for Euclid's formula for Pythagorean triplets. The early solution of Brahmagupta was not related to this simple formula.

2.6.4 Diagonalization of a Matrix (Eigenvalue/Eigenvector Decomposition)

As derived in Appendix B, the most efficient way to compute A^n is to diagonalize the matrix A by finding its eigenvalues and eigenvectors.

The eigenvalues λ_k and eigenvectors \vec{e}_k of a square matrix A are related by

$$A\vec{e}_k = \lambda_k \vec{e}_k, \tag{2.6.16}$$

such that multiplying an eigenvector \vec{e}_k of A by the matrix A is the same as multiplying by a scalar, $\lambda_k \in \mathbb{C}$ (the corresponding eigenvalue). The complete eigenvalue problem may be written as

$$AE = E\Lambda$$
.

If A is a 2×2 matrix,²⁴ the matrices E and Λ (of eigenvectors and eigenvalues, respectively) are

$$E = \begin{bmatrix} \vec{e}_1 & \vec{e}_2 \end{bmatrix}$$
 and $\Lambda = \begin{bmatrix} \lambda_1 & 0 \\ 0 & \lambda_2 \end{bmatrix}$.

Thus the matrix equation $AE = [A\vec{e}_1 \ A\vec{e}_2] = [\lambda_1\vec{e}_1 \ \lambda_2\vec{e}_2] = E\Lambda$ contains Eq. 2.6.16 for each eigenvalue–eigenvector pair.

²⁴These concepts may be easily extended to higher dimensions.

2.8 Pell's Equation 63

The diagonalization of the matrix A refers to the fact that the matrix of eigenvalues, Λ , has nonzero elements only on the diagonal. The key result is found by post-multiplication of the eigenvalue matrix by E^{-1} , giving

$$AEE^{-1} = A = E\Lambda E^{-1}. (2.6.17)$$

If we now take powers of A, the nth power of A is

$$A^{n} = (E\Lambda E^{-1})^{n}$$

$$= E\Lambda E^{-1}E\Lambda E^{-1} \cdots E\Lambda E^{-1}$$

$$= E\Lambda^{n}E^{-1}.$$
(2.6.18)

This is a very powerful result because the *n*th power of a diagonal matrix is extremely easy to calculate:

$$\Lambda^n = \begin{bmatrix} \lambda_1^n & 0 \\ 0 & \lambda_2^n \end{bmatrix}.$$

Thus, from Eq. 2.6.18 we can calculate A^n using only two matrix multiplications:

$$A^n = E \Lambda^n E^{-1}$$
.

2.6.5 Finding the Eigenvalues

The eigenvalues λ_k are determined from Eq. 2.6.16, by factoring out \vec{e}_k :

$$A\vec{e}_k = \lambda_k \vec{e}$$
$$(A - \lambda_k I)\vec{e}_k = \vec{0}.$$

Matrix $I = [1, 0; 0, 1]^T$ is the identity matrix, having the dimensions of A, with elements δ_{ij} (i.e., diagonal elements $\delta_{11,22} = 1$ and off-diagonal elements $\delta_{12,21} = 0$).

The vector \vec{e}_k is not zero, yet when operated on by $A - \lambda_k I$, the result must be zero. The only way this can happen is if the operator is degenerate (has no solution)—that is,

$$\det(A - \lambda I) = \det \begin{bmatrix} (a_{11} - \lambda) & a_{12} \\ a_{21} & (a_{22} - \lambda) \end{bmatrix} = 0.$$
 (2.6.19)

This means that the two equations have the same roots (the equation is degenerate). This determinant equation results in a second-degree polynomial in λ :

$$(a_{11} - \lambda)(a_{22} - \lambda) - a_{12}a_{21} = 0,$$

the roots of which are the eigenvalues of the matrix A.

2.6.6 Finding the Eigenvectors

An eigenvector \vec{e}_k can be found for each eigenvalue λ_k from Eq. 2.6.16,

$$(A - \lambda_k I)\vec{e}_k = \vec{0}.$$

The left side of the above equation becomes a column-vector, where each element is an equation in the elements of \vec{e}_k , set equal to 0 on the right side. These equations are always degenerate, since the determinant is zero. Thus the two equations have the same slope.

Solving for the eigenvectors is often confusing because they have arbitrary magnitudes, $||\vec{e}_k|| = \sqrt{\vec{e}_k \cdot \vec{e}_k} = \sqrt{e_{k,1}^2 + e_{k,2}^2} = d$. From Eq. 2.6.16, we can determine only the relative magnitudes and signs of the elements of \vec{e}_k , so we have to choose a magnitude d. It is common practice to normalize each eigenvector to have unit magnitude (d = 1).

2.7 Problems NS-3

2.7.1 Topic of This Homework

Pythagorean triplets, Pell's equation, Fibonacci sequence.

2.7.2 Pythagorean Triplets

Problem #1 Euclid's formula for the Pythagorean triplets a, b, c is $a = p^2 - q^2$, b = 2pq, and $c = p^2 + q^2$.

- -1.1: What condition(s) must hold for p and q such that a, b, and c are always positive and nonzero?
 - -1.2: Solve for p and q in terms of a, b, and c.

Problem #2 The ancient Babylonians (ca. 2000 BCE) cryptically recorded (a, c) pairs of numbers on a clay tablet, archeologically denoted Plimpton-322 (see 2.8).

-2.1: Find p and q for the first five pairs of a and c shown here from Plimpton-322.

а	С
119	169
3367	4825
4601	6649
12709	18541
65	97

Find a formula for a in terms of p and q.

- -2.2: Based on Euclid's formula, show that c > (a, b).
- -2.3: What happens when c = a?
- -2.4: Is b + c a perfect square? Discuss.

2.7.3 Pell's Equation

Problem #3 Pell's equation is one of the most historic (i.e., important) equations of Greek number theory because it was used to show that $\sqrt{2} \in \mathbb{L}$. We seek integer solutions of

$$x^2 - Ny^2 = 1.$$

As shown on Sect. 2.6.2, the solutions x_n , y_n for the case of N=2 are given by the linear 2×2 matrix recursion

$$\begin{bmatrix} x_{n+1} \\ y_{n+1} \end{bmatrix} = 1j \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} x_n \\ y_n \end{bmatrix}$$

with $[x_0, y_0]^T = [1, 0]^T$ and $1_J = \sqrt{-1} = e^{j\pi/2}$. It follows that the general solution to Pell's equation for N = 2 is

$$\begin{bmatrix} x_n \\ y_n \end{bmatrix} = (e^{J\pi/2})^n \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix}^n \begin{bmatrix} x_0 \\ y_0 \end{bmatrix}.$$

To calculate solutions to Pell's equation using the matrix equation above, we must calculate

$$A^{n} = e^{J\pi n/2} \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix}^{n} = e^{J\pi n/2} \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} \cdots \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix},$$

which becomes tedious for n > 2.

- -3.1: Find the companion matrix and thus the matrix A that has the same eigenvalues as Pell's equation. Hint: Use MATLAB'S function [E, Lambda] = eig(A) to check your results!
- -3.2: Solutions to Pell's equation were used by the Pythagoreans to explore the value of $\sqrt{2}$. Explain why Pell's equation is relevant to $\sqrt{2}$.
- -3.3: Find the first three values of $(x_n, y_n)^T$ by hand and show that they satisfy Pell's equation for N = 2.

By hand, find the eigenvalues λ_{\pm} of the 2 × 2 Pell's equation matrix

$$A = \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix}.$$

-3.4: By hand, show that the matrix of eigenvectors, E, is

$$E = \begin{bmatrix} \vec{e}_+ \ \vec{e}_- \end{bmatrix} = \frac{1}{\sqrt{3}} \begin{bmatrix} -\sqrt{2} \ \sqrt{2} \\ 1 \ 1 \end{bmatrix}.$$

-3.5: Using the eigenvalues and eigenvectors you found for A, verify that

$$E^{-1}AE = \Lambda \equiv \begin{bmatrix} \lambda_+ & 0 \\ 0 & \lambda_- \end{bmatrix}$$

-3.6: Now that you have diagonalized A (Equation 2.6.18), use your results for E and Λ to solve for the n = 10 solution $(x_{10}, y_{10})^T$ to Pell's equation with N = 2.

2.7.4 The Fibonacci Sequence

Problem #4 Here we seek the Fibonacci sequence for x_n . Like Pell's equation, Eq. 2.6.11 has a recursive, eigenanalysis solution. To find it we must recast x_n as a 2×2 matrix relationship and then proceed as we did for the Pell case.

-4.1: By example, show that the Fibonacci sequence x_n as described above may be generated by

$$\begin{bmatrix} x_n \\ y_n \end{bmatrix} = \begin{bmatrix} 1 & 1 \\ 1 & 0 \end{bmatrix}^n \begin{bmatrix} x_0 \\ y_0 \end{bmatrix}, \qquad \begin{bmatrix} x_0 \\ y_0 \end{bmatrix} = \begin{bmatrix} 1 \\ 0 \end{bmatrix}.$$
 (NS-3.1)

- -4.2: What is the relationship between y_n and x_n ?
- -4.3: Write a MATLAB/Octave program to compute x_n using the matrix equation above. Test your code using the first few values of the sequence. Using your program, what is x_{40} ? Note: Consider using the eigenanalysis of A, described by Eq. 2.6.18.
- -4.4: Using the eigenanalysis of the matrix A (and a lot of algebra) shows that it is possible to obtain the general formula for the Fibonacci sequence

67

2.8 Pell's Equation

$$x_n = \frac{1}{\sqrt{5}} \left[\left(\frac{1 + \sqrt{5}}{2} \right)^{n+1} - \left(\frac{1 - \sqrt{5}}{2} \right)^{n+1} \right].$$
 (NS-3.2)

- -4.5: What are the eigenvalues λ_{\pm} of the matrix A?
- -4.6: How is the formula for x_n related to these eigenvalues? Hint: Find the eigenvectors.
 - -4.7: What happens to each of the two terms

$$[(1 \pm \sqrt{5})/2]^{n+1}$$
?

-4.8: What happens to the ratio x_{n+1}/x_n ?

Problem #5 Replace the Fibonacci sequence with

$$x_n = \frac{x_{n-1} + x_{n-2}}{2},$$

such that the value x_n is the average of the previous two values in the sequence.

- −5.1: What matrix A is used to calculate this sequence?
- -5.2: Modify your computer program to calculate the new sequence x_n . What happens as $n \to \infty$?
- -5.3: What are the eigenvalues of your new A? How do they relate to the behavior of x_n as $n \to \infty$? Hint: You can expect the closed-form expression for x_n to be similar to Eq. NS-3.2.
 - −5.4: What matrix A is used to calculate this sequence?
- -5.5: Modify your computer program to calculate the new sequence x_n . What happens as $n \to \infty$?
- -5.6: What are the eigenvalues of your new A? How do they relate to the behavior of x_n as $n \to \infty$? Hint: You can expect the closed-form expression for x_n to be similar to Eq. NS-3.2.

Problem #6 Consider the expression

$$\sum_{1}^{N} f_n^2 = f_N f_{N+1}.$$

-6.1: Find a formula for f_n that satisfies this relationship. Hint: It holds for only the Fibonacci recursion formula.

Chapter 3 **Algebraic Equations: Stream 2**



3.1 Algebra and Geometry as Physics

Stream 2 is geometry, which led to the merging of Euclid's geometrical methods and the development of algebra by al-Khwarizmi in 830 CE (Fig. 1.1). This migration of ideas led Descartes and Fermat to develop analytic geometry (Fig. 1.2).

The mathematics upto the time of the Greeks, documented and formalized by Euclid, served students of mathematics for more than two thousand years. Algebra and geometry were, at first, independent lines of thought. When merged, the focus returned to the Pythagorean theorem. Algebra generalized the analytic conic section into the complex plane, greatly extending the geometrical approach as taught in Euclid's *Elements*. With the introduction of algebra, numbers, rather than lines, could be used to reproduce geometrical lengths in the complex plane. Thus the appreciation for geometry grew after the addition of rigorous analysis using numbers as shown as a time-line in Fig. 3.1.

History of Mathematics after the 15th Century

- 16th Bombelli 1526-1572; Galileo 1564-1642; Kepler 1571-1630; Mersenne 1588-1648;
- 17th Huygens 1629–1695; Newton 1642–1727^a, Principia 1687; Bernoulli, Jakob 1655–1705; Bernoulli, Johann 1667–1748; Fermat, Pierre de 1607–1665; Pascal, Blaise 1623–1662; Descartes, René 1596–1648
- 18th Bernoulli, Daniel 1700–1782; Euler, Leonhard 1707–1783; d'Alembert, Jean le Rond 1717–1783; Lagrange, Joseph-Louis 1736–1833; Laplace 1749–1827; Fourier 1768–1830; Gauss 1777–1855; Cauchy 1789–1857
- 19th Helmholtz 1821–1894; Kelvin 1824–1907; Kirchhoff 1824–1887; Riemann 1826–1866; Maxwell 1831–1879; Rayleigh 1842–1919; Heaviside 1850–1925; Poincare 1854–1912; Hilbert 1862–1942; Einstein 1879–1955; Fletcher 1884–1981; Sommerfeld 1886–1951; Brillouin 1889–1969; Nyquist 1889–1976
- 20th Bode 1905-1982

^aBorn Dec 25, 1942, Julian calendar

Physics inspires algebraic mathematics: The Chinese used music, art, and navigation to drive mathematics. Much of their knowledge has been handed down as either artifacts, such as musical bells and tools, or mathematical relationships documented, but not created by scholars such as Euclid, Archimedes, Diophantus, and perhaps Brahmagupta. With the invention of algebra in 830 CE by al-Khwarizmi, mathematics became more powerful and blossomed. During the sixteenth and seven-




Fig. 3.1 Timeline of the 300 years from the mid-seventeenth to the mid-twentieth centuries CE, an important era in mathematics that produced a continuous stream of fundamental theorems because mathematicians were sharing information. A few of the individuals who played notable roles in this development, in chronological (birth) order, are Galileo, Mersenne, Newton, d'Alembert, Fermat, Huygens, Descartes, Helmholtz, and Kirchhoff. These were some of the first to develop the basic ideas, in various forms, that were later reworked into the proofs that today we recognize as *the fundamental theorems of mathematics*. Mozart and Beethoven are included for orientation

teenth centuries, it became clear that differential equations (DEs), such as the wave equation, can characterize a law of nature at a single point in space and time. This principle was not obvious. A desire to understand the motions of planets other objects precipitated many new discoveries. This period, centered around Galileo, Newton, and Euler, is shown on the timeline in Fig. 1.2.

As we have described, the law of gravity was first formulated by Galileo using the concept of conservation of energy, which determines how masses are accelerated when friction is not considered and the mass is constant. Tycho Brahe investigated the motion of the planets. Starting in early 1600, Kepler (1571–1630) began an extended visit with Brahe. In 1604, working with Brahe's data Kepler described the inverse square law of light and studied the workings of the human eye. Kepler was also the first to predict that the orbits of planets are described by ellipses. It seems he under-appreciated the significance of his finding, as he continued working on his five polyhedra nested model of planetary motion (Stillwell 2010, p. 23).

Building on Galileo (1638) (see the discussion on "Preface"), Newton demonstrated that there must be a gravitational potential between two masses (m_1, m_2) of the form

$$\phi_{\text{New}}(r(t)) \propto \frac{m_1 m_2}{r(t)},$$
(3.1.1)

where $r = |x_1 - x_2|$ is the Euclidean distance between the two point masses at locations x_1 and x_2 . Using algebra and his calculus, Newton formalized the equations of gravity, forces, and motion (Newton's three laws), the most important being

$$f(t) = \frac{d}{dt}M(t)v(t), \tag{3.1.2}$$

and showed that Kepler's discovery of planetary elliptical motion naturally follows from these laws (see Sect. 3.10.2). With the discovery of Uranus in 1781, "Kepler's theory was ruined." (Stillwell 2010, p. 23).

In Fig. 3.1 we see the important 1640–1950 timeline, from Newton to Einstein. There are two clear developments: Newton to Cauchy and Stokes to Einstein.

Possibly the first measurement of the speed of sound, 1380 Paris feet per second, was made by Marin Mersenne in 1630.^a

Newton and the speed of sound: After Newton proposed the basic laws of gravity and explained the elliptical motion of the planets, he proposed the first model of the speed of sound.

In 1630 Mersenne showed that the speed of sound was approximately 1000 [ft/s]. This may have been done by finding the difference between the time of the flash of an explosion and the time it is heard. For example, if the explosion is 1 [mi] away, the delay is about 5 [s]. Thus with a simple clock, such as a pendulum, and a explosive, the speed may be accurately measured. If we say the speed of sound is c_o , then the equation for the wavefront is $f(x, t) = u(x - c_o t)$, where the function u(t) = 0 for t < 0 and 1 for t > 0. If the wave is traveling in the opposite direction, then the formula is $u(x + c_o t)$. If one also assumes that sounds add in an independent manner (superposition holds) (see Postulate P2 on Sect. 3.10.2), then the general solution for the acoustic wave is

$$f(x,t) = Au(x - c_0 t) + Bu(x + c_0 t),$$

where A and B are the amplitudes of the two waves. This is the solution proposed by d'Alembert in 1747 for the acoustic wave equation

$$\frac{\partial^2}{\partial x^2}\varrho(x,t) = \frac{1}{c_a^2} \frac{\partial^2}{\partial t^2}\varrho(x,t), \tag{3.1.3}$$

one of the most important equations of mathematical physics (see Eq. 4.4.1), 20 years after Newton's death.

It was well established, at least by the time of Galileo, that the wavelength λ and frequency f of a pure tone sound wave obey the relationship

$$f\lambda = c_o. (3.1.4)$$

Given what we know today, the general solution to the wave equation may be written in terms of a sum over the complex exponentials, famously credited to Euler,

^a1 English foot is 1.06575 Paris feet.

$$\varrho(x,t) = Ae^{j2\pi(ft-x/\lambda)} + Be^{j2\pi(ft+x/\lambda)}, \tag{3.1.5}$$

where t is time, x is position, and ft and x/λ are dimensionless. This equation describes only the steady-state solution, with no onsets or dispersion. Thus this solution must be generalized to include these important effects.

The basics of sound propagation were within Newton's grasp and were finally published in *Principia* in 1687. The general solution to Newton's wave equation [i.e., $p(x, t) = G(t \pm x/c)$], where G is any function, was first published 60 years later by d'Alembert. Newton's value for the speed of sound in air c_0 was incorrect by the thermodynamic constant $\sqrt{\eta_o} = \sqrt{1.4}$, a problem that would take well over a century to rectify, by Laplace in 1816, and experimentally by Rankine in 1850 (Rayleigh 1896, p. 19–23, Vol. II). What was needed was the adiabatic process (the concept of constant-heat energy). For audio frequencies (0.02-20 [kHz]), the temperature gradients cannot diffuse the distance of a wavelength in one cycle, so the heat energy is trapped in the wave (Tisza 1966; Pierce 1981; Boyer and Merzbach 2011). To repair Newton's formula for the sound speed it was necessary to define the adiabatic stiffness of air $\eta_o P_o$, where P_o is 1 [atm] or 10^5 [Pa] (1 [Pa] is 1 $[N/m^2]$). This required replacing Boyle's law (PV/T = constant) with the adiabatic expansion law ($PV^{\eta_o} = \text{constant}$). But this fix still ignores the important viscous and thermal losses, as discussed in Appendix D (Kirchhoff 1868; Rayleigh 1896; Mason 1927; Pierce 1981).

Today we know that when ignoring viscous and thermal losses, the speed of sound is given by

$$c_o = \sqrt{\frac{\eta_o P_o}{\rho_o}} = 343$$
 [m/s],

which is a function of the density $\rho_o = 1.12$ [kg/m³], $P_o = 10^5$ [Pa], and the dynamic stiffness $\eta_o P_o$ of air.² The speed of sound stated in other units is 343 [m/s], 1234.8 [km/h], 153.33 [m/s], 15.334 [cm/ms], 1.125 [ft/ms], 1125.3 [ft/s], 4.692 [s/mi], 12.78 [mi/min], 0.213 [mi/s], and 767.27 [mi/h]. A slightly useful approximation is the time between the lightning flash and the thunder (≈ 5 [sec/mi]).

Newton's success was important because it quantified the physics behind the speed of sound and demonstrated that momentum (mv), not mass m, is transported by the wave. His concept was correct, and his formulation using algebra and calculus represented a milestone in science.

In periodic structures, again the wave number becomes complex due to diffraction, as commonly observed in optics (e.g., diffraction gratings) and acoustics (creeping surface waves). Thus Eq. 3.1.4 holds for only the simplest cases. In general, the complex analytic (thus causal and dispersive) function *propagation vector* $\kappa(x, s)$ must be considered (see Eq. 3.1.6).

¹There were other physical enigmas, such as the observation that sound disappears in a vacuum, or Pascal's observation that a vacuum cannot draw water up a column by more than 34 ft..

 $^{^2\}eta_o=c_p/c_v=1.4$ is the ratio of two thermodynamic constants, and $P_o=10^5$ [Pa] is the barometric pressure of air.

The corresponding discovery of the formula for the speed of light was made nearly two centuries after *Principia* by Maxwell (ca.1861). Maxwell's formulation also required great ingenuity, as it was necessary to hypothesize an experimentally unmeasured term in his equations to get the mathematics to correctly predict the speed of light (and gravity waves). This parallel with the speed of sound is notable.

It is somewhat amazing that to this day we have failed to fully understand gravity significantly better than Newton's theory, although this may too harsh given Einstein's famous work on general relativity in 1915.³

Case of dispersive wave propagation: This classic relationship $\lambda f = c$ is deceptively simple, yet confusing, because the *wave number*⁴ $k = 2\pi/\lambda$ becomes a complex function of frequency (has both real and imaginary parts) in dispersive media when losses are considered, as discussed in Appendix D (Kirchhoff 1868; Mason 1928).

A second important example is the case of electron waves in silicon crystals, where the wave number $k(f) = 2\pi f/c$ is replaced by the complex analytic function of the Laplace frequency s, the propagation vector $\kappa(s)$. In this case the wave becomes the eigenfunction of the vector (3D) wave equation

$$p^{\pm}(\mathbf{x},t) = P_o(s)e^{st}e^{\pm\kappa(\mathbf{x},s)\cdot\mathbf{x}},\tag{3.1.6}$$

where $|\kappa(x, s)|$ is the vector eigenvalue (Brillouin 1953). In these more general cases, $\kappa(x, s)$ must be a vector complex analytic function of the Laplace frequency $s = \sigma + j\omega$, and inverted with the Laplace transform (Brillouin 1960, with help from Sommerfeld). This is because electron "waves" in the dispersive semiconductor (e.g., silicon) are "causally filtered" in three dimensions—in magnitude, phase, and directions x. These 3D dispersion relationships are known as *Brillouin zones*.

Silicon is a highly dispersive "wave-filter," forcing the wavelength to be a function of both *s* and direction. This view is elegantly explained by Brillouin (1953, Chap. 1) in his historic text. Although the most famous examples come from quantum mechanics (Condon and Morse 1929), modern acoustics contains a rich source of related examples (Morse 1948; Beranek 1954; Ramo et al. 1965; Fletcher and Rossing 2008).

3.1.1 The First Algebra

Prior to the invention of algebra, people worked out mathematical problems as sentences, using an obtuse description of the problem (Stillwell 2010, p. 93). Algebra changed this approach and led to a compact language of mathematics, where numbers are represented as symbols (e.g., x and α). The problem to be solved could be formu-

³Gravity waves were first observed experimentally while I was writing this chapter.

⁴This term is a misnomer, since the wave number is a complex function of the complex Laplace frequency $s = \sigma + j\omega$, thus not a number in the common sense. Much worse, $\kappa(s) = s/c_o$ must be complex analytic in s, which an even stronger condition. The term *wave number* is so well established, that there is little hope for recovery at this point.

lated in terms of sums of powers of smaller terms, the most common being powers of some independent variable (i.e., time or frequency). If we define $M_N(z) = P_N(z)/a_n$ and $m_k = a_k/a_n$, then

$$M_N(z) \equiv z^N + m_{N-1}z^{N-1} + \dots + m_0 z^0 = z^N + \sum_{k=0}^{N-1} m_k z^k = \prod_{k=1}^N (z - z_k)$$
(3.1.7)

is called a *monic polynomial* or simply a monic. The coefficient a_N cannot be zero, or the polynomial would not be of degree N. The resolution is to force $a_N = 1$, since this simplifies the expression and does not change the roots.

The key question is What values of $z=z_k$ result in $M_N(z_k)=0$? In other words, what are the roots z_k of the polynomial? Answering this question consumed thousands of years, with intense efforts by many aspiring mathematicians. In the earliest attempts, it was a competition to demonstrate mathematical acumen. Results were held as a secret to the death bed. It would be fair to view this effort as an obsession. Today the roots of any polynomial may be found, to high accuracy, by numerical methods. Finding roots is limited by the numerical limits of the representation—namely, by IEEE 754 (see Sect. 2.1.2). There are also a number of important theorems.

Of particular interest is the problem of drawing a circle and a line and finding the intersection (root). There was no solution to this venerable problem using geometry. The resolution is addressed in the solution of Euclid's formula (Problem #2 of Assignment Sect. 3.7.8).

3.1.2 Finding Roots of Polynomials

The problem of factoring polynomials has a history more than a millennium in the making.⁵ While the quadratic (degree N=2) was solved by the time of the Babylonians (i.e., the earliest recorded history of mathematics), the cubic solution was finally published by Cardano in 1545. The same year, Cardano's student Ferrari solved the quartic (N=4). In 1826 (281 years later) it was proved that the quintic (N=5) could not be factored by analytic methods.

As a concrete example we begin with the trivial case of the quadratic

$$P_2(s) = as^2 + bs + c. (3.1.8)$$

First note that if a = 0, the quadratic reduces to the monomial $P_1(s) = bs + c$. Thus we have the necessary condition that $a \neq 0$. The best way to proceed is to divide a out and work directly with the monic $M_2(s) = \frac{1}{a}P_2(s)$. In this way we do not need to worry about the a = 0 exception.

⁵https://www.britannica.com/science/algebra/Fundamental-concepts-of-modern-algebra.

The roots are the values of $s = s_k$ such that $M_2(s_k) = 0$. One of the earliest mathematical results, recorded by the Babylonians in about 2000 BCE, was the factoring of the quadratic by completing the square. We can isolate s by rewriting Eq. 3.1.8 as

$$M_2(s) \equiv \frac{1}{a} P_2(s) = (s + b/2a)^2 - (b/2a)^2 + c/a.$$
 (3.1.9)

The factorization may be verified by expanding the squared term and canceling $(b/2a)^2$:

$$M_2(s) = [s^2 + (b/a)s + (b/2a)^2] - (b/2a)^2 + c/a.$$

Setting Eq. 3.1.9 equal to zero and solving for the two roots s_{\pm} give the quadratic formula:

$$s_{\pm} = \frac{-b \pm \sqrt{b^2 - 4ac}}{2a} \bigg|_{a=1} = -b/2 \pm \sqrt{(b/2)^2 - c}.$$
 (3.1.10)

Role of the discriminant: Equation 3.1.10 can be further simplified. The term $(b/2)^2 - c > 0$ under the square root is called the *discriminant*. Nominally in physics and engineering problems, the discriminant is negative and $b/2 \ll \sqrt{c}$ may be ignored (the damping is small compared to the resonant frequency), leaving only -c under the radical. Thus the most natural way (i.e., corresponding to the most common physical cases) of writing the roots (Eq. 3.1.10) is⁶

$$s_{\pm} \approx -b/2 \pm j\sqrt{|c|} = -\sigma_o \pm s_o. \tag{3.1.11}$$

This form separates the real and imaginary parts of the solution in a natural way. The term $\sigma_o = b/2$ is called the damping, which accounts for losses in a resonant circuit; the term $\omega_o = \sqrt{|c|}$, for mechanical, acoustical, and electrical networks, is called the *resonant frequency*. The last approximation ignores the (typically) minor correction b/2 to the resonant frequency, which in engineering applications is almost always ignored. Knowing that there is a correction is highlighted by this formula, which makes us aware that the small approximation exists (thus can be ignored).

It is not required that $a, b, c \in \mathbb{R} > 0$, but for physical problems of interest, this is almost always true (>99.99% of the time).

Summary: The quadratic equation and its solution are ubiquitous in physics and engineering. It seems obvious that instead of memorizing the meaningless quadratic formula (Eq. 3.1.10), one should learn the physically meaningful solution (Eq. 3.1.11), obtained via Eq. 3.1.9 with a = 1. Arguably, the factored and normalized form (Eq. 3.1.9) is easier to remember as a method (completing the square) rather than as a formula to be memorized.

⁶This is the case for mechanical and electrical circuits that have small damping. Physically b > 0 is the damping coefficient and $\sqrt{c} > 0$ is the resonant frequency. One may then simplify and factor the form as $s^2 + 2bs + c^2 = (s + b + jc)(s + b - jc)$.

Additionally, the real (b/2) and imaginary $(\pm j\sqrt{c})$ parts of the two roots have physical significance as the damping and resonant frequencies. Equation 3.1.10 has none (it is useless).

No insight is gained by memorizing the quadratic formula. To the contrary, an important concept is gained by learning how to complete the square, which is typically easier than identifying a, b, c and blindly substituting them into Eq. 3.1.10. Thus it's worth learning the alternative solution (Eq. 3.1.11), since it is more common in practice and requires less algebra to interpret the final answer.

Exercise #1 By direct substitution, demonstrate that Eq. 3.1.10 is the solution of Eq. 3.1.8. Hint: Work with $M_2(x)$.

Sol: Setting a = 1, we can write the quadratic formula as

$$s_{\pm} = \frac{-b \pm 1 \sqrt{4c - b^2}}{2}.$$

Substituting this into $M_2(s)$ gives

$$\begin{split} M_{\pm}(s_{\pm}) &= s_{\pm}^{2} + bs_{\pm} + c = -b/2 \pm j\sqrt{c^{2} - (b/2)^{2}} \\ &= \left(\frac{-b \pm \sqrt{b^{2} - 4c}}{2}\right)^{2} + b\left(\frac{-b \pm \sqrt{b^{2} - 4c}}{2}\right) + c \\ &= \frac{1}{4}\left(b^{2} \pm 2b\sqrt{b^{2} - 4c} + (b^{2} - 4c)\right) + \frac{1}{4}\left(-2b^{2} \pm 2b\sqrt{b^{2} - 4c}\right) + \phi \\ &= 0. \end{split}$$

In third grade I learned the times-table trick for 9:

$$9 \cdot n = (n-1) \cdot 10 + (10-n).$$

With this simple rule I did not need to depend on my memory for the 9 times table. For example: $9 \cdot 7 = (7-1) \cdot 10 + (10-7) = 60 + 3$ and $9 \cdot 3 = (3-1) \cdot 10 + (10-3) = 20 + 7$. By expanding, one can see why it works: 9n = n10 + (2+10) + (2+10) - n = n(10-1). Note that the two terms (n-1) and (10-n) add to 9.

Learning an algorithm is much more powerful than memorizing the 9 times tables. How you think about a problem can have a great impact on your perception.

Newton's method for finding the roots of $P_N(s)$: Newton is well known for an approximate but efficient method to find the roots of a polynomial. Consider the polynomial $s, P_N(s) \in \mathbb{C}$:

$$P_N(s) = c_N(s - s_0)^N + c_{N-1}(s - s_0)^{N-1} + \dots + c_1(s - s_0) + c_0, \quad (3.1.12)$$

where we use Taylor's formula (see Sect. 3.2.3) to determine the coefficients

$$c_k = \frac{1}{k!} \frac{d^k}{ds^k} P_N(s) \bigg|_{s=s_o}.$$
 (3.1.13)

If our initial guess for the root s_1 is close to a root s_o (i.e., $s_1 - s_o$ is within the radius of convergence), then $|(s_1 - s_o)^k| \ll |(s_1 - s_o)|$ for $k \ge 2 \in \mathbb{N}$. Thus we may truncate $P_N(s_1)$ to its linear term c_1 :

$$P_N(s_1) \approx (s_1 - s_o) \frac{d}{ds} P_N(s) \Big|_{s_o} + P_N(s_o)$$

= $(s_1 - s_o) P'_N(s_o) + P_N(s_o)$,

where $P'_N(s_o)$ is shorthand for $dP_N(s_o)/ds$.

Newton's approach (approximation) was to define a recursion such that the next guess s_{n+1} is closer to the root s_o than the previous guess s_n . Replacing s_1 by s_{n+1} and s_o by s_n gives

$$P_N(s_{n+1}) = (s_{n+1} - s_n)P'_N(s_n) + P_N(s_n) \to 0.$$

Here we assume $P_N(s_{n+1}) \to 0$ because $s_{n+1} \to s_o$ as $n \to \infty$.

Solving for s_{n+1} , we get

$$s_{n+1} = s_n - \frac{P_N(s_n)}{P_N'(s_n)}. (3.1.14)$$

Everything on the right is known; thus s_{n+1} should converge to the root s_o as $n \to \infty$.

Note that if s_n is at a root, the numerator term $P_N(s_n) \to 0$, thus and the update goes to zero, and $s_{n+1} \to s_n$. This difference is useful in detecting the stopping condition. Also note that the denominator can never be zero near a root because $P'_N(s)$ cannot share a root with $P_N(s)$.

In practice, it takes only a few steps to approach the root. In experimental trials (see Fig. 3.2) fewer than 10 steps give double-precision floating-point machine accuracy. If any value s_n is close to a root of P'_N , the recursion fails, giving a large value for s_{n+1} and forcing the method to restart at s_{n+1} , far from the root. In such cases the solution typically converges to a different root. It should not be difficult to detect these large non-convergent steps by monitoring $|s_{n+1} - s_n|$, which should be monotonically decreasing.

However, if one assumes that the initial guess $s_1 \in \mathbb{R}$ and then evaluates the polynomial using real arithmetic, the estimate $s_{n+1} \in \mathbb{R}$. Thus the iteration will not converge if $s_o \in \mathbb{C}$.




Fig. 3.2 Newton's method applied to the polynomial that has real roots [1, 2, 3, 4] (left) and 5 complex roots (right). A random starting point was chosen, and each curve shows the values of s_n as Newton's method converges to the root. Different random starting points converge to different roots. The method always results in convergence to a root. Claims to the contrary (Stewart 2012, p. 347) are a result of forcing the roots to be real. For convergence, one must assume $s_n \in \mathbb{C}$. For a related discussion see Stillwell (2010, Sect. 14.7)

Root $s_0 \in \mathbb{C}$ may be found by a recursion that defines a sequence $s_n \to s_0$, $n \in \mathbb{N}$, such that $P_N(s_n) \to 0$ as $n \to \infty$. As shown in Fig. 3.2, solving for s_{n+1} using Eq. 3.1.14 always gives one of the roots, due to the analytic behavior of the complex *logarithmic derivative* P'_N/P_N .

With every step, s_{n+1} is closer to the root, finally converging to the root in the limit. As it comes closer, the linearity assumption becomes more accurate, resulting in a better approximation and thus a faster convergence.

Equation 3.1.14 depends on the log-derivative $d \log P(x)/dx = P'(x)/P(x)$. It follows that even for cases where fractional derivatives of roots are involved (see Sect. 4.5); Newton's method should converge, since the log-derivative linearizes the equation.⁷

Newton's view: Newton believed that imaginary roots and numbers have no meaning (see p. 179), thus he sought only real roots (Stillwell 2010, p. 119). In this case Newton's relationship may be explored as a graph, which puts Newton's method in the realm of analytic geometry.

Example: Given a polynomial $P_2 = 1 - x^2$ that has roots ± 1 , we can use Newton's method to find the roots. Since $P'_2(x) = -2x$, Newton's iteration becomes

$$x_{n+1} = x_n + \frac{1 - x_n^2}{2x_n}.$$

From the Gauss-Lucas theorem (see Seet. 4.5), for the case of N=2, the root of $P_2'(x)$ is always the average of the roots of $P_2(x)$. To start the iteration (n = 0) we

⁷This seems like a way to understand fractional, even irrational, roots.

need an initial guess for x_0 , which is an initial random guess of where a root might be. The only place we may not start is at the roots of P'_N . For $P_2(x) = 1 - x^2$,

$$x_1 = x_0 + \frac{1 - x_0^2}{2x_0} = x_0 + \frac{1}{2} (-x_0 + 1/x_0).$$

Exercise #2 Let $P_2(x) = 1 - x^2$. Choose the expansion point as $x_0 = 1/2$. Draw a graph describing the first step of the iteration.

Sol: We start with an (x, y) coordinate system and put points at $x_0 = (1/2, 0)$ and the vertex of $P_2(x)$; that is, (0, 1) ($P_2(0) = 1$). Then we draw $1 - x^2$, along with a line from x_0 to x_1 .

Exercise #3 Calculate x_1 and x_2 of Exercise #2. What root will it converge to? What are the roots of P_2 ?

Sol: First we must find $P_2'(x) = -2x$. Thus the equation we will iterate is

$$x_{n+1} = x_n + \frac{1 - x_n^2}{2x_n} = \frac{x_n^2 + 1}{2x_n} = (x_n + 1/x_n)/2.$$

By hand,

$$x_0 = 1/2$$

$$x_1 = \frac{(1/2)^2 + 1}{2(1/2)} = \frac{1}{4} + 1 = 5/4 = 1.25$$

$$x_2 = \frac{(5/4)^2 + 1}{2(5/4)} = \frac{(25/16) + 1}{10/4} = \frac{1}{2} \left(\frac{5}{4} + \frac{4}{5}\right) = \frac{41}{40} = 1.025.$$

These estimates rapidly approach the positive-real root x = 1. Note that if one starts at the root of P'(x) = 0 (i.e., $x_0 = 0$), the first step is indeterminate.

Exercise #4 Write an Octave/MATLAB2 script to check your answer for part Exercise #3.

Sol:

$$x=1/2$$
;
for $n = 1:3$
 $x = x+(1-x*x)/(2*x)$;
end

Exercise #5 For n = 4, what is the absolute difference between the root and the estimate, $|x_r - x_4|$?

Exercise #6 What happens if $x_0 = -1/2$?

Sol: The solution converges to the negative root, x = -1.

Exercise #7 Does Newton's method (Kelley 2003) work for $P_2(x) = 1 + x^2$? Hint: What are the roots in this case?

Sol: In this case $P_2'(x) = +2x$; thus the iteration gives

$$x_{n+1} = x_n - \frac{1 + x_n^2}{2x_n}.$$

The roots are purely imaginary, $x_{\pm} = \pm 1j$. Newton's method works fine as long as you use complex arithmetic. Study Fig. 3.2, and then try Octave/MATLAB to convince yourself.

Exercise #8 What if you let $x_0 = 1 + j$ for the case of $P_2(x) = 1 + x^2$? **Sol:**

```
x=1+j;
for n = 1:4
x = x-(1+x*x)/(2*x);
end
```

After 4 steps $x_4 = -0.0000046418 + 1.0000021605i$. After 6 steps $x_6 = 8.46e - 23 + i$. On the 7th Step the result is exact.

If you use only real arithmetic, obviously Newton's method fails, because there is no way for the answer to become complex. If, like Newton, you didn't believe in complex numbers, your method would fail to converge to the complex roots (i.e., Real in = Real out). This is because Octave/MATLAB assumes $x \in \mathbb{R}$ if it is initialized as \mathbb{R} . By starting with a complex initial value, we fix the Real in = Real out problem.

3.1.2.1 Basic Properties of Polynomials

In some sense polynomials such as $P_N(z)$ are the simplest constructions used in algebra, and a summary of their most basic properties is helpful.

- 1. The degree of a polynomial is n.
- 2. Polynomials are single-valued; that is, for every z_0 , there is precisely one value for $P_N(z_0)$.
- 3. In mathematical physics and engineering it is common to have real coefficients a_n , but complex coefficients are possible.
- 4. The coefficients of every polynomial are determined by its Taylor series—namely, Sect. 3.2.3.
- 5. If the coefficients are real and positive, then the $P_N(x)$ is positive and real if x > 0.
- 6. The fundamental theorem of algebra states that $P_N(z)$ has exactly N roots.
- 7. The number of coefficients of the monomial $M_N(x)$ is equal to N, thus the number of roots.
- 8. The roots of polynomials with positive and real coefficients typically have complex roots—that is, if $P_N(z_k) = 0$, then $z_k \in \mathbb{C}$.

- 9. The region of convergence (RoC) of every polynomial about the expansion point is infinite.
- 10. The roots of the derivative of a polynomial lie within the convex hull defined by the roots of $P_N(z)$, as described by the Gauss–Lucas theorem (see discussion below Eq. 3.1.15).
- 11. The eigenvalues of the companion matrix are identical to the roots as the monic $M_N(x)$.

Exercise #9 Find the logarithmic derivative of f(x)g(x).

Sol: From the definition of the logarithmic derivative and the chain rule for the differentiation of a product, we have

$$\frac{d}{dx}\ln f(x)g(x) = \frac{d}{dx}\ln f + \frac{d}{dx}\ln g$$
$$= \frac{1}{f}\frac{d}{dx}f + \frac{1}{g}\frac{d}{dx}g.$$

Example: If we assume that function $P_3(s) = (s-a)^2/(s-b)^{\pi}$, then

$$\ln P_3(s) = 2\ln(s - a) - \pi \ln(s - b)$$

and

$$\frac{d}{ds}\ln P_3(s) = \frac{2}{s-a} - \frac{\pi}{s-b}.$$

Reduction by the logarithmic derivative to simple poles: As shown for $P_3(s)$ of the previous example, a function that has poles of arbitrary degree (i.e., π in the example) may be reduced to the sum of two functions having simple poles by taking the logarithmic derivative, since

$$L_N(s) = \frac{N(s)}{D(s)} = \frac{d}{ds} \ln P_N(s) = \frac{P_N'(s)}{P_N(s)}.$$
 (3.1.15)

Here the polynomial is the denominator $D(s) = P_N(s)$, while the numerator $N(s) = P'_N(s)$ is the derivative of D(s). Thus the logarithmic derivative can play a key role in the analysis of complex analytic functions, as it reduces higher order poles, even those of irrational degree, to simple poles (those of degree 1).

The logarithmic derivative $L_N(s)$ has the following special properties:

- 1. $L_N(s)$ has simple poles s_p and zeros s_z .
- 2. The poles of $L_N(s)$ are the zeros of $P_N(s)$.
- 3. The zeros of $L_N(s)$ (i.e., $P'_N(s_z) = 0$) are the zeros of $P'_N(s)$.
- 4. $L_N(s)$ is analytic everywhere other than at its poles.
- 5. Since the zeros of $P_N(s)$ are simple (no second-order poles), the zeros of $L_N(s)$ always lie close to the line connecting the two poles. One may easily demonstrate

the truth of the statement numerically, and it has been quantified by the Gauss–Lucas theorem, which specifies the relationship between the roots of a polynomial and those of its derivative. Specifically, the roots of P'_{N-1} lie inside the convex hull of the roots of P_N .

6. The eigenvalues s_k of the companion matrix are equal to the roots of the monomial $M_N(s)$.

To understand the meaning of *convex hull*, consider the following construction: If stakes are placed at each of the N roots of $P_N(x)$, and a string is then wrapped around the stakes, with all the stakes inside the string, the convex hull is then the closed set inside the string. One can begin to imagine how the N-1 roots of the derivative must evolve with each set inside the convex hull of the previous set. This concept may be recused to smaller values of N.

Newton's method may be expressed in terms of the reciprocal of the logarithmic derivative, since

$$s_{k+1} = s_k + \epsilon_o / L_N(s),$$

where ϵ_o is called the *step size*, which is used to control the rate of convergence of the algorithm. If the step size is too large, the root-finding path may jump to a different domain of convergence and thus a different root of $P_N(s)$.

8. Not surprisingly, given all the special proprieties, $L_N(s)$ plays an key role in mathematical physics.

Euler's product formula: Counting may be written as a linear recursion simply by adding 1 to the previous value, starting from 0. The even numbers may be generated by adding 2, starting from 0. Multiples of 3 may be similarly generated by adding 3 to the previous value, starting from 0. Such recursions are fundamentally related to prime numbers $\pi_k \in \mathbb{P}$, as first investigated by Euler. This logic is the basis of the sieve (see Sect.2.4). The basic idea is both simple and important, taking almost everyone by surprise, likely even Euler. It is related to the old idea that the integers may be generated by the geometric series when viewed as a recursion.

Example: Let's look at counting modulo prime numbers. For example, if $k \in \mathbb{N}$, then

$$k \cdot \text{mod}(k, 2), k \cdot \text{mod}(k, 3), k \cdot \text{mod}(k, 5)$$

are all multiples of the primes $\pi_1 = 2$, $\pi_2 = 3$, and $\pi_3 = 5$.

To see this, we define the *step function* $u_n = 0$ for n < 0 and $u_n = 1$ for $n \ge 0$ and the *counting number function* $N_n = 0$ for n < 0. The counting numbers may be recursively generated from the recursion

$$N_{n+1} = N_{n-M} + u_n, (3.1.16)$$

which for M = 1 gives $N_n = n$. For M = 2, $N_n = 0, 2, 4, \dots$ gives the even numbers.




Fig. 3.3 This feedback network describes the linear discrete-time difference equation with delay M [s] given by Eq. 3.1.16. If M = 1 this circuit acts as an integrator. When the input is a step function, the output will be $N_n = nu_n = [0, 1, 2, 3, \ldots]$. Such discrete-time circuits are called digital filters

As was first published by Euler in 1737, one may recursively factor out the leading prime term, resulting in Euler's product formula. Based on the argument given in the discussion of the sieve on Sect. 2.2, one may automate the process and create a recursive procedure to identify multiples of the first item on the list, and then remove the multiples of that prime. The lowest number on this list is the next prime. One may then recursively generate all the multiples of this new prime and remove them from the list. Any numbers that remain are candidates for primes.

The observation that this procedure may be automated with a recursive filter, such as that shown in Fig. 3.3, implies that it may be transformed into the frequency domain and described in terms of its poles, which are related to the primes. For example, the poles of the filter shown in Fig. 3.3 may be determined by taking the z-transform of the recursion equation and solving for the roots of the resulting polynomial. The recursion equation is the time-domain equivalent to Riemann's zeta function $\zeta(s)$, which is the frequency-domain equivalent representation.

Exercise #10 Show that $N_n = n$ follows from the above recursion.

Sol: If n = -1, we have $N_n = 0$ and $u_n = 0$. For n = 0 the recursion gives $N_1 = N_0 + u_0$; thus $N_1 = 0 + 1$. When n = 1, we have $N_2 = N_1 + 1 = 1 + 1 = 2$. For n = 2, the recursion gives $N_3 = N_2 + 1 = 3$. Continuing the recursion, we find that $N_n = n$. Today we denote a recursions of this form as a *digital filter*. The state diagram for N_n is shown in Fig. 3.3.

To start the recursion, we define $u_n = 0$ for n < 0. Thus $u_0 = u_{-1} + 1$. But since $u_{-1} = 0$, $u_0 = 1$. The counting numbers follow from this recursion. A more understandable notation is convolution of the step function with itself—namely,

$$nu_n = u_n \star u_n = \sum_{m=0}^{\infty} u_m u_{m-n} \leftrightarrow \frac{1}{(1-z)^2},$$

which says that the counting numbers $\hat{\mathbf{n}} \in \mathbb{N}$ are easily generated by convolution, which corresponds to a second-order pole at z = 1 in the z-transform frequency domain (see Sect. 3.4.1).

Exercise #11 Write an Octave/MATLAB program that generates the odd numbers $N_n = \{1, 0, 3, 0, 5, 0, 7, 0, 9, ...\}$ by removing the even numbers. **Sol:**

```
M=50; N=(0:M-1); u=ones(1,M); u(1)=0; Dem=[1 1]; Num=[1]; n=filter(Num, Dem, u); y2=n.*N; F1=N-y2 which generates: F1=[0,1,0,3,0,5,0,7,0,9,0,...].
```

An alternative is to use the mod(n, N) function:

```
M=20; n=0:M; k=mod(n,2); m=(k==0).*n; which generates m = [0, 1, 0, 3, 0, 5, ...]
```

Exercise #12 Write a program to recursively down-sample N_n by 2:1. **Sol:**

```
N=[1 0 3 0 5 0 7 0 9 0 11 0 13 0 15]

M=N(2:2:end);

which gives: M = [1, 3, 5, 7, 9, 11, 13, 15, ...]
```

For the next step toward a full sieve (Fig. 2.3), we generate all the multiples of 3 (the second prime) and subtract these from the list. This will either zero out these numbers from the list or create negative items, which may then be removed. Numbers are negative when the number has already been removed because it has a second factor of that number. For example, 6 is already removed because it is a multiple of 2 and thus was removed with the multiples of prime number 2.

3.1.3 Matrix Formulation of the Polynomial

There is a simple relationship between every constant coefficient differential equation, its characteristic polynomial, and the equivalent matrix form of that differential equation, defined by the *companion matrix*. The roots of the monic polynomial are the eigenvalues of the companion matrix C_N (Horn and Johnson 1988, p. 147).

The companion matrix: The $N \times N$ companion matrix is defined as

$$C_{N} = \begin{bmatrix} 0 & & & -c_{0} \\ 1 & 0 & & 0 & -c_{1} \\ 0 & 1 & 0 & & -c_{2} \\ \vdots & 0 & 1 & 0 & \cdots & \vdots \\ & \cdots & \ddots & 0 & \vdots \\ 0 & & 1 & 0 - c_{N-2} \\ & & 0 & 1 - c_{N-1} \end{bmatrix}_{N \times N}$$

$$(3.1.17)$$

The constants c_{N-n} are from the monic polynomial of degree N,

$$P_N(s) = s^N + c_{N-1}s^{N-1} + \dots + c_2s^2 + c_1s + c_0$$

= $s^N + \sum_{n=0}^{N-1} c_n s^n$,

which has coefficient vector

$$\mathbf{c}_N = [1, c_{N-1}, c_{N-2}, \dots, c_1, c_0]^T.$$

Any transformation of a matrix that leaves the eigenvalues invariant (e.g., the transpose) results in an equivalent definition of C_N . Note that the Octave/MATLAB companion matrix function C=compan(A) returns the coefficient vector along the top row.

Example: MATLAB/Octave returns the companion matrix in a different format with the coefficients along the top row rather than on the final column. For example if $P_3(s) = [1, c_2, c_1, c_0]$ then Octave/MATLAB returns

$$P_3(s) = \begin{bmatrix} -c_2 - c_1 - c_0 \\ 1 & 0 & 0 \\ 0 & 1 & 0 \end{bmatrix}.$$

Exercise #13 Show that the eigenvalues of the 3×3 companion matrix are the same as the roots of $P_3(s)$.

Sol: Expanding the determinant of $C_3 - sI_3$ along the rightmost column, we get

$$P_3(s) = -\begin{vmatrix} -s & 0 & -c_0 \\ 1 & -s & -c_1 \\ 0 & 1 & -(c_2 + s) \end{vmatrix} = c_0 + c_1 s + (c_2 + s) s^2 = s^3 + c_2 s^2 + c_1 s + c_0.$$

Setting this to zero gives the requested result.

Exercise #14 Find the companion matrix for the Fibonacci sequence defined by the recursion (i.e., difference equation)

$$f_{n+1} = f_n + f_{n-1}$$

and initialized with $f_n = 0$ for n < 0 and $f_0 = 1$.

Sol: Taking the z-transform gives the polynomial $(z^1 - z^0 - z^{-1})F(z) = 0$, which has the coefficient vector $\mathbf{c} = [1, -1, -1]^T$, resulting in the Fibonacci companion matrix

 $C = \begin{bmatrix} 0 & 1 \\ 1 & 1 \end{bmatrix}.$

The MATLAB/Octave companion matrix routine compan(C) uses an alternative definition that has the same eigenvalues (see Sect. 2.7).

Example: A polynomial is represented in MATLAB/Octave in terms of its coefficient vector. When the polynomial vector for the poles of a differential equation is

$$c_N = [1, c_{N-1}, c_{N-2}, \dots, c_0]^T,$$

the coefficient $c_N = 1$. This normalization guarantees that the leading term is not zero and the number of roots (N) is equal to the degree of the monic polynomial.

3.1.4 Working with Polynomials in MATLAB/Octave

In MATLAB/Octave there are eight related functions you must become familiar with:

1. $\mathbb{R}=\mathtt{roots}(\mathbb{A})$: Vector $\mathbb{A}=[a_N,a_{N-1},\ldots,a_0]\in\mathbb{C}$ are the complex coefficients of polynomial $P_N(z)=\sum_{n=0}^N a_n z^n\in\mathbb{C}$, where $N\in\mathbb{N}$ is the degree of the polynomial. It is convenient to force $a_N=1$, corresponding to dividing the polynomial by this value, when it is not 1, thus guaranteeing it cannot be zero. Further, \mathbb{R} is the vector of roots $[z_1,z_2,\ldots,z_n]\in\mathbb{C}$ such that $\mathtt{polyval}(\mathbb{A},z_k)=0$.

Example: roots([1, -1])=1

2. y=polyval(A,x): This evaluates the polynomial defined by vector $A \in \mathbb{C}^N$ evaluated at $x \in \mathbb{C}$, returning vector $y(x) \in \mathbb{C}$.

Example: polyval([1 -1],1)=0, polyval([1, 1],3)=4

3. P=poly(): This is the inverse of root(), returning a vector of polynomial coefficients $P \in \mathbb{C}^N$ of the corresponding characteristic polynomial, starting from either a vector of roots R or a matrix A, for example, defined with the roots on the diagonal. The characteristic polynomial is defined as the determinant of $|A - \lambda I| = 0$ that has roots R.

Example: poly([1]) = [1, -1], poly([1, 2]) = [1, -3, 2]

Due to IEEE 754 scaling issues, this can give strange results that are numerically correct, but only within the limits of IEEE 754 accuracy.

4. R=polyder (C): This routine takes the N coefficients of polynomial C and returns the N-1 coefficients of the derivative of the polynomial. This is useful when working with Newton's method, where each step is proportional to $P_N(x)/P_{N-1}'(x)$.

Example: polyder([1,1]) = [1]

5. [K,R]=residue(N,D): Given the ratio of two polynomials N,D, residue(N,D) returns vectors K,R such that

$$\frac{N(s)}{D(s)} = \sum_{k} \frac{K_k}{s - s_k},\tag{3.1.18}$$

where $s_k \in \mathbb{C}$ are the roots of the denominator \mathbb{D} polynomial and $\mathbb{K} \in \mathbb{C}$ is a vector of residues, which characterize the roots of the numerator polynomial N(s). The use of residue (\mathbb{N}, \mathbb{D}) is discussed on Sect. 4.4. This is one of the most valuable time-saving routines I know.

Example: residue(2, [1 0 -1]) = [1 -1]

6. C=conv(A, B): Vector $C \in \mathbb{C}^{N+M-1}$ contains the polynomial coefficients of the convolution of the two vectors of coefficients of polynomials A, B $\in \mathbb{C}^N$ and B $\in \mathbb{C}^M$.

Example: [1, 2, 1]=conv([1, 1], [1, 1])

7. [C,R]=deconv(N,D): Vectors C, N, D \in C. This operation uses long division of polynomials to find C(s) = N(s)/D(s) with remainder R(s), where N = conv(D,C)+R, which is

$$C = \frac{N}{D} \text{ with remainder } R. \tag{3.1.19}$$

Example: By defining the coefficients of two polynomials as $A = [1, a_1, a_2, a_3]$ and $B = [1, b_1, b + 2]$, we can find the coefficients of the product from C=conv(A, B) and recover B from C with B=deconv(C, A).

8. A=compan(D): Vector $D = [1, d_{N-1}, d_{N-2}, \dots, d_0]^T \in \mathbb{C}$ contains the coefficients of the monic polynomial

$$D(s) = s^{N} + \sum_{k=1}^{N} d_{N-k} s^{k},$$

and A is the companion matrix of vector D (Eq. 3.1.17). The eigenvalues of A are the roots of the monic polynomial D(s).

Example: compan([1 -1 -1]) = [1 1; 1 0]

Exercise #15 Practice the use of MATLAB'S/Octave's related functions that manipulate roots, polynomials, and residues: root(), conv(), deconv(), poly(), polyval(), residue(), compan().

Sol: We try Newton's method for various polynomials. We use N=poly(R) to provide the coefficients of a polynomial given the roots R. Then we use polynomial to factor the resulting polynomial. Finally, we use Newton's method and show that the iteration converges to the nearest root.

3.2 Eigenanalysis

At this point we turn a corner in the discussion toward the important topic of eigenanalysis, which starts with the computation of the eigenvalues of a matrix, and their eigenvectors. As briefly discussed on Sect. 2.3, eigenvectors are mathematical generalizations of resonances or modes, naturally found in physical systems.

When you pluck the string of a violin or guitar or hammer a bell or tuning fork, there are natural resonances that occur. These are the eigenmodes of the instrument. The frequency of each mode is related to the eigenvalue, which in physical terms is the frequency of the mode. But this idea goes way beyond simple acoustical instruments. Wave-guides and atoms are resonant systems. The resonances of the hydrogen atom are called the Lyman series, a special case of the Rydberg series and Rydberg atom (Bohr 1954; Gallagher 2005).

Thus this stream runs deep in both physics and eventually mathematics. In some real sense, eigenanalysis was what the Pythagoreans were seeking to understand. This relationship is rarely spoken about in the literature, but once you see it, it can never be forgotten, as it colors your entire view of all aspects of modern physics.

3.2.1 Eigenvalues of a Matrix

The method for finding eigenvalues is best described with an example. Starting from the matrix Eq. 2.6.15), the eigenvalues are defined by the eigenmatrix equation

$$\frac{1}{2} \begin{bmatrix} 1 & 1 \\ 2 & 0 \end{bmatrix} \begin{bmatrix} e_1 \\ e_2 \end{bmatrix} = \lambda \begin{bmatrix} e_1 \\ e_2 \end{bmatrix}. \tag{3.2.1}$$

The unknowns here are the eigenvalue λ and the eigenvector $\mathbf{e} = [e_1, e_2]^T$. First we find λ by subtracting the right from the left:

⁸ A MATLAB/Octave program that does this may be downloaded from https://jontalle.web.engr. illinois.edu/uploads/493/M/NewtonJPD.m.

⁹Appendix B) is an introduction to the topic of eigenanalysis for 2×2 matrices.

3.2 Eigenanalysis 89

$$\frac{1}{2} \begin{bmatrix} 1 & 1 \\ 2 & 0 \end{bmatrix} \begin{bmatrix} e_1 \\ e_2 \end{bmatrix} - \lambda \begin{bmatrix} e_1 \\ e_2 \end{bmatrix} = \frac{1}{2} \begin{bmatrix} 1 - 2\lambda & 1 \\ 2 & -2\lambda \end{bmatrix} \begin{bmatrix} e_1 \\ e_2 \end{bmatrix} = 0.$$

The only way this equation for e can have a non-trivial ($e_1 = e_2 = 0$) solution is if the matrix is singular. If it is singular, the determinant of the matrix is zero.

Example: The determinant in the above equation is the product of the diagonal elements minus the product of the off-diagonal elements, which results in the quadratic equation

$$-2\lambda(1 - 2\lambda) - 2 = 4\lambda^2 - 2\lambda - 2 = 0.$$

Completing the square gives

$$(\lambda - 1/4)^2 - (1/4)^2 - 1/2 = 0;$$

thus the roots (i.e., eigenvalues) are $\lambda_{\pm} = \frac{1\pm 3}{4} = \{1, -1/2\}.$

Exercise #16 Expand Eq. 3.2.1 and recover the quadratic equation. Sol:

$$(\lambda - 1/4)^2 - (1/4)^2 - 1/2 = \lambda^2 - \lambda/2 + (1/4)^2 - (1/4)^2 - 1/2 = 0.$$

Thus completing the square is the same as the original equation.

Exercise #17 Find the eigenvalues of the matrix of Eq. 2.6.9.

Sol: This is a minor variation on the previous example. Briefly, we have

$$\det\begin{bmatrix} 1 - \lambda & N \\ 1 & 1 - \lambda \end{bmatrix} = (1 - \lambda)^2 - N = 0.$$

Thus
$$\lambda_{+} = 1 \pm \sqrt{N}$$
.

Exercise #18 Starting with Eq. 3.2.1 and initial conditions $[x_1, y_1]^T = [1, 0]^T$, compute the first five values of $[x_n, y_n]^T$.

Sol: Here is a MATLAB/Octave code for computing $[x_n, y_n]^T$:

$$x=[1;0];$$
 $A=[1 1;2 0]/2;$
for $k=1:10; x(k+1)=A*x(:,k);$ end

which gives the rational $(x_n \in \mathbb{Q})$ sequence: 1, 1/2, 3/4, 5/8, 11/2⁴, 21/2⁵, 43/2⁶, 85/2⁷, 171/2⁸, 341/2⁹, 683/2¹⁰,

Exercise #19 Show that the solution to the mean-Fibonacci sequence (Eq. 2.6.14) is bounded, unlike that of the Fibonacci sequence. Explain what is going on.

Sol: Because the next value is the mean of the last two, the sequence is bounded. To see this one needs to compute the eigenvalues of the matrix in Eq. 2.6.15).

The key to the analysis of such equations is called eigenanalysis or the modalanalysis method (see Appendix B). The eigenvalues (eigenfrequencies) are also known as resonant frequencies in engineering and eigenmodes in physics. Eigenmodes describe the naturally occurring "ringing" found in physical wave-dominated boundary value problems and in resonant circuits. Each mode's eigenvalue quantifies the mode's natural complex frequency $s_k = \sigma_k + \omega_{kJ}$.

Complex eigenvalues result in damped modes having frequencies $s_k \in \mathbb{C}$, which decay in time as $\tau_k = 1/\sigma_k$ due to energy losses, as determined by σ_k .

Two modes that have exactly the same frequency are said to be degenerate. This is a very special condition representing a very high degree of symmetry. When two modes are slightly different in frequency, one hears a beating of the modes at the difference frequency (they are not degenerate). If they have different decay, the beats will die away with the shorter of the two time constants.

Common examples include tuning forks, pendulums, bells, and the strings of musical instruments (such as guitar and fiddles), all of which (except for tuning forks) have hundreds of modes (Fletcher and Rossing 2008; Morse 1948). For those interested in musical acoustics, these books are excellent.

3.2.2 Cauchy's Theorem and Eigenmodes

Cauchy's residue theorem (see Sect. 4.4) is used to find the time-domain response of each frequency-domain complex eigenmode. Thus eigenanalysis and eigenmodes of physics are the same thing (see Sect. 4.4) but are described using different notional methods. ¹⁰ The eigenanalysis method is summarized in Appendix B.3.

Taking a simple example of a 2×2 matrix $\mathcal{T} \in \mathbb{C}$, we start from the definition of the two eigenequations

$$\mathcal{T}\boldsymbol{e}_{+} = \lambda_{+}\boldsymbol{e}_{+} \tag{3.2.2}$$

corresponding to two eigenvalues $\lambda_{\pm} \in \mathbb{C}$ and two 2×1 eigenvectors $e_{\pm} \in \mathbb{C}$. **Example:** Assume that T is the Fibonacci matrix in Eq. 2.6.12.

The eigenvalues λ_{\pm} may be merged into a 2 \times 2 diagonal eigenvalue matrix

$$\Lambda = \begin{bmatrix} \lambda_+ & 0 \\ 0 & \lambda_- \end{bmatrix},$$

while the two eigenvectors e_+ and e_- are merged into a 2 \times 2 eigenvector matrix

$$E = [e_+, e_-] = \begin{bmatrix} e_1^+ & e_1^- \\ e_2^+ & e_2^- \end{bmatrix}, \tag{3.2.3}$$

¹⁰During the discovery or creation of quantum mechanics, two alternatives were developed: Schrödinger's differential equation method and Heisenberg's matrix method. Eventually it was realized the two were equivalent.

3.2 Eigenanalysis 91

corresponding to the two eigenvalues. Using matrix notation, we can write this compactly as

$$\mathcal{T}E = E\Lambda. \tag{3.2.4}$$

Note that while λ_+ and E_+ commute, $E\Lambda \neq \Lambda E$.

From Eq. 3.2.4 we may obtain two very important relations:

1. the diagonalization of \mathcal{T}

$$\Lambda = \mathbf{E}^{-1} \mathcal{T} \mathbf{E},\tag{3.2.5}$$

and

2. the eigenexpansion of T

$$\mathcal{T} = \mathbf{E} \Lambda \mathbf{E}^{-1}, \tag{3.2.6}$$

which is used for computing powers of \mathcal{T} (i.e., $\mathcal{T}^{100} = \mathbf{E} \Lambda^{100} \mathbf{E}^{-1}$).

Example: If we take

$$\mathcal{T} = \begin{bmatrix} 1 & 1 \\ 1 & -1 \end{bmatrix},$$

then the eigenvalues are given by $(1 - \lambda_{\pm})(1 + \lambda_{\pm}) = -1$; thus $\lambda_{\pm} = \pm \sqrt{2}$. This method of eigenanalysis is discussed on Sect. 3.7.8 and in Appendix B.2.

Exercise #20 Show that the geometric series formula holds for 2×2 matrices. Starting with the 2×2 identity matrix I_2 and $a \in \mathbb{C}$, with |a| < 1, show that

$$I_2(I_2 - aI_2)^{-1} = I_2 + aI_2 + a^2I_2^2 + a^3I_2^3 + \cdots$$

Sol: Multiply both sides by $I_2 - aI_2^k$ results in an identity

$$I_2 = I_2 + aI_2 + a^2I_2^2 + a^3I_2^3 + \dots - aI_2(aI_2 + a^2I_2^2 + a^3I_2^3 + \dots)$$

= $[1 + (a + a^2 + a^3 + \dots) - (a + a^2 + a^3 + a^4 + \dots)]I_2$
= I_2 .

This equality requires that the two series converge, but only if |a| < 1.

When the matrix T is not a square matrix, Eq. 3.2.6 may be generalized as

$$\mathcal{T}_{m,n} = \mathbf{U}_{m,m} \Lambda_{m,n} \mathbf{V}_{n,n}^{\dagger}.$$

This useful generalization of eigenanalysis is called singlar value decomposition (SVD). To see this use the MATLAB/Octave command [U, L, V] = svd(A) where A is a rectangular (non-square) matrix.

Exercise #21 Verify that $\Lambda = E^{-1}AE$.

Sol: We shall work with the unnormalized eigenmatrix $c\mathbf{E}$, where $c = \sqrt{\sqrt{2}^2 + 1} = \sqrt{3}$. To compute the inverse of $c\mathbf{E}$, 1) swap the diagonal values, 2) change the sign of the off diagonals, and 3) divide by the determinant Δ :

$$(c\mathbf{E})^{-1} = \frac{1}{2c\sqrt{2}} \begin{bmatrix} 1 & \sqrt{2} \\ -1 & \sqrt{2} \end{bmatrix} = \frac{1}{2c} \begin{bmatrix} 0.707 & 1 \\ -0.707 & 1 \end{bmatrix}.$$

We wish to show that $\Lambda = E^{-1}AE$

$$\frac{1}{2e^{1}} \begin{bmatrix} 0.707 & 1 \\ -0.707 & 1 \end{bmatrix} \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} e^{1} \begin{bmatrix} \sqrt{2} & -\sqrt{2} \\ 1 & 1 \end{bmatrix} = \begin{bmatrix} 1 + \sqrt{2} & 0 \\ 0 & 1 - \sqrt{2} \end{bmatrix}$$

which is best verified with MATLAB/Octave.

Exercise #22 Verify that $A = E \Lambda E^{-1}$.

Sol: We wish to show that

$$\begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix} = \frac{1}{\sqrt{3}} \begin{bmatrix} \sqrt{2} & -\sqrt{2} \\ 1 & 1 \end{bmatrix} \cdot \begin{bmatrix} 1 + \sqrt{2} & 0 \\ 0 & 1 - \sqrt{2} \end{bmatrix} \cdot \frac{\sqrt{3}}{2\sqrt{2}} \begin{bmatrix} 1 & \sqrt{2} \\ -1 & \sqrt{2} \end{bmatrix}.$$

All the above solutions have been verified with Octave.

Eigenmatrix diagonalization is helpful in generating solutions for finding the solutions of Pell's and Fibonacci's equations using transmission matrices.

Example: If the matrix corresponds to a transmission line, the eigenvalues have units of seconds [s]

$$\begin{bmatrix} V^+ \\ V^- \end{bmatrix}_n = \begin{bmatrix} e^{-sT_o} & 0 \\ 0 & e^{sT_o} \end{bmatrix} \begin{bmatrix} V^+ \\ V^- \end{bmatrix}_{n+1}.$$
 (3.2.7)

In the time domain the forward traveling wave $v_{n+1}^+(t-(n+1)T_o) = v_n^+(t-nT_o)$ is delayed by T_o . Two applications of the matrix delay the signal by $2T_o$.

Summary: The GCD (Euclidean algorithm), Pell's equation, and the Fibonacci sequence may all be written as compositions of 2×2 matrices. Thus Pell's equation and the Fibonacci sequence are special cases of the 2×2 matrix composition

$$\begin{bmatrix} x \\ y \end{bmatrix}_{n+1} = \begin{bmatrix} a & b \\ c & d \end{bmatrix} \begin{bmatrix} x \\ y \end{bmatrix}_{n}.$$

This is an important and common thread of these early mathematical findings. This 2×2 linearized matrix recursion plays a special role in physics, mathematics, and engineering because one-dimensional system equations are solved using the 2×2 eigenanalysis method. More than several thousand years of mathematical trial and error set the stage for this breakthrough. But it took even longer to be fully appreciated.

3.2 Eigenanalysis 93

The key idea of the 2×2 matrix solution, widely used in modern engineering, can be traced back to Brahmagupta's solution of Pell's equation for arbitrary N. Brahmagupta's recursion, identical to that of the Pythagoreans' N=2 case (see Eq. 2.6.9), eventually led to the concept of linear algebra, defined by the simultaneous solutions of many linear equations. The recursion by the Pythagoreans (sixth century BCE) predated the creation of algebra by al-Khwarizmi (ninth century CE), as seen in Fig. 1.1.

3.2.3 Taylor Series

An analytic function is one that meets these criteria:

1. It may be expanded in a Taylor series:

$$P(x) = \sum_{n=0}^{\infty} c_n (x - x_o)^n.$$
 (3.2.8)

- 2. It converges for $|x x_o| < 1$, called the region of convergence (RoC), with coefficients c_n .
- 3. The Taylor series coefficients c_n are defined by taking derivatives of P(x) and evaluating them at the expansion point x_o —namely,

$$c_n = \frac{1}{n!} \frac{d^n}{dx^n} P(x) \bigg|_{x = x_0}.$$
 (3.2.9)

4. Although P(x) may be multivalued, the Taylor series is always single-valued.

Exercise #23 Verify that c_0 and c_1 of Eq. 3.2.8 follow from Eq. 3.2.9.

Sol: To obtain c_0 , for n=0, there is no derivative (d^0/dx^0) indicates no derivative is taken), so we must simply evaluate $P(x-x_o)=c_0+c_1(x-x_o)+\cdots$ at $x=x_o$, leaving c_0 . To find c_1 , we take one derivative, which results in $P'(x)=c_1+2c_2(x-x_o))+\cdots$. Evaluating this at $x=x_o$ leaves c_1 . Each time we take a derivative we reduce the degree of the series by 1, leaving the next constant term.

Exercise #24 Suppose we truncate the Taylor series expansion to *N* terms. What is the name of such functions?

Sol: When an infinite series is truncated, the resulting function is an Nth-degree polynomial:

$$P_N(x) = \sum_{n=0}^{N} = c_0 + c_1(x - x_o) + c_2(x - x_o)^2 + \dots + c_N(x - x_o)^N.$$

We can find c_0 by evaluating $P_N(x)$ at the expansion point x_o , since from the above formula $P_N(x_o) = c_0$. From the Taylor formula, $c_1 = P'_N(x)|_{x_o}$.

Exercise #25 How many roots do $P_N(x)$ and $P'_N(x)$ have?

Sol: According to the fundamental theorem of algebra, $P_N(x)$ has N roots and $P'_N(x)$ has N-1 roots. The Gauss–Lucas theorem states that the N-1 roots of $P'_N(x)$ lie inside the convex hull of the N roots of $P_N(x)$ (see Sect. 3.1.3).

Exercise #26 Would it be possible to find an inverse Gauss–Lucas theorem, that states where the roots of the integral of a polynomial might be?

Sol: To the best of my knowledge this problem has not been addressed. With each integral there is a new degree of freedom that must be accommodated, expanding the convex hull.

Properties: The Taylor formula is a prescription for how to uniquely define the coefficients c_n . Without the Taylor series formula, we would have no way of determining c_n . The proof of the Taylor formula is transparent; The coefficients may be determined by simply taking successive derivatives of Eq. 3.2.8 and then evaluating the result at the expansion point. If P(x) is analytic, then this procedure will always be successful. If P(x) fails to have a derivative of any order, then the function is not analytic and Eq. 3.2.8 is not valid.

The Taylor series representation of P(x) has special applications for solving differential equations for these reasons:

- 1. It is single-valued.
- 2. The series if valid inside the RoC (an open set).
- 3. All its derivatives and integrals are uniquely defined.
- 4. It may be continued into the complex plane by extending $x \in \mathbb{C}$. This extension is necessary because the eigenvalues are typically in \mathbb{C} . In fact the only reasonable eigenvalues must be complex, having negative real parts. If the real part of λ_k is zero, the solution is lossless, thus never dies away, which is non-physical in the macroscopic world. If it is positive, the solution is unstable (blows up). Typically this involves expanding the series about a different expansion point.

Analytic continuation: A limitation of the Taylor series expansion is that it is not valid outside of its RoC. One method for working with this limitation is to move the expansion point. This is called analytic continuation. However, analytic continuation is a non-trivial operation because: (1) It requires manipulating an infinite number of derivatives of P(x), (2) at the new expansion point x_o , where (3) $P(x - x_o)$ may not have derivatives, due to possible singularities. (4) Thus one needs to know where the singularities of P(s) are in the complex s plane. Due to these many problems analytic continuation is rarely used, other than as an important theoretical concept.

Every Taylor series is a single-valued representation because powers of the variable are single-valued. Single valuedness is key feature to the series representation. However functions have regions where the series is not valid. This is best seen with a simple example using the geometric series

$$f(s) = \frac{1}{1 - as} = \sum_{n=0}^{\infty} (as)^n, |as| < 1$$

¹¹Quantum eigenstates are lossless.

3.2 Eigenanalysis 95

with $a, s \in \mathbb{C}$. Note that f(s) has a pole at $s_0 = 1/a$ and residue 1/a.

However f(s) is perfectly well defined for |as| > 1, for which it has a different series expansion. If we let s = 1/z we find

$$f(z) = \frac{1}{1 - a/z} = \frac{-z/a}{1 - z/a} = -\frac{z}{a} \sum_{n=0}^{\infty} \left(\frac{z}{a}\right)^n, \quad |z/a| < 1.$$

Expressed in terms of z = 1/s we have that |sa| > 1.

Thus the first expansion is good inside the circle |s| < 1/a while the second is valid outside the circle. While each series is single valued within its RoC, f(s) is valid everywhere, except at the pole s = 1/a, where it is singular.

Example: The similar case is the geometric series P(x) = 1/(j-x) about the expansion point x = 1. The function P(x) is defined everywhere, except at the singular point x = j, whereas the geometric series is valid for |x| < 1. However P(x) is valid for |x| > 1. For example P(10) = 1/(j-10) = (j+10)/(j+10)(j-10) = -(j+10)/101.

Role of the Taylor series: The Taylor series plays a key role in the mathematics of differential equations and their solution, as the coefficients of the series uniquely determine the analytic series representation via its derivatives. The implications and limitations of the power series representation are very specific: If the series fails to converge (i.e., outside the RoC), it is meaningless.

Every differential equation has as many independent solutions as it has eigenvalues. To obtain these solutions we must use the Taylor series, with its single-value property, to uniquely represent each solution. The general solution is then the weighted sum over the independent solutions. This theory trivially follows from the Cauchy residue theorem CT-3 (Eq. 4.5.3).

Starting from a differential equation, it may be transformed to a matrix equation using the companion matrix (Sect. 3.1.3) having K eigenvalues $\lambda_1, \dots, \lambda_k, \dots, \lambda_K$, with a general solution

$$f(t; C_k) = \sum_{k=1}^K C_k e^{s_k t}.$$

The constants $C_k \in \mathbb{C}$ are determined using the initial conditions.

A very important fact about the RoC: It is relevant to only the series, not the function being expanded. Typically the function has a pole at the radius of the RoC, beyond which the series fails to converge. However, the function being expanded is valid everywhere (other than at its poles). This point has been inadequately explained in many text books. In addition, the RoC is the region of divergence (RoD), which is the RoC's complement.

The Taylor series does not need to be infinite to converge to the function it represents, since it obviously works for any polynomial $P_N(x)$ of degree N. But in the finite case $(N < \infty)$, the RoC is infinite and the series is the function $P_N(x)$ exactly, everywhere. Of course, $P_N(x)$ is a polynomial of degree N. When $N \to \infty$, the

Taylor series is valid only within the RoC, and it is (typically) the representation of the reciprocal of a polynomial.

These properties are both the curse and the blessing of the analytic function. On the positive side, analytic functions are the ideal starting point for solving differential equations, which is exactly how they were used by Newton and others. Analytic functions are "smooth," since they are infinitely differentiable, with coefficients given by Eq. 3.2.9. They are single-valued, so there can be no ambiguity in their interpretation. On the negative side, they only represent the function within the RoC, which depends on the expansion point.

Two well-known analytic functions are the geometric series (|x| < 1)

$$\frac{1}{1-x} = 1 + x + x^2 + x^3 + \dots = \sum_{n=0}^{\infty} x^n$$
 (3.2.10)

and the exponential series $(|x| < \infty)$

$$e^{x} = 1 + x + \frac{1}{2}x^{2} + \frac{1}{3 \cdot 2}x^{3} + \frac{1}{4 \cdot 3 \cdot 2}x^{4} + \dots = \sum_{n=0}^{\infty} \frac{1}{n!}x^{n}.$$
 (3.2.11)

Exercise #27 Provide the Taylor series expression for the following functions:

$$F_1(x) = \int_0^x \frac{1}{1 - x} dx \tag{3.2.12}$$

Sol:
$$F_1(x) = x + \frac{1}{2}x^2 + \frac{1}{3}x^3 + \cdots$$

$$F_2(x) = \frac{d}{dx} \frac{1}{1-x} \tag{3.2.13}$$

Sol:
$$F_2(x) = 1 + 2x + 3x^2 + \cdots$$

$$F_3(x) = \ln \frac{1}{1 - x} \tag{3.2.14}$$

Sol:
$$F_3(x) = 1 + \frac{1}{2}x + \frac{1}{3}x^2 + \cdots$$

$$F_4(x) = \frac{d}{dx} \ln \frac{1}{1 - x}$$
 (3.2.15)

Sol:
$$F_4(x) = 1 + x + x^2 + x^3 + \cdots$$

Exercise #28 Using symbolic manipulation (MATLAB, Octave, Mathematica), expand the function F(s) in a Taylor series and find the recurrence relationships among the Taylor coefficients c_n , c_{n-1} , c_{n-2} . Assume $a \in \mathbb{C}$ and $T \in \mathbb{R}$.

$$F(s) = e^{as}$$

3.2 Eigenanalysis 97

Sol: A Google search on *octave syms taylor* is useful. The MATLAB/Octave code to expand this in a Taylor series is

```
syms s
taylor(exp(s),s,0,'order',10)
```

Exercise #29 Find the coefficients of the following functions by the method of Eq. 3.2.9 and give the RoC.

1.
$$w(x) = \frac{1}{1-x}$$

Sol: From a straightforward expansion we know the coefficients are

$$\frac{1}{1-x_J} = 1 + x_J + (x_J)^2 + (x_J)^3 + \dots = 1 + x_J - x^2 + -jx^3 + \dots$$

Working this out using Eq. 3.2.9 is more work:

$$c_0 = \frac{1}{0!} w \big|_0 = 1; c_1 = \frac{1}{1!} \frac{dw}{dx} \big|_0 = -\frac{-J}{(1-xJ)^2} \big|_{x=0} = J; \quad c_2 = \frac{1}{2!} \frac{d^2w}{dx^2} \big|_0 = \frac{1}{2!} \frac{-2}{(1-xJ)^3} \big|_0 = -1;$$

$$c_3 = \frac{1}{3!} \frac{d^3 w}{dx^3} \Big|_{0} = \frac{-j}{(1-xj)^4} \Big|_{0} = -j.$$

However, if we take derivatives of the series expansion, it is much easier and we can even figure out the term for c_n :

$$c_0 = 1; c_1 = \frac{d}{dx} \sum (jx)^n \Big|_0 = j; c_2 = \frac{1}{2!} \frac{d^2}{dx^2} \sum (jx)^n \Big|_0 = 2(j)^2;$$

$$c_3 = \frac{1}{3!} \frac{d^3}{dx^3} \sum (jx)^n \Big|_0 = (j)^3 = -j;$$

$$\cdots, c_n = \frac{1}{n!} j^n n! = j^n.$$

The RoC is
$$|xj| = |x| < 1$$
.

2. $w(x) = e^{xj}$.

Sol: $c_n = \frac{1}{n!} J^n$. The RoC is $|x| < \infty$. Functions with an RoC of ∞ are called *entire*. Thus $c_n = J c_{n-1} / n$.

Exercise #30 Show that $Z(s) = 1/\sqrt{s}$ is positive-real but not a Brune impedance. **Sol:** Since it may not be written as the ratio of two polynomials, it is not in the Brune impedance class. If we write $Z(s) = |Z(s)|e^{\phi J}$ in polar coordinates, since $-\pi/4 \le \phi \le \pi/4$ when $|\angle s| < \pi/2$, Z(s) satisfies the Brune condition and thus is positive-real.

Determining the region of convergence (RoC): Determining the RoC for a given analytic function is quite important and may not always be obvious. In general the RoC is a circle whose radius extends from the expansion point out to the nearest

pole. Thus when the expansion point is moved, the RoC changes, since the location of the pole is fixed.

Example: For the geometric series (Eq. 3.2.10), the expansion point is $x_o = 0$ and the RoC is |x| < 1, since 1/(1-x) has a pole at x = 1. We may move the expansion point by a linear transformation—for example, by replacing x with z + 3. Then the series becomes 1/((z + 3) - 1) = 1/(z + 2), so the RoC becomes 3 because in the z plane the pole has moved to -2.

Example: A second important example is the function $1/(x^2 + 1)$, which has the same RoC as the geometric series, since it may be expressed in terms of its residue expansion (also called its partial fraction expansion)

$$\frac{1}{x^2+1} = \frac{1}{(x+1j)(x-1j)} = \frac{1}{2j} \left(\frac{1}{x-1j} - \frac{1}{x+1j} \right).$$

Each term has an RoC of $|x| < |1_J| = 1$. The amplitude of each pole is called the *residue*, defined in Eq. 4.5.4. The residue for the pole at 1_J is $1/2_J$.

The roots must be found by factoring the polynomial (e.g., Newton's method). Once the roots are known, the residues are best found via complex linear algebra.

In summary, the function $1/(x^2 + 1)$ is the sum of two geometric series, with poles at $\pm 1_J$, which is not initially obvious because the roots are complex and conjugate. Only when the function is factored does it become clear what is going on.

Exercise #31 Verify that the above expression is correct and show that the residues are $\pm 1/2J$.

Sol: We cross-multiply and cancel, leaving 1, as required. The RoC is the coefficient on the pole. Thus the residue of the pole at x_1 is 1/2.

Exercise #32 Find the residue of $\frac{d}{dz}z^{\pi}$.

Sol: Taking the derivative gives $\pi z^{\pi-1}$, which has a pole at z=0. Applying the formula for the residue (Eq. 4.5.4), we find

$$c^{-1} = \pi \lim_{z \to 0} z z^{\pi - 1} = \pi \lim_{z \to 0} z^{\pi} = 0.$$

Thus the residue is zero.

3.2.4 Analytic Functions

Any function that has a Taylor series expansion is called an *analytic function*. Within the RoC, the series expansion defines a single-valued function. Polynomials 1/(1-x) and e^x are examples of analytic functions that are real functions of their real argument x.

Every analytic function has a corresponding differential equation, which is determined by the coefficients a_k of the analytic power series. An example is the exponential, which has the property that it is the eigenfunction of the derivative operation

3.2 Eigenanalysis 99

$$\frac{d}{dx}e^{ax} = ae^{ax},$$

which may be verified using Eq. 3.2.11. This relationship is a common definition of the exponential function, which is special because it is the eigenfunction of the derivative.

The complex analytic power series (i.e., complex analytic functions) may also be integrated term by term, since

$$\int_{-\infty}^{x} f(x)dx = \sum_{k=1}^{\infty} \frac{a_k}{k+1} x^{k+1}.$$
 (3.2.16)

Newton took full advantage of this property of the analytic function and used the analytic series (Taylor series) to solve analytic problems, especially for working out integrals. This enabled him to solve differential equations. To fully understand the theory of differential equations, one must master single-valued analytic functions and their analytic power series.

Single- versus multivalued functions: Polynomials and their ∞-degree extensions (analytic functions) are single-valued: For each x there is a single value for $P_N(x)$. The roles of the domain and codomain may be swapped to obtain an inverse function with properties that can be very different from those of the function. For example, $y(x) = x^2 + 1$ has the inverse $x = \pm \sqrt{y-1}$, which is double-valued and complex when y < 1. Periodic functions such as $y(x) = \sin(x)$ are even more "exotic," since $x(y) = \arcsin(x) = \sin^{-1}(x)$ has an infinite number of x(y) values for each y. This problem was first addressed in Bernhard Riemann's 1851 Ph.D. thesis, written while he was working with Gauss.

Exercise #33 Let $y(x) = \sin(x)$. Then $dy/dx = \cos(x)$. Show that $dx/dy = \pm 1/\sqrt{1-y^2}$.

Sol: Since $\sin^2 x + \cos^2 x = 1$, it follows that $y^2(x) + (dy/dx)^2 = 1$. Thus $dy/dx = \pm \sqrt{1 - y^2}$. Taking the reciprocal gives the result.

To fully understand this, Google "implicit function theorem" (D'Angelo 2017, p. 104).

Exercise #34 Evaluate the integral

$$I(y) = \int^{y} \frac{dy}{\sqrt{1 - y^2}}.$$

Sol: From the previous Exercise we know that

$$x(y) = \int_{-\infty}^{x} dx = \int_{-\infty}^{y} \frac{dy}{\sqrt{1 - y^2}}.$$

But since $y(x) = \sin(x)$, it follows that $x(y) = \sin^{-1} y = \arcsin(y)$.

Exercise #35 Find the Taylor series coefficients of $y = \sin(x)$ and $x = \sin^{-1}(y)$. Note that $\log e^s = s$ and

$$\sin(\sin^{-1}(s)) = \sin^{-1}(\sin(s)) = 1.$$

Hint: Use symbolic Octave. Note $\sin^{-1}(y) = \arcsin(y)$. **Sol:** syms s; taylor($\sin(s)$, 'order', 10);

$$\sin(s) = s - s^3/3! + s^5/5! - s^7/7! + \cdots$$

and syms s; taylor(asin(s), 'order', 15);

$$\arcsin(s) = s + \frac{1}{6}s^2 + \frac{3}{40}s^5 + \frac{5}{112}s^7 + \frac{35}{1152}s^9 + \frac{63}{2816}s^{11} + \frac{231}{13312}s^{13} + \cdots$$

$$= s + \frac{1}{3 \cdot 2^1}s^3 + \frac{3}{5 \cdot 2^3}s^5 + \frac{5}{7 \cdot 2^4}s^7 + \frac{7 \cdot 5}{9 \cdot 2^7}s^9 + \frac{7 \cdot 3^2}{11 \cdot 2^8}s^{11} + \frac{3 \cdot 7 \cdot 11}{13 \cdot 2^{10}}s^{13} + \cdots$$

Note that every complex analytic function may be expanded in a Taylor series, within its RoC. It follows that the inverse is also complex analytic, as demonstrated in this case using symbolic algebra.

Exercise #36 What is the necessary condition such that if dy/dx = F(x), then dx/dy = 1/F(x)?

Sol: This will be true when df(x)/dx = F(x) is complex analytic because the Fundamental Theorem of Complex Calculus (FTCC) (see Sect. 4.2.2) defines the antiderivative. In this case $dy/dx = (dx/dy)^{-1}$ (except at singular points, where it is not analytic).

3.2.5 Brune Impedances

A special family of functions is formed from ratios of two polynomials Z(s) = N(s)/D(s) commonly used to define an impedance Z(s), called a *Brune impedance*. Impedance functions are a special class of complex analytic functions because they must have a nonnegative real part

$$\Re Z(s) = \Re \frac{N(s)}{D(s)} \ge 0$$

so as to obey conservation of energy. A physical Brune impedance cannot have a negative resistance (the real part); otherwise, it would act like a power source, violating conservation of energy. Most impedances used in engineering applications are in the class of Brune impedances, defined by the ratio of two polynomials of degrees M and N:

3.2 Eigenanalysis 101

$$Z_{\text{Brune}}(s) = \frac{P_M(s)}{P_N(s)} = \frac{s^M + a_1 S^{M-1} + \dots + a_0}{s^N + b_1 S^{N-1} + \dots + b_0},$$
 (3.2.17)

where $M = N \pm 1$ (i.e., $N = M \pm 1$). This fraction of polynomials is sometimes known as a *Padé approximation*, with poles and zeros, defined as the complex roots of the two polynomials. The key property of the Brune impedance is that the real part of the impedance is nonnegative (positive or zero) in the right s half-plane:

$$\Re Z(s) = \Re \left[R(\sigma, \omega) + j X(\sigma, \omega) \right] = R(\sigma, \omega) \ge 0 \qquad \text{for } \Re s = \sigma \ge 0.$$
(3.2.18)

Since $s = \sigma + \omega J$, the complex frequency (s) right half-plane (RHP) corresponds to $\Re s = \sigma \ge 0$. This condition defines the class of positive-real functions, also known as the *Brune condition*, which is frequently written in the abbreviated form

$$\Re Z(\Re s \ge 0) \ge 0. \tag{3.2.19}$$

As a result of this positive-real (PR) constraint, the subset of Brune impedances (those given by Eq. 3.2.17 and satisfying Eq. 3.2.18) must be complex analytic in the entire right s half-plane. This is a powerful constraint that places strict limitations on the locations of both the poles and the zeros of every positive-real Brune impedance. A **little history:** The key idea that every impedance Z(s) must be complex analytic and its real part be nonnegative ($\Re Z(s) \ge 0$) for $\sigma = \Re s > 0$, as first proposed by Otto Brune in his Ph.D. thesis at MIT. His supervised was Ernst A. Guillemin, an MIT electrical engineering professor who played an important role in the development of circuit theory and likely was a student of Arnold Sommerfeld. Other MIT advisors were Norbert Wiener and Vannevar Bush. Brune's primary, but non-MIT advisor was W. Cauer, who was trained in nineteenth-century German mathematics, perhaps under Sommerfeld (Brune 1931b).

3.2.6 Complex Analytic Functions

We are given that the argument of an analytic function F(x) is complex; that is, $x \in \mathbb{R}$ is replaced by $s = \sigma + \omega j \in \mathbb{C}$. Recall that $\mathbb{R} \subset \mathbb{C}$. Thus

$$F(s) = \sum_{n=0}^{\infty} c_n (s - s_o)^n,$$
 (3.2.20)

with $c_n \in \mathbb{C}$. In this case, that function is said to be a *complex analytic*. An important example is when the exponential becomes complex, since

 $^{^{12}}$ It must be noted that University of Illinois Professor "Mac" Van Valkenburg was arguably more influential in circuit theory during the same period. Mac's books are certainly more accessible, but perhaps less widely cited.

$$e^{st} = e^{(\sigma + \omega_J)t} = e^{\sigma t}e^{J\omega t} = e^{\sigma t}\left[\cos(\omega t) + j\sin(\omega t)\right]. \tag{3.2.21}$$

Taking the real part gives

$$\Re\{e^{st}\} = e^{\sigma t} \frac{e^{\omega Jt} + e^{-\omega Jt}}{2} = e^{\sigma t} \cos(\omega t)$$

and $\Im\{e^{st}\}=e^{\sigma t}\sin(\omega t)$. Once the argument is allowed to be complex, it becomes obvious that the exponential and circular functions are fundamentally related. This exposes the family of entire circular functions [i.e., e^s , $\sin(s)$, $\cos(s)$, $\tan(s)$, $\cosh(s)$, $\sinh(s)$] and their inverses [$\ln(s)$, $\arcsin(s)$, $\arccos(s)$, $\arctan(s)$, $\cosh^{-1}(s)$, $\sinh^{-1}(s)$], first fully elucidated by Euler in about 1750 (Stillwell 2010, p. 315).

Note that because $\sin(\omega t)$ is periodic, its inverse must be multivalued. What was needed is some systematic way to account for this multivalued property. This extension to multivalued functions is called a *branch cut*, invented by Riemann in his 1851 Ph.D. thesis, supervised by Gauss in the final years of Gauss's long life.

The Taylor series of a complex analytic function: However, there is a fundamental problem: We cannot formally define the Taylor series for the coefficients c_k until we have defined the derivative with respect to the complex variable dF(s)/ds, with $s \in \mathbb{C}$. Thus simply substituting s for x in an analytic function leaves a major hole in one's understanding of the complex analytic function.

It was Cauchy in 1814 (Fig. 3.1) who uncovered the much deeper relationships within complex analytic functions (see Sect. 3.11) by defining differentiation and integration in the complex plane, leading to several fundamental theorems of complex calculus, including the fundamental theorem of complex calculus and Cauchy's formula.

There seems to be some disagreement as to the status of multivalued functions: Are they functions, or is a function strictly single-valued? If so, then we are missing out on a host of interesting possibilities, including all the inverses of nearly every complex analytic function. For example, the inverse of a complex analytic function is a complex analytic function (e.g., e^s and $\log(s)$).

Impact of complex analytic mathematics on physics: It seems likely, if not obvious, that the success of Newton was his ability to describe physics using mathematics. He was inventing new mathematics at the same time he was explaining new physics. The same might be said for Galileo. It seems likely that Newton was extending the successful techniques and results of Galileo's work on gravity (Galileo 1638). Galileo died on January 8, 1642, and Newton was born January 4, 1643, just short of one year later. Obviously Newton was well aware of Galileo's great success and naturally would have been influenced by him (see p. 9).

The application of complex analytic functions to physics was dramatic, as may be seen in the six volumes on physics written by Arnold Sommerfeld (1868–1951), and from the productivity of his many (36) students (e.g., Debye, Lenz, Ewald, Pauli, Guillemin, Bethe, Heisenberg, Morse, and Seebach, to name a few), notable coworkers (Leon Brillouin), and others (John Bardeen) upon whom Sommerfeld had a strong influence. Sommerfeld is famous for training many students who were awarded the Nobel Prize in Physics, yet he never won a Nobel Prize (the prize is not

3.2 Eigenanalysis 103

awarded in mathematics). Sommerfeld brought mathematical physics (the merging of physical and experimental principles via mathematics) to a new level with the use of complex integration of analytic functions to solve otherwise difficult problems, thus following the lead of Newton, who used real integration of Taylor series to solve differential equations (Brillouin 1960, Chap. 3 by Sommerfeld).

3.3 Problems AE-1

Topics of this homework: Fundamental theorem of algebra, polynomials, analytic functions and their inverse, convolution, Newton's root-finding method, Riemann zeta function. Deliverables: Answers to problems.

Note: The term analytic is used in two different ways. (1) An analytic function is a function that may be expressed as a locally convergent power series; (2) analytic geometry refers to geometry using a coordinate system.

3.3.1 Polynomials and the Fundamental Theorem of Algebra (FTA)

Problem #1 A polynomial of degree N is defined as

$$P_N(x) = a_0 + a_1 x + a_2 x^2 + \dots + a_N x^N.$$

- -1.1: How many coefficients a_n does a polynomial of degree N have?
- -1.2: How many roots does $P_N(x)$ have?

Problem #2 The fundamental theorem of algebra (FTA)

- -2.1: State and then explain the FTA.
- -2.2: Using the FTA, prove your answer to question 1.2. Hint: Apply the FTA to prove how many roots a polynomial $P_N(x)$ of order N has.

Problem #3 Consider the polynomial function $P_2(x) = 1 + x^2$ of degree N = 2 and the related function $F(x) = 1/P_2(x)$. What are the roots (e.g., zeros) x_{\pm} of $P_2(x)$? Hint: Complete the square on the polynomial $P_2(x) = 1 + x^2$ of degree 2, and find the roots.

Problem #4 F(x) may be expressed as $(A, B, x_{\pm} \in \mathbb{C})$

$$F(x) = \frac{A}{x - x_{+}} + \frac{B}{x - x_{-}},$$
 (AE-1.1)

where x_{\pm} are the roots (zeros) of $P_2(x)$, which become the *poles* of F(x); A and B are the *residues*. The expression for F(x) is sometimes called a *partial fraction expansion* or *residue expansion*, and it appears in many engineering applications.

- -4.1: Find $A, B \in \mathbb{C}$ in terms of the roots x_+ of $P_2(x)$.
- -4.2: Verify your answers for A and B by showing that this expression for F(x) is indeed equal to $1/P_2(x)$.
 - -4.3: Give the values of the poles and zeros of $P_2(x)$.
 - -4.4: Give the values of the poles and zeros of $F(x) = 1/P_2(x)$.

3.3.2 Analytic Functions

Overview: Analytic functions are defined by infinite (power) series. The function f(x) is said to be *analytic* at any value of constant $x = x_o$, where there exists a convergent power series

$$P(x) = \sum_{n=0}^{\infty} a_n (x - x_o)^n$$

such that $P(x_o) = f(x_o)$. The point $x = x_o$ is called the *expansion point*. The region around x_o such that $|x - x_o| < 1$ is called the *radius of convergence* or region of convergence (RoC). The local power series for f(x) about $x = x_o$ is defined by the Taylor series:

$$f(x) \approx f(x_o) + \frac{df}{dx} \Big|_{x=x_o} (x - x_o) + \frac{1}{2!} \frac{d^2 f}{dx^2} \Big|_{x=x_o} (x - x_o)^2 + \cdots$$
$$= \sum_{n=0}^{\infty} \frac{1}{n!} \frac{d^n}{dx^n} f(x) \Big|_{x=x_o} (x - x_o)^n.$$

Two classic examples are the geometric series¹³ where $a_n = 1$,

$$\frac{1}{1-x} = 1 + x + x^2 + x^3 + \dots = \sum_{n=0}^{\infty} x^n,$$
 (AE-1.2)

and the exponential function where $a_n = 1/n!$, Eq. 3.2.11. The coefficients for both series may be derived from the Taylor formula.

Problem #5 The geometric series

-5.1: What is the *region of convergence* (RoC) for the power series Eq. AE-1.2 of 1/(1-x) given above—for example, where does the power series P(x) converge to the function value f(x)? State your answer as a condition on x.

Hint: What happens to the power series when x > 1?

- -5.2: In terms of the pole, what is the RoC for the geometric series in Eq. AE-1.2?
- -5.3: How does the RoC relate to the location of the pole of 1/(1-x)?

¹³The geometric series is *not* defined as the function 1/(1-x), it is defined as the series $1+x+x^2+x^3+\cdots$, such that the ratio of consecutive terms is x.

3.3 Problems AE-1 105

- −5.4: Where are the zeros, if any, in Eq. AE-1.2?
- -5.5: Assuming x is in the RoC, prove that the geometric series correctly represents 1/(1-x) by multiplying both sides of Eq. AE-1.2 by (1-x).

Problem #6 Use the geometric series to study the degree N polynomial. It is very important to note that all the coefficients c_n of this polynomial are 1.

$$P_N(x) = 1 + x + x^2 + \dots + x^N = \sum_{n=0}^{N} x^n.$$
 (AE-1.3)

-6.1: Prove that

$$P_N(x) = \frac{1 - x^{N+1}}{1 - x}. (AE-1.4)$$

- -6.2: What is the RoC for Eq. AE-1.3?
- -6.3: What is the RoC for Eq. AE-1.4?
- -6.4: How many poles does $P_N(x)$ (Eq. AE-1.3) have? Where are they?
- -6.5: How many zeros does $P_N(x)$ (Eq. AE-1.4) have? State where are they in the complex plane.
- -6.6: Explain why Eqs. AE-1.3 and AE-1.4 have different numbers of poles and zeros.
- -6.7: Is the function 1/(1-x) analytic outside of the RoC stated in the first question in Problem #5? Hint: Can it be represented by a different power series outside this RoC?
- -6.8: Extra credit. Evaluate $P_N(x)$ at x = 0 and x = 0.9 for the case of N = 100, and compare the result to that from MATLAB.

```
%sum the geometric series and P_100(0.9) clear all; close all; format long N=100; x=0.9; S=0; for n=0:N S=S+x^n end P100=(1-x^n(N+1))/(1-x); disp(sprintf('S= %g, P100= %g, error= %g',S,P100, S-P100))
```

Problem #7 The exponential series

- −7.1: What is the RoC for the exponential series Eq. 3.2.11?
- -7.2: Let x = j in Eq. 3.2.11, and write out the series expansion of e^x in terms of its real and imaginary parts.
- -7.3: Let $x = j\theta$ in Eq. 3.2.11, and write out the series expansion of e^x in terms of its real and imaginary parts. How does your result relate to Euler's identity $(e^{j\theta} = \cos(\theta) + j\sin(\theta))$?

3.3.3 Inverse Analytic Functions and Composition

Overview: It may be surprising, but every analytic function has an inverse function. Starting from the function $(x, y \in \mathbb{C})$

$$y(x) = \frac{1}{1 - x}$$

the inverse is

$$x = \frac{y - 1}{y} = 1 - \frac{1}{y}.$$

Problem #8 Consider the inverse function described above

- -8.1: Where are the poles and zeros of x(y)?
- -8.2: Where (for what condition on y) is x(y) analytic?

Problem #9 Consider the exponential function $z(x) = e^x$ $(x, z \in \mathbb{C})$.

- -9.1: Find the inverse x(z).
- -9.2: Where are the poles and zeros of x(z)?
- -9.3: If y(s) = 1/(1-s) and $z(s) = e^s$, compose these two functions to obtain $(y \circ z)(s)$.

Give the expression for $(y \circ z)(s) = y(z(s))$.

- -9.4: Where are the poles and zeros of $(y \circ z)(s)$?
- -9.5: Where (for what condition on x) is $(y \circ z)(x)$ analytic?

3.3.4 Convolution

Multiplying two short or simple polynomials is not demanding. However, if the polynomials have many terms, it can become tedious. For example, multiplying two 10th-degree polynomials is not something one would want to do every day.

An alternative is a method called *convolution*, as described in Sect. 3.4.

Problem #10 Convolution of sequences. Practice convolution (by hand!!) using a few simple examples. Show your work!!! Check your solution using MATLAB.

- -10.1: Convolve the sequence $\{0\ 1\ 1\ 1\ 1\}$ with itself.
- -10.2: Calculate $\{1, 1\} \star \{1, 1\} \star \{1, 1\}$.

Problem #11 Multiplying two polynomials is the same as convolving their coefficients.

$$f(x) = x^3 + 3x^2 + 3x + 1$$
$$q(x) = x^3 + 2x^2 + x + 2.$$

3.3 Problems AE-1 107

-11.1: In Octave/MATLAB, compute $h(x) = f(x) \cdot g(x)$ in two ways: (1) use the commands roots and poly, and (2) use the convolution command conv. Confirm that both methods give the same result.

-11.2: What is h(x)?

3.3.5 Newton's Root-Finding Method

Problem #12 Use Newton's iteration to find the roots of the polynomial

$$P_3(x) = 1 - x^3$$
.

- -12.1: Draw a graph describing the first step of the iteration starting with $x_0 = (1/2, 0)$.
 - -12.2: Calculate x_1 and x_2 . What number is the algorithm approaching?
- -12.3: Here is an Octave/MATLAB script for the $P_2(x)$ case. Modify it to find $P_3(x)$:

```
x(1)=1/2; %x(1)=0.9; %x(1)=-10

y(1)=x(1);

for n=2:10

x(n) = x(n-1) + (1-x(n-1)^2)/(2*x(n-1));

y(n) = (1+y(n-1)^2)/(2*x(n-1));

end

semilogy(abs(x)-1); hold on

semilogy(abs(7)-1,'or'); hold off
```

- -12.4: For n = 4, what is the absolute difference between the root and the estimate, $|x_r x_4|$?
- -12.5: Does Newton's method work for $P_2(x) = 1 + x^2$? If so, why? *Hint: What are the roots in this case?*
 - -12.6: What if we let $x_0 = (1 + j)/2$ for the case of $P_2(x) = 1 + x^2$?

3.3.6 Riemann Zeta Function $\zeta(s)$

Definitions and preliminary analysis: The zeta function $\zeta(s)$ is defined by the complex analytic power series

$$\zeta(s) \equiv \sum_{n=1}^{\infty} \frac{1}{n^s} = \frac{1}{1^s} + \frac{1}{2^s} + \frac{1}{3^s} + \frac{1}{4^s} + \cdots$$

This series converges, and thus is valid, only in the RoC given by $\Re s = \sigma > 1$, since there $|n^{-\sigma}| \le 1$. To determine its formula in other regions of the s plane, one must extend the series via analytic continuation (see Sect. 3.2.3).

Euler product formula: As Euler first published in 1737, one may recursively factor out the leading prime term, which results in Euler's product formula. ¹⁴ Multiplying $\zeta(s)$ by the factor $1/2^s$ and subtracting from $\zeta(s)$ remove all the terms $1/(2n)^s$ (e.g., $1/2^s + 1/4^s + 1/6^s + 1/8^s + \cdots$)

$$\left(1 - \frac{1}{2^s}\right)\zeta(s) = 1 + \frac{1}{2^s} + \frac{1}{3^s} + \frac{1}{4^s} + \frac{1}{5^s} + \dots - \left(\frac{1}{2^s} + \frac{1}{4^s} + \frac{1}{6^s} + \frac{1}{8^s} + \frac{1}{10^s} + \dots\right),\tag{AE-1.5}$$

which results in

$$\left(1 - \frac{1}{2^s}\right)\zeta(s) = 1 + \frac{1}{3^s} + \frac{1}{5^s} + \frac{1}{7^s} + \frac{1}{9^s} + \frac{1}{11^s} + \frac{1}{13^s} + \cdots$$
 (AE-1.6)

Problem #13 Questions about the Riemann zeta function.

- -13.1: What is the RoC for Eq. AE-1.6?
- -13.2: Repeat the algebra of Eq. AE-1.5 using the lead factor of $1/3^s$.
- -13.3: What is the RoC for Eq. AE-1.6?
- -13.4: Repeat the algebra of Eq. AE-1.5 for all prime scale factors (i.e., $1/5^s$, $1/7^s$, ..., $1/\pi_k^s$, ...) to show that

$$\zeta(s) = \prod_{\pi_k \in \mathbb{P}} \frac{1}{1 - \pi_k^{-s}} = \prod_{\pi_k \in \mathbb{P}} \zeta_k(s),$$
 (AE-1.7)

where π_p represents the pth prime.

-13.5: Given the product formula, identify the poles of $\zeta_p(s)$ ($p \in \mathbb{Z}$), which is important for defining the RoC of each factor. For example, the pth factor of Eq. AE-1.7, expressed as an exponential, is

$$\zeta_p(s) \equiv \frac{1}{1 - \pi_p^{-s}} = \frac{1}{1 - e^{-sT_p}},$$
 (AE-1.8)

where $T_p \equiv \ln \pi_p$.

-13.6: Plot Eq. AE-1.8 using zviz for p = 1. Describe what you see.

3.4 Root Classification by Convolution

Following the exploration of algebraic relationships by Fermat and Descartes, the first theorem was being formulated by d'Alembert. The idea behind this theorem is that every polynomial of degree N (Eq. 3.1.7) has at least one root. Every polynomial

¹⁴This is known as *Euler's sieve*, as distinguished from the Eratosthenes sieve.

may be written as the product of a monomial root and a second polynomial of degree of N-1. By the recursive application of this concept, it is clear that every polynomial of degree N has N roots. Today this result is known as the *fundamental theorem of algebra*:

Every polynomial equation P(z) = 0 has a solution in the complex numbers. As Descartes observed, a solution z = a implies that P(z) has a factor z - a. The quotient

$$Q(z) = \frac{P(z)}{z - a} = \frac{P(z)}{a} \left[1 + \frac{z}{a} + \left(\frac{z}{a}\right)^2 + \left(\frac{z}{a}\right)^3 + \cdots \right]$$
(3.4.1)

is then a polynomial of one lower degree. . . . We can go on to factorize P(z) into n linear factors.

— Stillwell (2010, p. 285).

The ultimate expression of this theorem is given by Eq. 3.1.7, which indirectly states that an nth degree polynomial has n roots. We shall use the term degree when speaking of polynomials and the term order when speaking of differential equations. A general rule is that order applies to the time domain and degree to the frequency domain, since the Laplace transform of a differential equation, having constant coefficients, of order N, is a polynomial of degree N in Laplace frequency s.

Today this theorem is so widely accepted we fail to appreciate it. Certainly at about the time you learned the quadratic formula, you were prepared to understand the concept of polynomials having roots. The simple quadratic case may be extended to a higher degree polynomial. The Octave/MATLAB command roots ($[1, a_2, a_1, a_0]$) provides the roots [s_1, s_2, s_3] of the cubic equation, defined by the coefficient vector [$[1, a_2, a_1, a_0]$]. The command poly ([s_1, s_2, s_3]) returns the coefficient vector. I don't know the largest degree that can be accurately factored numerically by MATLAB/Octave, but I'm sure it's well over $N = 10^3$. Today, finding the roots numerically is a solved problem.

The best way to gain insight into the polynomial factorization problem is through the inverse operation, multiplication of monomials. Given the roots x_k , there is a simple algorithm for computing the coefficients a_k of $P_N(x)$ for any n, no matter how large. This method is called *convolution*. Convolution is said to be a *trapdoor function*, since it is easy, while the inverse, factoring (deconvolution), is hard and analytically intractable for degree $N \ge 5$ (Stillwell 2010, p. 102).

3.4.1 Convolution of Monomials

As outlined by Eq. 3.1.7, a polynomial has two equivalent descriptions, first as a series with coefficients a_n and second as a product of monomial roots x_r . The question is What is the relationship between the coefficients and the roots? The simple answer is that they are related by convolution.

Let us start with the quadratic

$$(x+a)(x+b) = x^2 + (a+b)x + ab,$$
 (3.4.2)

where in vector notation [-a, -b] are the roots and [1, a + b, ab] are the coefficients. To see how the result generalizes, we may work out the coefficients for the cubic (N = 3). Multiplying the following three factors gives

$$(x-1)(x-2)(x-3) = (x^2 - 3x + 2)(x-3) = x(x^2 - 3x + 2) - 3(x^2 - 3x + 2) = x^3 - 6x^2 + 11x - 6.$$
(3.4.3)

When the roots are [1, 2, 3], the coefficients of the polynomial are [1, -6, 11, -6]. To verify, we can substitute the roots into the polynomial and show that they give zero. For example, $r_1 = 1$ is a root, since $P_3(1) = 1 - 6 + 11 - 6 = 0$.

As the degree increases, the algebra becomes more difficult. Imagine trying to work out the coefficients for N=100. What is needed is a simple way of finding the coefficients from the roots. Fortunately, convolution keeps track of the bookkeeping, formalizing the procedure, along with Newton's deconvolution method for finding the roots of polynomials (see Sect. 3.4.1).

Convolution of two vectors: To obtain the coefficients by convolution we may write the monomial roots as vectors [1, a] and [1, b]. Convolution is a recursive operation described by $[1, a] \star [1, b]$, where \star denotes convolution. The convolution of $[1, a] \star [1, b]$ is done as follows: Reverse one of the two monomials, padding unused elements with zeros. Next slide one monomial against the other, forming the local scalar product (element-wise multiply and add):

resulting in coefficients $[\ldots, 0, 0, 1, a+b, ab, 0, 0, \ldots]$.

If we reverse one of the polynomials and then take successive scalar products, all the terms in the sum of the scalar product correspond to the same power of x. This explains why the convolution of the coefficients gives the same answer as the product of the polynomials.

As seen from the above example, the positions of the first monomial coefficients are reversed and then slid across the second set of coefficients, the scalar product is computed, and the result is placed in the output vector. Outside the range shown, all the elements are zero. In summary,

$$[1,-1] \star [1,-2] = [1,-1-2,2] = [1,-3,2].$$

In general,

$$[a, b] \star [c, d] = [ac, bc + ad, bd].$$

Convolving a third term [1, -3] with [1, -3, 2] gives (Eq. 3.4.3)

$$[1, -3] \star [1, -3, 2] = [1, -3 - 3, 9 + 2, -6] = [1, -6, 11, -6],$$

which is identical to the cubic example found by the algebraic method.

When we convolve one monomial factor at a time, the overlap is always two elements; thus it is never necessary to compute more than two multiplications and one addition for each output coefficient. This greatly simplifies the operations (i.e., they are easily done in your head). Thus the final result is more likely to be correct. Comparing this to the algebraic method, we see that convolution has the clear advantage.

Exercise #37 What three nonlinear equations would we need to solve to find the roots of a cubic?

Sol: From our formula for the convolution of three monomials, we may find the nonlinear deconvolution relationships between the roots [-a, -b, -c] and the cubic's coefficients $[1, \alpha, \beta, \gamma]^{15}$:

$$(x+a) \star (x+b) \star (x+c) = (x+c) \star (x^2 + (a+b)x + ab)$$

$$= x \cdot (x^2 + (a+b)x + ab) + c \cdot (x^2 + (a+b)x + ab)$$

$$= x^3 + (a+b+c)x^2 + (ab+ac+cb)x + abc$$

$$= [1, a+b+c, ab+ac+cb, abc].$$

It follows that the nonlinear equations must be

$$\alpha = a + b + c$$

$$\beta = ab + ac + bc$$

$$\gamma = abc.$$

These equations may be solved by the classic cubic solution, which therefore is a deconvolution problem, also known as *long division of polynomials*. Therefore the following long division of polynomials must be true:

$$\frac{x^3 + (a+b+c)x^2 + (ab+ac+bc)x + abc}{x+a} = x^2 + (b+c)x + bc.$$

The product of a monomial $P_1(x)$ and a polynomial $P_N(x)$ gives $P_{N+1}(x)$: This is another way of stating the fundamental theorem of algebra. Each time we convolve a monomial with a polynomial of degree N, we obtain a polynomial of degree N+1. The convolution of two monomials results in a quadratic (degree 2 polynomial). The convolution of three monomials gives a cubic (degree 3). In general, the degree k of the product of two polynomials of degree n, m is the sum of the degrees (k = n + m). For example, if the degrees are each 5 (n = m = 5), then the resulting degree is 10.

While we all know this theorem from high school algebra class, it is important to explicitly identify the fundamental theorem of algebra.

 $^{^{15}\}mathrm{By}$ working with the negative roots, we may avoid an unnecessary and messy alternating sign problem.

Note that the degree of a polynomial is one less than the length of the vector of coefficients. Since the leading term of the polynomial cannot be zero, or else the polynomial would not have degree N, when we look for roots, the coefficient can (and should always) be normalized to 1.

In summary, the product of two polynomials of degree m, n having m and n roots is a polynomial of degree m + n. This is an analysis process of merging polynomials by coefficient convolution. Multiplying polynomials is a merging process into a single polynomial.

Composition of polynomials: Convolution is not the only important operation between two polynomials. Another is composition $c(z) = f(z) \circ g(z) = f(g(z))$ which is defined for analytic functions f(z) and g(z). For example suppose $f(z) = 1 + z + z^2$ and $g(z) = e^{2z}$. Thus

$$f(z) \circ g(z) = 1 + e^{2z} + (e^{2z})^2 = 1 + e^{2z} + e^{4z}.$$

Note that $f(z) \circ g(z) \neq g(z) \circ f(z)$.

Exercise #38 Find $g(z) \circ f(z)$. **Sol:** $e^{2f(z)} = e^{2(1+z+z^2)} = e^2 e^{(1+z+z^2)} = e^3 e^z e^{z^2}$

3.4.2 Residue Expansions of Rational Functions

As we discussed on Sect. 3.1.4, there are eight important MATLAB/Octave routines that are closely related: conv(), deconv(), poly(), polyder(), polyval(), residue() and root(). Several of these are complements of each other or do a similar operation in a slightly different way. The routines conv() and poly() build polynomials from the roots, while root() solves for the roots given the polynomial coefficients. The operation residue() expands the ratio of two polynomials in a partial fraction expansion, as poles and residues.

When lines and planes are defined, the equations are said to be *linear* in the independent variables. In keeping with this definition of *linear*, we say that the equations are *nonlinear* when the equations have degree greater than 1 in the independent variables. The term *bilinear* has a special meaning: Both the domain and codomain are linearly related by lines (or planes). As an example, impedance is defined in frequency as the ratio of the voltage over the current, but it often has a representation as the ratio of two polynomials, N(s) and D(s):

$$Z(s) = \frac{N(s)}{D(s)} = sL_o + R_o + \sum_{k=0}^{K} \frac{K_k}{s - s_k}.$$
 (3.4.4)

Here Z(s) is the impedance, V and I are the voltage and current at radian frequency ω , and K_k , s_k are the residues and eigenvalues. ¹⁶

¹⁶Note that the relationship between the impedance and the residues K_k is a linear one, ideally solved by formulating a linear system of equations in the unknown residues.

Such an impedance is typically specified as a rational or bilinear function—namely, the ratio of two polynomials, $P_N(s) = N(s) = [a_N, a_{n-1}, \ldots, a_o]$ and $P_K(s) = D(s) = [b_K, b_{K-1}, \ldots, b_o]$ of degrees $N, K \in \mathbb{N}$, as functions of complex Laplace frequency $s = \sigma + j\omega$ with simple roots. Most impedances are rational functions, since they may be written as D(s)V = N(s)I. Since D(s) and N(s) are both polynomials in s, a rational function is also called a *bilinear transformation*, or in the mathematical literature a *Möbius transformation*, which comes from a corresponding scalar differential equation of the form

$$\sum_{k=0}^{K} b_k \frac{d^k}{dt^k} i(t) = \sum_{n=0}^{N} a_n \frac{d^n}{dt^n} v(t) \quad \Leftrightarrow \quad I(\omega) \sum_{k=0}^{K} b_k s^k = V(\omega) \sum_{n=0}^{N} a_n s^n. \quad (3.4.5)$$

This construction is also known as the ABCD method in the engineering literature (Eq. 3.8.1). This equation, as well as Eq. 3.4.4, follows from the Laplace transform (see Sect. 3.10) of the differential equation (on left) by forming the impedance Z(s) = V/I = A(s)/B(s). This form of the differential equation follows from Kirchhoff's voltage and current laws (KCL, KVL) or from Newton's laws (for the case of mechanics).

Impedance is a very important and general concept. It is typically defined as the ratio of the change in voltage across a device, over the current through the device, which is known as *Ohm's law*. However it applies to many more physical variables than just electricity (see Table 3.2, p. 147), which leads to the concept of a *generalized impedance*.

It began as the real ratio of the voltage drop over the current through, but by at least 1893 it was realized that complex numbers could be used to represent the complex impedance of inductors (mass) and capacitors (springs) (Heaviside 1892; Kennelly 1893). As we explore more deeply it is is likely that Maxwell understood this concept as well, since he first formulated his famous equations of electricity using complex analysis (Maxwell 1865).

Since impedance is the ratio of a force over a flow, it does not directly depend on either the force or the flow. Rather it is the complex, frequency dependent proportionality factor between them:

force =
$$Z(s)$$
 · flow with $s, Z(s) \in \mathbb{C}$,

where $s = \sigma + \omega_I$ is the Laplace frequency.

The physical properties of an impedance: Based on d'Alembert's observation that the solution to the wave equation is the sum of forward and backward traveling waves,

the impedance may be rewritten in terms of forward and backward traveling waves (see Sect. 4.4):

JBA: This needs review.

$$Z(s) = \frac{V}{I} = \frac{V^{+} + V^{-}}{I^{+} - I^{-}} = r_{o} \frac{1 + \Gamma(s)}{1 - \Gamma(s)},$$
(3.4.6)

where $r_o = V^+/I^+$ is called the *characteristic impedance* of the transmission line (e.g., wire) connected to the load impedance Z(s), and $\Gamma(s) = V^-/V_+ = I^-/I^+$ is the reflection coefficient corresponding to Z(s). Any impedance of this type is called a *Brune impedance* due to its special properties (Brune 1931a; Van Valkenburg 1964a). Like Z(s), $\Gamma(s)$ is causal and complex analytic. The impedance and the reflectance function $\Gamma(s)$ must both be complex analytic, since they are related to the bilinear transformation, which ensures the mutual complex analytic properties.

Due to the bilinear transformation, the physical properties of Z(s) and $\Gamma(s)$ are very different. Specifically, the real part of the load impedance is nonnegative $(\Re\{Z(\omega_J)\} \ge 0)$ if and only if $|\Gamma(s)| \le 1$. In the time domain, the impedance $z(t) \leftrightarrow Z(s)$ must have a value of r_o at t=0. Correspondingly, the time-domain reflectance $\gamma(t) \leftrightarrow \Gamma(s)$ must be zero at t=0.

This is the basis of conservation of energy, which may be traced back to the properties of the reflectance $\Gamma(s)$. We shall show that the reflectance is composed of the sum of the forward and retrograde eigenfunctions, as determined by the load impedance at the far end of the horn.

Exercise #39 Show that if $\Re\{Z(s)\} \ge 0$, then $|\Gamma(s)| \le 1$.

Sol: Taking the real part of Eq. 3.4.6, which must be ≥ 0 , we find

$$\Re\{Z(s)\} = \frac{r_o}{2} \left[\frac{1 + \Gamma(s)}{1 - \Gamma(s)} + \frac{1 + \Gamma^*(s)}{1 - \Gamma^*(s)} \right] = r_o \frac{1 - |\Gamma(s)|^2}{|1 + \Gamma(s)|^2} \ge 0.$$

Thus $|\Gamma| \leq 1$.

3.5 Introduction to Analytic Geometry

Analytic geometry came about as Euclid's geometry merged with algebra. The combination of Euclid's (323 BCE) geometry and al-Khwarizmi's (830 CE) algebra resulted in a totally new and powerful tool, analytic geometry, independently worked out by Descartes and Fermat (Stillwell 2010). The development of matrix algebra during the eighteenth century enabled an analysis in more than three dimensions. Due to modern computation, today this is one of the most powerful tools used in artificial intelligence, data science, and machine learning. The utility and importance of these new tools cannot be overstated. The timeline for this period of development in mathematics is shown in Fig. 1.2.

There are many important relationships between Euclidean geometry and sixteenth-century algebra. Table 3.1 is an attempt at a detailed comparison. Important similarities include vectors, their Pythagorean lengths [a, b, c],

Euclidean geomerty: \mathbb{R}^3	Analytic geometry: \mathbb{R}^n	Uncertain
Proof	Numbers	Recursion
Line length	Algebra	Iteration $\in \mathbb{C}^2$,
Line intersection	Power series	Newton's method
Point	Analytic functions	Appximation: (Least-squares)
Projection (scalar product)	Complex analytic functions:	
Line direction	$\sin \theta$, $\cos \theta$, $e^{\theta J}$, $\log z$	
Vector (sort of)	Scalar product	
Conic section	Wedge (scalar) product $A \perp B$	
Square roots (spiral of	Generalized scalar product	
Theodorus)	(Eq. 3.5.5)	
	Normed vector spaces	
	Composition	
	Elimination	
	Integration	
	Derivatives	
	Calculus	
	Polynomial $\in \mathbb{C}$	
	Fundamental theorem of algebra	

Table 3.1 An ad hoc comparison of Euclidean geometry and analytic geometry. I am uncertain of the classification of the items in the third column

$$c = \sqrt{(x_2 - x_1)^2 + (y_2 - y_1)^2},$$
 (3.5.1)

 $a = x_2 - x_1$, and $b = y_2 - y_1$, and the angles. Euclid's geometry had length and angles but no concept of coordinates or thus of vectors. One of the main innovations of analytic geometry is that we could compute with real, and soon after, complex numbers, first observed in the completion of squares, Eq. 3.1.9.

3.5.1 Merging the Concepts

Several new concepts came with the development of analytic geometry:

- 1. Composition of functions: If y = f(x) and z = g(y), then the composition of functions f and g is denoted $z(x) = g \circ f(x) = g(f(x))$.
- 2. Elimination: Given two functions f(x, y) and g(x, y), elimination removes either x or y. This procedure, well known to the Chinese, is now known as *Gaussian elimination*.
- 3. Intersection: One may speak of the intersection of two lines to define a point or two planes to define a line. This is a special case of elimination when the functions f(x, y) and g(x, y) are linear in their arguments. The term *intersection* is also an important but very different from the meaning of the term as used in set theory.
- 4. Vectors: Analytic geometry provides the concept of a vector (see Appendix A.3.1) as a line with length and orientation (i.e., direction). Analytic geometry defines vectors in any number of dimensions as ordered sets of points.




Fig. 3.4 Vectors A, B, $C \in \mathbb{C}$ are used to define the scalar product $A \cdot B \in \mathbb{C}$ and the scalar wedge-product $A \wedge B \in \mathbb{C}$. The scalar wedge-product is the same as the vector cross-product except the output is a scalar. As shown, the scalar dot and wedge-products complement each other, since one is proportional to the sine of the angle θ between them, and the other to the cosine. The dot product computes the projection of one vector on the other (the length of the base of the triangle formed by the two vectors), while the vector wedge-product $A \wedge B$ computes the area of the right triangle ($area = base \cdot height = A \cdot B \cdot L_*$) formed by the two vectors. Thus $|A \cdot B|^2 + |A \wedge B|^2 = ||A||^2 ||B||^2$. The $scalar triple product C \cdot (A \times B)$ represents the volume of the parallelepiped (i.e., prism) defined by the three vectors A, B, and C. When all the angles are 90° , the volume becomes a cuboid

5. Scalar products of vectors: Analytic geometry extends the ideas of Euclidean geometry with the introduction of the scalar (dot) product of two vectors $\mathbf{f} \cdot \mathbf{g}$ and the scalar wedge-product $\mathbf{f} \wedge \mathbf{g}$. The vector wedge-product adds a unit vector \bot the plane of the two vectors

$$f \wedge g\hat{z}$$
,

as described in the caption of Fig. 3.4.

What algebra also added to geometry was the ability to compute with complex (polar) numbers. For example, in geometry the length of a line (Eq. 3.5.1) was measured with a compass; numbers played no role. Once algebra was available, the line's Euclidean length could be computed numerically, directly from the coordinates of the two ends, defined by the 3-vector

$$\mathbf{e} = x\hat{\mathbf{x}} + y\hat{\mathbf{y}} + z\hat{\mathbf{z}} = [x, y, z]^T,$$

which represents a point at $(x, y, z) \in \mathbb{R}^3 \subset \mathbb{C}^3$ in three dimensions, having direction from the origin (0, 0, 0) to (x, y, z). An alternative matrix notation is $\mathbf{e} = [x, y, z]^T$, a column-vector of three numbers. These two notations are different ways of representing a vector \mathbf{e} .

By defining the vector, analytic geometry allows Euclidean geometry to become quantitative, beyond the physical drawing of an object (e.g., a sphere, triangle, or line). With analytic geometry we have the Euclidean concept of a vector, a line that has a magnitude (length) and direction (angle), but analytic, defined in terms

of physical coordinates (i.e., numbers). The difference between two vectors $(\mathbf{x} - \mathbf{y})$ defines a third vector form, a concept already present in Euclidean geometry. For the first time, complex numbers were allowed into geometry (but rarely used before Cauchy and Riemann).

Scalar product of two vectors: When we use algebra, many concepts that are obvious with Euclid's geometry may be made precise. There are many examples of how algebra extends Euclidean geometry, the most basic being the scalar product (also known as the dot product) between vectors $\mathbf{x} \in \mathbb{R}^3$ and $\boldsymbol{\kappa} \in \mathbb{C}^3$:

$$\mathbf{x} \cdot \boldsymbol{\kappa} = (x\hat{\mathbf{x}} + y\hat{\mathbf{y}} + z\hat{\mathbf{z}}) \cdot (\alpha\hat{\mathbf{x}} + \beta\hat{\mathbf{y}} + \gamma\hat{\mathbf{z}}) \in \mathbb{C}$$
$$= \alpha x + \beta y + \gamma z.$$

Scalar products play an important role in vector algebra and calculus.

In vector notation the scalar product is written as (see Appendix A.3).

$$\mathbf{x} \cdot \boldsymbol{\kappa} = \begin{bmatrix} x \\ y \\ z \end{bmatrix}^T \begin{bmatrix} \alpha \\ \beta \\ \gamma \end{bmatrix} = [x, y, z] \begin{bmatrix} \alpha \\ \beta \\ \gamma \end{bmatrix} = \alpha x + \beta y + \gamma z. \tag{3.5.2}$$

If $\kappa(s) \in \mathbb{C}^3$ is a complex function of frequency s, then the scalar product is a complex function of s.

Norm (length) of a vector: The norm of a vector

$$||\mathbf{e}|| \equiv +\sqrt{\mathbf{e} \cdot \mathbf{e}} \ge 0$$

is defined as the positive square root of the scalar product of the vector with itself (see Appendix A.3). This is a generalization of the length, in any number of dimensions, that forces the sign of the square root to be nonnegative. The length is a concept of Euclidean geometry, and it must always be positive and real. A complex (or negative) length is not physically meaningful. More generally, the Euclidean length of a line is given as the norm of the difference between two real vectors $\mathbf{e}_1, \mathbf{e}_2 \in \mathbb{R}$:

$$||\mathbf{e}_1 - \mathbf{e}_2||^2 = (\mathbf{e}_1 - \mathbf{e}_2) \cdot (\mathbf{e}_1 - \mathbf{e}_2)$$

= $(x_1 - x_2)^2 + (y_1 - y_2)^2 + (z_1 - z_2)^2 > 0.$ (3.5.3)

From this formula we see that the norm of the difference of two vectors is a compact expression for the Euclidean length. A zero-length vector, such as a point, is the result of the fact that

$$||x - x||^2 = (x - x) \cdot (x - x) = 0.$$

Integral definition of a scalar product: Following Euclid, we only considered a vector to be a set of elements $\{x_n\} \in \mathbb{R}$, index over $n \in \mathbb{N}$. Starting with Fig. 3.4 we assume the vectors are in \mathbb{C} .

An obvious question presents itself: Can we extend our definition of vectors to differentiable functions (i.e., f(t) and g(t)) indexed over $t \in \mathbb{R}$ with coefficients labeled by $t \in \mathbb{R}$ rather than by $n \in \mathbb{N}$? Clearly, if the functions are analytic, there is no obvious reason that this should be a problem, since analytic functions may be represented by a convergent series that has Taylor coefficients and thus are integrable term by term.

Specifically, under certain conditions, the function f(t) may be thought of as a vector, defining a normed vector space called a Hilbert space. This intuitive and somewhat obvious idea is powerful. In this case the scalar product can be defined in terms of the integral

$$f(t) \cdot g(t) = \int_{t} f(t)g(t)dt$$
$$= ||f(t)|| ||g(t)|| \cos \theta$$

summed over $t \in \mathbb{R}$, rather than a sum over $n \in \mathbb{N}$.

This definition of the vector–scalar product allows for a significant but straightforward generalization of our vector space, which will turn out to be both useful and an important extension of the concept of a normed vector space. In this space we can define the derivative of a norm with respect to t, which is not possible for the discrete case, indexed over n. The distinction introduces the concept of analytic continuity in the index t, which also fails to exist for the discrete index $n \in \mathbb{N}$.

Pythagorean theorem and the Schwarz inequality: Regarding Fig. 3.4, suppose we compute the difference between vector $A \in \mathbb{R}$ and $\alpha B \in \mathbb{R}$ as $L = ||A - \alpha B|| \in \mathbb{R}$, where $\alpha \in \mathbb{R}$ is a scalar that modifies the length of B. We seek the value of α , which we denote as α^* , that minimizes the length of L. From simple geometrical considerations, $L(\alpha)$ will be minimum when the difference vector is perpendicular to B, as shown in the figure by the dashed line from the tip of $A \perp B$.

To show this algebraically, we write the expression for $L(\alpha)$, take the derivative with respect to α , and set it to zero, which gives the formula for α^* . The argument does not change, but the algebra greatly simplifies if we normalize \boldsymbol{A} and \boldsymbol{B} to be unit vectors $\boldsymbol{a} = \boldsymbol{A}/||\boldsymbol{A}||$ and $\boldsymbol{b} = \boldsymbol{B}/||\boldsymbol{B}||$, which each have norm = 1:

$$L^{2} = (\boldsymbol{a} - \alpha \boldsymbol{b}) \cdot (\boldsymbol{a} - \alpha \boldsymbol{b}) = 1 - 2\alpha \boldsymbol{a} \cdot \boldsymbol{b} + \alpha^{2}. \tag{3.5.4}$$

Thus the length is shortest $(L = L_*, \text{ as shown in Fig. 3.4})$ when

$$\frac{d}{d\alpha}L_*^2 = -2\boldsymbol{a} \cdot \boldsymbol{b} + 2\alpha^* = 0.$$

Solving for $\alpha^* \in \mathbb{R}$, we find $\alpha^* = \mathbf{a} \cdot \mathbf{b}$. Since $L_* > 0$ ($\mathbf{a} \neq \mathbf{b}$), Eq. 3.5.4 becomes

$$1 - 2|\boldsymbol{a} \cdot \boldsymbol{b}|^2 + |\boldsymbol{a} \cdot \boldsymbol{b}|^2 = 1 - |\boldsymbol{a} \cdot \boldsymbol{b}|^2 > 0.$$

In terms of A and B this is $|A \cdot B| < ||A|| \, ||B|| \cos \theta$, as shown adjacent to B in Fig. 3.4.

In conclusion, $\cos\theta \equiv |a\cdot b| < 1$. Thus the scalar product between two vectors is their direction-cosine. Furthermore, since this forms a right triangle, the Pythagorean theorem must hold. The triangle inequality says that the sum of the lengths of the two sides must be greater than the length of the hypotenuse. Note that $\Theta \in \mathbb{R} \notin \mathbb{C}$. Equality cannot be obtained because in Fourier space the scalar product defines an open set, which gives rise to Gibbs ringing in the time domain (Greenberg 1988, p. 854). This derivation is an abbreviated version of a related discussion on Sect. 3.5.5. **Vector cross** (×) **and wedge** (\wedge) **products of two vectors:** The vector product (cross-product) $A \times B$ and the exterior product (wedge-product) $A \wedge B$ are the second and

Ed:

$$\mathbf{C} = \mathbf{A} \times \mathbf{B} = (a_1 \hat{\mathbf{x}} + a_2 \hat{\mathbf{y}} + a_3 \hat{\mathbf{z}}) \times (b_1 \hat{\mathbf{x}} + b_2 \hat{\mathbf{y}} + b_3 \hat{\mathbf{z}}) = \begin{vmatrix} \hat{\mathbf{x}} & \hat{\mathbf{y}} & \hat{\mathbf{z}} \\ a_1 & a_2 & a_3 \\ b_1 & b_2 & b_3 \end{vmatrix}$$

third types of vector products. As shown in Fig. 3.4.

is \perp to the plane defined by A and B. The cross-product is strictly limited to two input vectors A and $B \in \mathbb{R}^2$ taken from three real dimensions (i.e., \mathbb{R}^3).

The exterior (wedge) product generalizes the cross-product, since it may be defined in terms of any two vectors A, $B \in \mathbb{C}^2$ taken from n dimensions (\mathbb{C}^n) with output in \mathbb{C}^1 . Thus the cross-product is composed of three wedge-products.

From this specific example we see that the absolute value of the wedge-product $|\mathbf{a} \wedge \mathbf{b}| = ||\mathbf{a} \times \mathbf{b}||$, namely,

$$|(a_2\hat{\mathbf{y}} + a_3\hat{\mathbf{z}}) \wedge (b_2\hat{\mathbf{y}} + b_3\hat{\mathbf{z}})| = ||\mathbf{a} \times \mathbf{b}|| = ||\mathbf{a}|| ||\mathbf{b}|| |\sin \theta|.$$

The wedge-product is especially useful because it is zero when the two vectors are colinear: that is, $\hat{\mathbf{x}} \wedge \hat{\mathbf{x}} = 0$ and $\hat{\mathbf{x}} \wedge \hat{\mathbf{y}} = 1$, where $\hat{\mathbf{x}}$ and $\hat{\mathbf{y}}$ are unit vectors.

Since

$$\mathbf{a} \cdot \mathbf{b} = ||\mathbf{a}|| \, ||\mathbf{b}|| \cos \theta$$
 and $\mathbf{a} \wedge \mathbf{b} = ||\mathbf{a}|| \, ||\mathbf{b}|| \sin \theta$,

it follows that

$$\mathbf{a} \cdot \mathbf{b} + j \, \mathbf{a} \wedge \mathbf{b} = ||\mathbf{a}|| \, ||\mathbf{b}|| \, e^{j\theta},$$

which may be viewed as a generalized complex scalar product $\in \mathbb{C}$, with the right-hand side the polar form.

The main advantage of the wedge-product is that it is valid in $n \ge 3$ dimensions since it is defined for any two vectors in any number of dimensions.

Scalar triple product: The triple of a third vector C with the vector product $A \times B \in \mathbb{R}$ is

$$\boldsymbol{C} \cdot (\boldsymbol{A} \times \boldsymbol{B}) = \begin{vmatrix} c_1 & c_2 & c_3 \\ a_1 & a_2 & a_3 \\ b_1 & b_2 & b_3 \end{vmatrix} \in \mathbb{R}^3,$$

which equals the volume of a parallelepiped.

3.5.2 Generalized Scalar Product

As shown in Fig. 3.4, any two vectors A, $B \in \{\hat{\mathbf{x}}, \hat{\mathbf{y}}\}\$ define a plane. There are two types of scalar products¹⁷: the scalar dot product

$$\mathbf{A} \cdot \mathbf{B} = ||\mathbf{A}|| \, ||\mathbf{B}|| \cos \theta \in \mathbb{R},$$

and the scalar wedge-product¹⁸

$$A \wedge B = ||A|| ||B|| \sin \theta \in \mathbb{R}.$$

As shown in the figure, these two products form a right triangle and thus may be naturally merged, defining the complex analytic scalar product

$$\mathbf{A} \wedge \mathbf{B} = \mathbf{A} \cdot \mathbf{B} + j \mathbf{A} \wedge \mathbf{B} = ||\mathbf{A}|| ||\mathbf{B}|| e^{j\theta} \in \mathbb{C}.$$
 (3.5.5)

Important examples, based on the Poynting theorem, come from Maxwell's equations

$$\mathcal{P} = \mathbf{E} \perp \mathbf{H} = \mathbf{E} \cdot \mathbf{H} + j \mathbf{E} \wedge \mathbf{H} \qquad [\text{W/m}^2]$$

(Sommerfeld 1952, p. 26), and the corresponding momentum equation (Johnson et al. 1994)

$$\mathcal{M} = \mathbf{D} \wedge \mathbf{B} = \mathbf{D} \cdot \mathbf{B} + j \mathbf{D} \wedge \mathbf{B} = \frac{1}{c_o^2} \mathcal{P}$$
 [J s/m⁴].

While the *solar constant* $\mathcal{P}=1.3$ [kW/m²] is large, solar gravity, which follows from Maxwell's equations, is $1/c_o^2=1.1\times 10^{-17}$ smaller.

Example: If we define $\mathbf{A} = 3J\hat{\mathbf{x}} - 2\hat{\mathbf{y}} + 0\hat{\mathbf{z}}$ and $\mathbf{B} = 1\hat{\mathbf{x}} + 1\hat{\mathbf{y}} + 0\hat{\mathbf{z}}$, then the cross-product is

$$\mathbf{A} \times \mathbf{B} = \begin{vmatrix} \hat{\mathbf{x}} & \hat{\mathbf{y}} & \hat{\mathbf{z}} \\ 3J & -2 & 0 \\ 1 & 1 & 0 \end{vmatrix} = (3J + 2)\hat{\mathbf{z}}.$$

Since $a_1 \in \mathbb{C}$, this example violates the common assumption that $A \in \mathbb{R}^3$. The wedge-product $A \wedge B$ takes two vectors and returns a scalar, which is the magnitude of a vector \bot to the plane defined by the two input vectors (see Fig. 3.4). It is defined as

¹⁷https://en.wikipedia.org/wiki/Bivector.

¹⁸In some texts the wedge-product is called the vector exterior-product.

$$A \wedge B = \begin{vmatrix} a_1 & b_1 \\ a_2 & b_2 \end{vmatrix} = \begin{vmatrix} 3J & 1 \\ -2 & 1 \end{vmatrix}$$

$$= (3J\hat{\mathbf{x}} - 2\hat{\mathbf{y}}) \wedge (\hat{\mathbf{x}} + \hat{\mathbf{y}})$$

$$= 3 \cdot 0 \times \mathbf{x} - 2\hat{\mathbf{y}} \wedge \hat{\mathbf{x}} + 3J\hat{\mathbf{x}} \wedge \hat{\mathbf{y}} - 2\hat{\mathbf{y}} \wedge \hat{\mathbf{y}}$$

$$= (3J + 2)||\hat{\mathbf{x}} \wedge \hat{\mathbf{y}}||$$

$$= (3J + 2)||\hat{\mathbf{y}}|| = 3J + 2.$$

This defines a compact and useful algebra (Hestenes 2003).

Impact of Analytic Geometry: The most obvious impact of analytic geometry was its detailed analysis of the conic sections using algebra rather than drawings with a compass and ruler. An important example is the composition of the line and circle, a venerable pre-Euclid construction.

Once algebra was invented, analysis could be done using formulas. With analysis came complex numbers.

The first two mathematicians to appreciate this mixture of Euclid's geometry and the new algebra were Fermat and Descartes (Fig. 1.5). Soon Newton contributed to this effort by adding physics (e.g., calculations in acoustics, orbits of the planets, and the theory of gravity and light, significant concepts for 1687) (Stillwell 2010, p. 115–117)).

Given these new methods, many new solutions to problems emerged. The complex roots of polynomials continued to appear, without any obvious physical meaning. Newton called them *imaginary*. Complex numbers seem to have been viewed as an inconvenience. Newton's solution to this dilemma was to simply ignore the "imaginary" cases (Stillwell 2010, p. 115–19).

3.5.3 Development of Analytic Geometry

The first "algebra" (*al-jabr*) is credited to al-Khwarizmi (830 CE). Its invention advanced the theory of polynomial equations in one variable, Taylor series, and composition versus intersections of curves. The solution of the quadratic equation had been worked out thousands of years earlier, but with algebra a general solution could be defined. The Chinese had found the way to solve several equations in several unknowns—for example, finding the values of the intersections of two circles. With the invention of algebra by al-Khwarizmi, a powerful tool became available to solve more difficult problems.

In algebra there are two contrasting operations on functions: composition and elimination (e.g., intersection).

3.5.3.1 Composition:

Composition is the merging of functions by feeding one into the other. If the two functions are f and g, then their composition is indicated by $f \circ g$, meaning the function y = f(x) is substituted into the function z = g(y), giving z = g(f(x)).

Composition is not limited to linear equations, even though that is where it is most frequently applied. That requires solving for that substitution variable, which is not always possible in the case of nonlinear equations. However, many tricks are available that may work around this restriction. For example, if one equation is in x^2 and the other in x^3 or \sqrt{x} , it may be possible to multiply the first by x or square the second. The point is that one of the variables must be isolated so that when it is substituted into the other equation, the variable is removed from the mix.

Example: Let $y = f(x) = x^2 - 2$ and z = g(y) = y + 1. Then

$$g \circ f = g(f(x)) = (x^2 - 2) + 1 = x^2 - 1.$$
 (3.5.6)

In general, composition does not commute (i.e., $f \circ g \neq g \circ f$), as is easily demonstrated. Swapping the order of composition for our example gives

$$f \circ g = f(g(y)) = z^2 - 2 = (y+1)^2 - 2 = y^2 + 2y - 1.$$
 (3.5.7)

3.5.3.2 Intersection:

Complementary to composition is intersection (i.e., decomposition). For example, the intersection of two lines is defined as the point where they meet. This is not to be confused with finding roots. A polynomial of degree N has N roots, but the points where two polynomials intersect has nothing to do with the roots of the polynomials. The intersection is a function (equation) of lower degree, implemented by Gaussian elimination.

A system of linear equations Ax = y has many interpretations, and one should not be biased by the notation. As engineers, we are trained to view x as the input and y as the output. Then y = Ax seems natural, much like the functional relationship y = f(x). But what does the linear relationship x = Ay mean, when x is the input? The answer is $y = A^{-1}x$.

But when we work with systems of equations, there are many uses of equations, and we need to be more flexible in our interpretation. For example, $y = A^2x$ has a useful meaning, and in fact we saw this type of relationship we worked with Pell's equation (Sect. 2.6.2) and the Fibonacci sequence (Sect. 2.6.3). As another example, consider

$$\begin{bmatrix} z_1 \\ z_2 \end{bmatrix} = \begin{bmatrix} a_{1x} \ a_{1y} \\ a_{2x} \ a_{2y} \end{bmatrix} \begin{bmatrix} x \\ y \end{bmatrix},$$

which is reminiscent of a two-dimensional surface $\mathbf{z} = \mathbf{f}(x, y)$. We shall find that such generalizations are much more than a curiosity.

Intersection of two lines: Unless they are parallel, two lines meet at a point. In terms of linear algebra, this may be written as two linear equations¹⁹ (on the left) along with the intersection point $[x_1, x_2]^T$ given by the inverse of the 2×2 set of equations (on the right):

$$\begin{bmatrix} a & b \\ c & d \end{bmatrix} \begin{bmatrix} x_1 \\ x_2 \end{bmatrix} = \begin{bmatrix} y_1 \\ y_2 \end{bmatrix} \qquad \begin{bmatrix} x_1 \\ x_2 \end{bmatrix} = \frac{1}{\Delta} \begin{bmatrix} d & -b \\ -c & a \end{bmatrix} \begin{bmatrix} y_1 \\ y_2 \end{bmatrix}. \tag{3.5.8}$$

By substituting the expression for the intersection point $[x_1, x_2]^T$ into the original equation, we see that it satisfies the equations. Thus the equation on the right is the solution to the equation on the left.

3.5.3.3 Elimination:

Note the structure of the inverse: (1) The diagonal values (a, d) are swapped, (2) the off-diagonal values (b, c) are negated, and (3) the 2×2 matrix is divided by the determinant $\Delta = ad - bc$. If $\Delta = 0$, there is no solution. When the determinant is zero ($\Delta = 0$), the slopes of the two lines

slope =
$$\frac{b}{a} = \frac{d}{c}$$

are equal; thus the lines are parallel. Only if the slopes differ can there be a unique solution.

Algebra can give the solution when geometry cannot. When the two curves fail to intersect on the real plane, the solution still exists, but it is complex-valued. In such cases, geometry, which considers only the real solutions, fails. For example, when the coefficients [a, b, c, d] are complex, the solution exists but the determinant can be complex. Thus algebra is much more general than geometry. Geometry fails when the solution has a complex intersection.

3.5.4 Applications of Scalar Products

Another important example of algebraic expressions in mathematics is Hilbert's generalization of the Pythagorean theorem (Eq. 1.1), known as the *Schwarz* inequality and shown in Fig. 3.5. What is special about this generalization is that it proves that when the vertex is 90° , the Euclidean length of the leg is minimum.

¹⁹When we write the equation Ax = y in matrix format, the two equations are $ax_1 + bx_2 = y_1$ and $dx_1 + ex_2 = y_2$ with unknowns (x_1, x_2) , whereas in the original equations ay + bx = c and dy + ex = f, the unknowns are y and x. Thus in matrix format, the names are changed. The first time you see this scrambling of variables, it can be confusing.




Fig. 3.5 The *Schwarz inequality* is related to the shortest distance (length of a line) between the ends of the two vectors. $||U|| = \sqrt{U \cdot U}$ is the scalar product of that vector with itself

Vectors may be generalized to have ∞ dimensions. For example $\mathbf{U} = [u_1, u_2, \dots, u_{\infty}]$, $\mathbf{V} = [v_1, v_2, \dots, v_{\infty}]$. The Euclidean inner product (i.e., scalar product) between two such vectors generalizes the finite-dimensional case

$$\mathbf{U} \cdot \mathbf{V} = \sum_{k=1}^{\infty} u_k v_k = \|\mathbf{U}\| \|\mathbf{V}\| \cos \theta$$

where $\theta \in \mathbb{R}$ is the multivalued angle between the two normalized (unit) vectors

$$\theta = \cos^{-1}\left(\frac{\mathbf{U}}{\|\mathbf{U}\|} \cdot \frac{\mathbf{V}}{\|\mathbf{U}\|}\right).$$

As with the finite case the norm $||\mathbf{U}|| = \sqrt{\mathbf{U} \cdot \mathbf{U}} = \sqrt{\sum u_k^2}$, the scalar product of the vector with itself, defines the length of the infinite component vector. There is an issue of convergence when the norm of the vectors is zero.

It is a somewhat arbitrary requirement that $a, b, c \in \mathbb{R}$ for (Eq. 1.1). This seems natural enough, since the sides are lengths. But what if these lengths are taken from high-dimensionality complex vectors, as for the lossy vector wave equation or the lengths of vectors in the Fourier transform $(\mathcal{FT}) \in \mathbb{C}^n$? Then the equation generalizes to $K \to \infty$ dimensions

$$\mathbf{c} \cdot \mathbf{c} = ||\mathbf{c}||^2 = \sum_{k=1}^{K \to \infty} |c_k|^2.$$

As before, $||\mathbf{c}|| = \sqrt{||\mathbf{c}||^2}$ is the *norm* of vector \mathbf{c} , akin to a length, which must be finite (converge). This is simply the important case of complex analytic functions, which also must converge.

Schwarz inequality: The Schwarz inequality says that the magnitude of the inner product of two vectors is less than or equal to the product of their lengths:

$$|U \cdot V| < ||U|| \, ||V||.$$

This may be simplified by normalizing the vectors to have unit length ($\widehat{U} = U/||U||$, $\widehat{V} = V/||V||$), in which case $-1 < \widehat{U} \cdot \widehat{V} \le 1$. Another simplification is

to define the scalar product in terms of the direction-cosine

$$\cos \theta = |\widehat{U} \cdot \widehat{V}| \le 1.$$

From these definitions we may define the minimum difference between the two vectors as the perpendicular from the end of the first to the intersection with the second. As shown in Fig. 3.5, $U \perp V$ may be found by minimizing the length of the vector difference:

$$\min_{\alpha} ||V - \alpha U||^2 = ||V||^2 + 2\alpha V \cdot U + \alpha^2 ||U||^2 > 0$$

$$0 = \partial_{\alpha} (V - \alpha U) \cdot (V - \alpha U)$$

$$= V \cdot U - \alpha^* ||U||^2$$

$$\therefore \alpha^* = V \cdot U / ||U||^2.$$

The Schwarz inequality follows:

$$I_{\min} = ||V - \alpha^* U||^2 = ||V||^2 - \frac{|U \cdot V|^2}{||U||^2} > 0$$
 (3.5.9)

$$0 \le |U \cdot V| \le ||U|| \, ||V||.$$

An important example of such a vector space includes the definition of the \mathcal{FT} where we may set

$$U(\omega) = e^{-\omega_0 J t} \qquad V(\omega) = e^{\omega J t} \qquad U \cdot V = \int_{\Omega} e^{J \omega t} e^{-J \omega_0 t} \frac{d\omega}{2\pi} = \delta(\omega - \omega_0).$$

It seems that the Fourier transform is a result that follows from a minimization, unlike the Laplace transform, which follows from causality. This explains the important differences between the two in terms of their properties (unlike the \mathcal{LT} the \mathcal{FT} is not complex analytic). Recall that

$$U \cdot V + jU \wedge V = ||U|| ||V|| e^{j\theta}.$$

3.5.5 Gaussian Elimination

The method for finding the intersection of equations is based on the recursive elimination of all the variables but one. This method, known as *Gaussian elimination* (Appendix 5), works across a broad range of cases but may be defined as a systematic algorithm when the equations are linear in the variables (Strang et al. 1993). Rarely do we even attempt to solve problems in several variables of degree greater

than 1. But Gaussian elimination may still work in such cases (Stillwell 2010, p. 90). In Appendix 3.6.6 we derive the inverse of a 2×2 linear system of equations. Even for a 2×2 case, the general solution requires a great deal of algebra. Working out a numeric example of Gaussian elimination is more instructive. For example, suppose we wish to find the intersection of the two equations

$$x - y = 3$$
$$2x + y = 2.$$

This 2×2 system of equations is so simple that you may immediately visualize the solution: By adding the two equations, y is eliminated, leaving 3x = 5. But doing it this way takes advantage of the specific example, and we need a method for larger systems of equations. We need a generalized (algorithmic) approach. This general approach is called Gaussian elimination.

We start by writing the equations in matrix form (note this is not in the form Ax = y):

$$\begin{bmatrix} 1 & -1 \\ 2 & 1 \end{bmatrix} \begin{bmatrix} x \\ y \end{bmatrix} = \begin{bmatrix} 3 \\ 2 \end{bmatrix}. \tag{3.5.10}$$

Next, we eliminate the lower left term (2x) using a scaled version of the upper left term (x). Specifically, we multiply the first equation by -2 and add it to the second equation, replacing the second equation with the result. This gives

$$\begin{bmatrix} 1 & -1 \\ 0 & 3 \end{bmatrix} \begin{bmatrix} x \\ y \end{bmatrix} = \begin{bmatrix} 3 \\ 2 - 3 \cdot 2 \end{bmatrix} = \begin{bmatrix} 3 \\ -4 \end{bmatrix}. \tag{3.5.11}$$

Note that the top equation did not change. Once the matrix is "upper triangular" (zero below the diagonal), we have the solution. If we start from the bottom equation, y = -4/3. Then the upper equation gives x - (-4/3) = 3 or x = 3 - 4/3 = 5/3.

In principle, Gaussian elimination is easy, but if you make a calculation mistake along the way, it is very difficult to find your error. The method requires a lot of mental labor, and you have a high probability of making a mistake. Thus you do not want to apply this method every time. For example, suppose the elements are complex numbers or polynomials in some other variable such as frequency. Once the coefficients become more complicated, the seemingly trivial problem becomes corrosive. There is a much better way that is easily verified; it puts all the numerics at the end in a single step.

The above operations may be automated by finding a carefully chosen upperdiagonalized matrix G. For example, we can define the *Gaussian matrix* that zeros the element 2 in the matrix in Eq. 3.5.10. More generally let

$$G = \begin{bmatrix} 1 & 0 \\ a & 1 \end{bmatrix}. \tag{3.5.12}$$

Multiplying Eq. 3.5.10 by G, we find

$$\begin{bmatrix} 1 & 0 \\ a & 1 \end{bmatrix} \begin{bmatrix} 1 & -1 \\ 2 & 1 \end{bmatrix} \begin{bmatrix} x \\ y \end{bmatrix} = \begin{bmatrix} 1 & -1 \\ a+2 & 1-a \end{bmatrix} \begin{bmatrix} x \\ y \end{bmatrix} = \begin{bmatrix} 3 \\ 3a+2 \end{bmatrix}.$$
 (3.5.13)

Thus we obtain Eq. 3.5.11 if we let a=-2 (we choose a to force the lower left to be zero). At this point we can either back-substitute and obtain the solution, as we did above, or find a matrix L that finishes the job by removing elements above the diagonal. Note that the determinant of matrix G is 1, thus it will always have an inverse.

Exercise #40 Using G and A from the discussion above show that det(G) = det(GA) = 3.

Sol: A common convention is to denote det(A) = |A|. The two sides of the identity are

$$|A| = \det \begin{bmatrix} 1 & -1 \\ 2 & 1 \end{bmatrix} = 1 + 2 = 3, \qquad |GA| = \det \begin{bmatrix} 1 & -1 \\ 0 & 3 \end{bmatrix} = 3,$$

and |G| = 1. Thus |GA| = |G||A| = 3.

Matrix inverse: In Appendix 3.6.6, finding the inverse of a general 2×2 matrix takes three steps: (1) swap the diagonal elements, (2) reverse the signs of the off-diagonal elements, and (3) divide by the determinant $\Delta = ab - cd$. Specifically,

$$\begin{bmatrix} a & b \\ c & d \end{bmatrix}^{-1} = \frac{1}{\Delta} \begin{bmatrix} d & -b \\ -c & a \end{bmatrix}. \tag{3.5.14}$$

There are very few things that you must memorize, but the inverse of a 2×2 matrix is one of them. It needs to be in your mental toolkit, like completing the square (see Sect. 3.1.1).

While it is difficult to compute the inverse matrix from scratch (see Appendix 5), it takes only a few seconds (four dot products) to verify it (steps 1 and 2):

$$\begin{bmatrix} a & b \\ c & d \end{bmatrix} \begin{bmatrix} d & -b \\ -c & a \end{bmatrix} = \begin{bmatrix} ad - bc - ab + ab \\ cd - cd - bc + ad \end{bmatrix} = \begin{bmatrix} \Delta & 0 \\ 0 & \Delta \end{bmatrix}. \tag{3.5.15}$$

Thus dividing by the determinant gives the 2×2 identity matrix. A good strategy (don't trust your memory) is to write down the inverse as best you recall and then verify.

Using the 2×2 matrix inverse on our example (Eq. 3.5.10), we find

$$\begin{bmatrix} x \\ y \end{bmatrix} = \frac{1}{1+2} \begin{bmatrix} 1 & 1 \\ -2 & 1 \end{bmatrix} \begin{bmatrix} 3 \\ 2 \end{bmatrix} = \frac{1}{3} \begin{bmatrix} 5 \\ -6+2 \end{bmatrix} = \begin{bmatrix} 5/3 \\ -4/3 \end{bmatrix}.$$
 (3.5.16)

If you use this method, you will rarely (never) make a mistake and the solution is easily verified.

Augmented matrix: There is one minor notational improvement. Rather than writing the matrix equation as Eq. 3.5.10 (Ax = y), we place the y vector next to the elements of A to remove the equal sign, which is cumbersome. In this case we write GA_{aug} :

$$GA_{\text{aug}} = \begin{bmatrix} 1 & 0 \\ -2 & 1 \end{bmatrix} \begin{bmatrix} 1 & -1 & | & 3 \\ 2 & 1 & | & 2 \end{bmatrix} = \begin{bmatrix} 1 & -1 & | & 3 \\ 0 & 3 & | & -4 \end{bmatrix}.$$

In summary, this is the same as Eq. 3.5.12, where a = -2. Thus the lower-left 2 is removed (becomes 0).

3.6 Matrix Algebra: Systems

3.6.1 *Vectors*

Vectors as columns of ordered sets of scalars $\in \mathbb{C}$. When we write them out in text, we typically use row notation, with the *transpose* symbol:

$$[a, b, c]^T = \begin{bmatrix} a \\ b \\ c \end{bmatrix}.$$

This is strictly to save space on the page. The notation for *conjugate transpose* is \dagger , for example,

$$\begin{bmatrix} a \\ b \\ c \end{bmatrix}^{\dagger} = \begin{bmatrix} a^* \ b^* \ c^* \end{bmatrix}.$$

The above example is said to be a *3-dimensional* vector because it has three components.

Row versus column-vectors: With rare exceptions, vectors are columns, denoted *column-major*. ²⁰ To avoid confusion, it is a good rule to make your mental default column-major, in keeping with most signal processing (vectorized) software. ²¹ Column-vectors are the unstated default of MATLAB/Octave, only revealed when matrix operations are performed. The need for the column (or row) major is revealed as a consequence of efficiency when accessing long sequences of numbers from computer memory. For example, when forming the sum of many numbers using the MATLAB/Octave command sum(A), where A is a matrix, MATLAB/Octave operates on the columns, returning a row vector of column sums:

$$\operatorname{sum}\begin{bmatrix} 1 & 2 \\ 3 & 4 \end{bmatrix} = [4, 6].$$

²⁰https://en.wikipedia.org/wiki/Row-_and_column-major_order.

²¹In contrast, reading words in English is "row-major".

If the data were stored in row-major order, the answer would be the Column-vector $\begin{bmatrix} 3 \\ 7 \end{bmatrix}$. Thus MATLAB/Octave is column-major by default.

3.6.2 Vector Products

A *scalar product* (aka dot product) is defined to "weight" vector elements before summing them, resulting in a scalar. The transpose of a vector (a *row-vector*) is typically used as a *scale factor* (i.e., weights) on the elements of a vector. For example,

$$\begin{bmatrix} 1\\2\\-1 \end{bmatrix} \cdot \begin{bmatrix} 1\\2\\3 \end{bmatrix} = \begin{bmatrix} 1\\2\\-1 \end{bmatrix}^T \begin{bmatrix} 1\\2\\3 \end{bmatrix} = \begin{bmatrix} 1,2,-1 \end{bmatrix} \begin{bmatrix} 1\\2\\3 \end{bmatrix} = 1 + 2 \cdot 2 - 3 = 2.$$
 Ed:

A more interesting example defines a polynomial

$$\begin{bmatrix} 1\\2\\4 \end{bmatrix} \cdot \begin{bmatrix} 1\\s\\s^2 \end{bmatrix} = \begin{bmatrix} 1\\2\\4 \end{bmatrix}^T \begin{bmatrix} 1\\s\\s^2 \end{bmatrix} = \begin{bmatrix} 1,2,4 \end{bmatrix} \begin{bmatrix} 1\\s\\s^2 \end{bmatrix} = 1 + 2s + 4s^2.$$
 Ed:

Polar scalar product: The vector–scalar product in polar coordinates is (Fig. 3.4)

$$\boldsymbol{B} \cdot \boldsymbol{C} = \|\boldsymbol{B}\| \|\boldsymbol{C}\| \cos \theta \in \mathbb{R},$$

where $\cos \theta \in \mathbb{R}$ is called the *direction-cosine* between **B** and **C**.

Polar wedge-product: The vector wedge-product in polar coordinates is (Fig. 3.4)

$$B \wedge C = ||B|| ||C|| \sin \theta \in \mathbb{R}$$
.

where $\sin \theta \in \mathbb{R}$ is therefore the *direction-sine* between **B** and **C**.

Complex polar scalar product: From these two polar definitions and $e^{J\theta} = \cos \theta + J \sin \theta$,

$$\mathbf{B} \cdot \mathbf{C} + i \mathbf{B} \wedge \mathbf{C} = ||\mathbf{B}||||\mathbf{C}|| e^{s}$$
.

Hence

$$|\mathbf{B} \cdot \mathbf{C}|^2 + |\mathbf{B} \wedge \mathbf{C}|^2 = |\|\mathbf{B}\|^2 \|\mathbf{C}\|^2 \cos^2 \theta | + |\|\mathbf{B}\|^2 \|\mathbf{C}\|^2 \sin^2 \theta | = ||\mathbf{B}||^2 ||\mathbf{C}||^2.$$

This relationship holds true in any vector space, of any number of dimensions, containing vectors \mathbf{B} and \mathbf{C} . In this case $s = \sigma + \omega_J \in \mathbb{C}$ can be the Laplace frequency. Jaynes (1991) has an relevant discussion about this type of scalar product.

3.6.3 Norms of Vectors

The norm of a vector is the scalar product of the vector with itself

$$||A|| = \sqrt{A \cdot A} > 0,$$

forming the Euclidean length of the vector.²²

Euclidean distance between two points in \mathbb{R}^3 : The scalar product of the difference between two vectors $(A - B) \cdot (A - B)$ is the Euclidean distance between the points they define

$$\|\mathbf{A} - \mathbf{B}\| = \sqrt{(a_1 - b_1)^2 + (a_2 - b_2)^2 + (a_3 - b_3)^2}.$$

Triangle inequality

$$\|\mathbf{A} + \mathbf{B}\| = \sqrt{(a_1 + b_1)^2 + (a_2 + b_2)^2 + (a_3 + b_3)^2} \le \|\mathbf{A}\| + \|\mathbf{B}\|.$$

In terms of a right triangle this says the sum of the lengths of the two sides is greater to the length of the hypotenuse, and equal when the triangle degenerates into a line. **Vector cross-product:** The *vector product* (aka cross-product) $A \times B = ||A|| ||B|| \sin \theta$ is defined between the two vectors A and B. In Cartesian coordinates

$$\mathbf{A} \times \mathbf{B} = \det \begin{vmatrix} \hat{\mathbf{x}} & \hat{\mathbf{y}} & \hat{\mathbf{z}} \\ a_1 & a_2 & a_3 \\ b_1 & b_2 & b_3 \end{vmatrix}.$$

The triple product: This is defined between three vectors as

$$\mathbf{A} \cdot (\mathbf{B} \times \mathbf{C}) = \det \begin{vmatrix} a_1 & a_2 & a_3 \\ b_1 & b_2 & b_3 \\ c_1 & c_2 & c_3 \end{vmatrix}.$$

This may be indicated without the use of parentheses, since there can be no other meaningful interpretation. However for clarity, parentheses should be used. The triple product is the volume of the parallelepiped (3D-crystal shape) outlined by the three vectors, as shown in Fig. 3.4.

Dialects of vector notation: Physical fields are, by definition, functions of space \mathbf{x} [m], and in the most general case, time t [s]. When Laplace transformed, the fields become functions of space and complex frequency (e.g., $\mathbf{E}(\mathbf{x},t) \leftrightarrow \mathbf{E}(\mathbf{x},s)$). As before, there are several equivalent vector notations. For example, $\mathbf{E}(\mathbf{x},t) = \begin{bmatrix} E_x, E_y, E_z \end{bmatrix}^T = E_x(\mathbf{x},t)\hat{\mathbf{x}} + E_y(\mathbf{x},t)\hat{\mathbf{y}} + E_z(\mathbf{x},t)\hat{\mathbf{z}}$ is "in-line," to save space. The same equation may written in "displayed" notation as

²²This leaves open the interpretation of the curly norm $||A|| = \sqrt{A \land A} \ge 0$. The obvious answer is in the properties of the Schwarz inequality, which has a complex analytic angle $\theta \in \mathbb{C}(\notin \mathbb{R})$.

$$\boldsymbol{E}(\boldsymbol{x},t) = \begin{bmatrix} E_x(\boldsymbol{x},t) \\ E_y(\boldsymbol{x},t) \\ E_z(\boldsymbol{x},t) \end{bmatrix} = \begin{bmatrix} E_x \\ E_y \\ E_z \end{bmatrix} (\boldsymbol{x},t) = \begin{bmatrix} E_x, E_y, E_z \end{bmatrix}^T \equiv E_x \hat{\boldsymbol{x}} + E_y \hat{\boldsymbol{y}} + E_z \hat{\boldsymbol{z}}.$$

Note the four notations for vectors, bold font, element-wise columns, element-wise transposed rows, and dyadic format. These are all shorthand notations for expressing the vector. Such usage is similar to a dialect in a language.

Complex elements: When the elements are complex $(\in \mathbb{C})$, the transpose is defined as the complex conjugate of the elements. In such complex cases the transpose conjugate may be denoted with a \dagger rather than T

$$\begin{bmatrix} -2J \\ 3J \\ 1 \end{bmatrix}^{\dagger} = \begin{bmatrix} -2J, 3J, 1 \end{bmatrix} \in \mathbb{C}.$$

For this case when the elements are complex, the dot product is a real number (like a length)

$$\mathbf{a} \cdot \mathbf{b} = \mathbf{a}^{\dagger} \mathbf{b} = \begin{bmatrix} a_1^* \ a_2^* \ a_3^* \end{bmatrix} \begin{bmatrix} b_1 \\ b_2 \\ b_3 \end{bmatrix} = a_1^* b_1 + a_2^* b_2 + a_3^* b_3 \in \mathbb{R}.$$

Norm of a complex vector: The dot product of a vector with itself is called the *norm* of a

$$||a|| = \sqrt{a^{\dagger}a} \ge 0.$$

which is always nonnegative, and real.

Such a construction is useful when a and b are related by an impedance matrix

$$V(s) = Z(s)I(s)$$

and we wish to compute the power. For example, the impedance of a mass is ms and a capacitor is 1/sC. When given a system of equations (a mechanical or electrical circuit) one may define an impedance matrix.

Complex power: In this special case, the *complex power* $\mathcal{P}(s) \in \mathbb{C}(s)$ is defined, in the complex frequency domain (s), as

$$\mathcal{P}(s) = \mathbf{I}^{\dagger}(s)\mathbf{V}(s) = \mathbf{I}^{\dagger}(s)\mathbf{Z}(s)\mathbf{I}(s) \leftrightarrow p(t)$$
 [W].

The real part of the complex power must be positive. The imaginary part corresponds to available stored energy.

3.6.4 Matrices

When working with matrices, the role of the weights and vectors can change, depending on the context. A useful way to view a matrix is as a set of column-vectors, weighted by the elements of the column-vector of weights multiplied from the right. For example,

$$\begin{bmatrix} a_{11} & a_{12} & a_{13} & \cdots & a_{1M} \\ a_{21} & a_{22} & a_{23} & \cdots & a_{2M} \\ & & \ddots & \\ a_{N1} & a_{N2} & a_{N3} & \cdots & a_{NM} \end{bmatrix} \begin{bmatrix} w_1 \\ w_2 \\ w_3 \\ \vdots \\ w_M \end{bmatrix} = w_1 \begin{bmatrix} a_{11} \\ a_{21} \\ a_{31} \\ \vdots \\ a_{N1} \end{bmatrix} + w_2 \begin{bmatrix} a_{12} \\ a_{22} \\ a_{32} \\ \vdots \\ a_{N2} \end{bmatrix} + \cdots + w_M \begin{bmatrix} a_{1M} \\ a_{2M} \\ a_{3M} \\ \vdots \\ a_{NM} \end{bmatrix},$$

where the weights are $[w_1, w_2, \dots, w_M]^T$. Note that a_{23} is in row 2, column 3, thus is $a_{\text{row,col}}$. Rows are index vertically, according to the column definition of a vector. Think of the matrix as M column vectors with a_{n1} being the first vector.

Alternatively, the matrix is a set of row vectors of weights, each of which is applied to the column-vector on the right ($[w_1, w_2, \ldots, W_M]^T$). Both views are important (and correct). Don't think of a matrix as being just one or the other. It is both, but not at the same time.

The determinant of a matrix is denoted as either det A or simply |A| (as in the absolute value). The inverse of a square matrix is A^{-1} or invA. If |A| = 0, the inverse does not exist. If it does then $AA^{-1} = A^{-1}A$.

MATLAB/Octave's notional convention for a row-vector is [a, b, c] and a column-vector is [a; b; c]. A prime on a vector takes the complex conjugate transpose. To suppress the conjugation, place a period before the prime. The argument converts the array into a column-vector, without conjugation. A tacit notation in MATLAB is that *vectors* are columns and the index to a vector is a row vector. MATLAB defines the notation 1:4 as the "row-vector" [1, 2, 3, 4], which is unfortunate as it leads users to assume that the default vector is a row. This can lead to serious confusion later, as MATLAB'S default vector is a column. I have not found the above convention explicitly stated, and it took me years to figure this out for myself.

3.6.5 $N \times M$ Complex Matrices

Here are some definitions to learn:

- 1. Scalar: A number—for example, $\{a, b, c, \alpha, \beta, \ldots\} \in \{\mathbb{Z}, \mathbb{Q}, \mathbb{I}, \mathbb{R}, \mathbb{C}\}$
- 2. *Vector*: A quantity having direction as well as magnitude, often denoted by a bold letter \mathbf{x} , or with an arrow over the top \mathbf{x} . In matrix notation, this is typically represented as a single row $[x_1, x_2, x_3, \ldots]$ or single column $[x_1, x_2, x_3, \ldots]^T$ (where T indicates the transpose). In this text we will typically use column-vectors. The

vector may also be written out using unit vector notation to indicate direction. For example, $\mathbf{x}_{3,1} = x_1\hat{\mathbf{x}} + x_2\hat{\mathbf{y}} + x_3\hat{\mathbf{z}} = [x_1, x_2, x_3]^T$, where $\hat{\mathbf{x}}, \hat{\mathbf{y}}, \hat{\mathbf{z}}$ are unit vectors in the x, y, z Cartesian directions (here the vector's subscript 3, 1 indicates its dimensions). The type of notation used frequently depends on the engineering problem you are solving.

- 3. *Matrix:* $A = [\mathbf{a}_1, \mathbf{a}_2, \mathbf{a}_3, \dots, \mathbf{a}_M]_{N,M} = \{a_{n,m}\}_{N,M}$ can be a non-square matrix if the number of elements in each of the vectors (N) is not equal to the number of vectors (M). When M = N, the matrix is square. It may be inverted if its determinant $|A| = \prod \lambda_k \neq 0$ (where λ_k are the eigenvalues). In this text we mainly work only with 2×2 and 3×3 square matrices.
- 4. Linear system of equations: $A\mathbf{x} = \mathbf{b}$ where \mathbf{x} and \mathbf{b} are vectors and matrix A is a square.
 - (a) *Inverse*: The solution of this system of equations may be found by finding the inverse $\mathbf{x} = A^{-1}\mathbf{b}$.
 - (b) Equivalence: If two systems of equations $A_0\mathbf{x} = \mathbf{b}_0$ and $A_1\mathbf{x} = \mathbf{b}_1$ have the same solution (i.e., $\mathbf{x} = A_0^{-1}\mathbf{b}_0 = A_1^{-1}\mathbf{b}_1$), they are said to be equivalent.
 - (c) Augmented matrix: The first type of augmented matrix is defined by combining the matrix with the right-hand side. For example, given the linear system of equations of the form $A\mathbf{x} = \mathbf{y}$

$$\begin{bmatrix} a & b \\ c & d \end{bmatrix} \begin{bmatrix} x_1 \\ x_2 \end{bmatrix} = \begin{bmatrix} y_1 \\ y_2 \end{bmatrix},$$

the augmented matrix is

$$[A|y] = \begin{bmatrix} a & b & y_1 \\ c & d & y_2 \end{bmatrix}.$$

A second type of augmented matrix may be used for finding the inverse of a matrix (rather than solving a specific instance of linear equations Ax = b). In this case the augmented matrix is

$$[A|I] = \begin{bmatrix} a & b & 1 & 0 \\ c & d & 0 & 1 \end{bmatrix}.$$

Performing Gaussian elimination on this matrix, until the left side becomes the identity matrix, yields A^{-1} . This is because multiplying both sides by A^{-1} gives $A^{-1}A|A^{-1}I = I|A^{-1}$.

5. *Permutation matrix* (P): A matrix that is equivalent to the identity matrix, but with scrambled rows (or columns). Such a matrix has the properties $\det(P) = \pm 1$ and $P^2 = I$. For the 2 × 2 case, there is only one permutation matrix:

$$P = \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix} \qquad P^2 = \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix} \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix} = \begin{bmatrix} 1 & 0 \\ 0 & 1 \end{bmatrix}.$$

A permutation matrix P swaps rows or columns of the matrix it operates on. For example, in the 2×2 case, pre-multiplication swaps the rows,

$$PA = \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix} \begin{bmatrix} a & b \\ \alpha & \beta \end{bmatrix} = \begin{bmatrix} \alpha & \beta \\ a & b \end{bmatrix},$$

whereas post-multiplication swaps the columns,

$$AP = \begin{bmatrix} a & b \\ \alpha & \beta \end{bmatrix} \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix} = \begin{bmatrix} b & a \\ \beta & \alpha \end{bmatrix}.$$

For the 3×2 case there are $3 \cdot 2/2 = 3$ such matrices (swap a row with the other 2, then swap the remaining two rows).

6. Gaussian elimination (GE) operations G_k : There are three types of elementary row operations, which may be performed without fundamentally altering a system of equations (e.g., the resulting system of equations is *equivalent*). These operations are (1) swap rows (e.g., using a permutation matrix), (2) scale rows, or (3) perform addition/subtraction of two scaled rows. All such operations can be performed using matrices.

For lack of a better term, we'll describe these as "Gaussian elimination" or "GE" matrices.²³ We will categorize any matrix that performs only elementary row operations (but any number of them) as a "GE" matrix. Therefore, a cascade of GE matrices is also a GE matrix.

Consider the GE matrix

$$G = \begin{bmatrix} 1 & 0 \\ 1 & -1 \end{bmatrix}.$$

(a) This pre-multiplication scales and subtracts row (2) from (1) and returns it to row (2).

$$GA = \begin{bmatrix} 1 & 0 \\ 1 & -1 \end{bmatrix} \begin{bmatrix} a & b \\ \alpha & \beta \end{bmatrix} = \begin{bmatrix} a & b \\ a - \alpha & b - \beta \end{bmatrix}.$$

The shorthand for this Gaussian elimination operation is $(1) \leftarrow (1)$ and $(2) \leftarrow (1) - (2)$.

(b) Post-multiplication adds and scales columns.

$$AG = \begin{bmatrix} a & b \\ \alpha & \beta \end{bmatrix} \begin{bmatrix} 1 & 0 \\ -1 & 1 \end{bmatrix} = \begin{bmatrix} a - b & b \\ \alpha - \beta & \beta \end{bmatrix}.$$

Here the second column is subtracted from the first, and placed in the first. The second column is untouched. This operation is *not* a Gaussian elimination.

²³The term "elementary matrix" may also be used to refer to a matrix that performs an elementary row operation. Typically, each elementary matrix differs from the identity matrix by a single row operation. A cascade of elementary matrices could be used to perform Gaussian elimination.

Therefore, to put Gaussian elimination operations in matrix form, we form a cascade of pre-multiplication matrices.

Here $\det(G) = 1$, $G^2 = I$, which won't always be true if we scale by a number greater than 1. For instance, if $G = \begin{bmatrix} 1 & 0 \\ m & 1 \end{bmatrix}$ (scale and add), then we have $\det(G) = 1$, $G^n = \begin{bmatrix} 1 & 0 \\ n \cdot m & 1 \end{bmatrix}$.

3.6.6 Inverse of the 2×2 Matrix

We shall now apply Gaussian elimination to find the solution $[x_1, x_2]$ for the 2×2 matrix equation Ax = y (Eq. 3.5.8, left). We assume to know [a, b, c, d] and $[y_1, y_2]$.

Here we wish to prove that the left equation (i) has an inverse given by the right equation (ii):

$$\begin{bmatrix} a & b \\ c & d \end{bmatrix} \begin{bmatrix} x_1 \\ x_2 \end{bmatrix} = \begin{bmatrix} y_1 \\ y_2 \end{bmatrix} \quad (i); \qquad \begin{bmatrix} x_1 \\ x_2 \end{bmatrix} = \frac{1}{\Delta} \begin{bmatrix} d & -b \\ -c & a \end{bmatrix} \begin{bmatrix} y_1 \\ y_2 \end{bmatrix} \quad (ii).$$

To take the inverse:

(1) swap the diagonal, (2) change the off-diagonal signs, and (3) normalize by the determinant Δ . We wish to show that the intersection (solution) is given by the equation on the right.

Exercise #1 Show that the equation on the right is the solution of the equation on the left

Sol: By direct substitution (composition) of the right equation into the left equation, we have

$$\begin{bmatrix} a & b \\ c & d \end{bmatrix} \cdot \frac{1}{\Delta} \begin{bmatrix} d & -b \\ -c & a \end{bmatrix} \begin{bmatrix} y_1 \\ y_2 \end{bmatrix} = \frac{1}{\Delta} \begin{bmatrix} ad - bc - ab + ab \\ cd - cd - cb + ad \end{bmatrix} = \frac{1}{\Delta} \begin{bmatrix} \Delta & 0 \\ 0 & \Delta \end{bmatrix}, \quad (3.6.1)$$

which gives the identity matrix.

3.7 Problems AE-2

3.7.1 Topics of This Homework

Linear versus nonlinear systems of equations, Euclid's formula, Gaussian elimination, matrix permutations, Ohm's law, two-port networks,

Deliverables: Answers to problems

3.7.2 Gaussian Elimination

Problem #1 Gaussian elimination

-1.1: Find the inverse of

$$A = \begin{bmatrix} 1 & 2 \\ 4 & 3 \end{bmatrix}.$$

-1.2: Verify that
$$A^{-1}A = AA^{-1} = \begin{bmatrix} 1 & 0 \\ 0 & 1 \end{bmatrix}$$
.

Problem #2 Find the solution to the following 3×3 matrix equation Ax = b by GE. Show your intermediate steps. You can check your work at each step using Octave/MATLAB.

$$\begin{bmatrix} 1 & 1 & -1 \\ 3 & 1 & 1 \\ 1 & -1 & 4 \end{bmatrix} \begin{bmatrix} x_1 \\ x_2 \\ x_3 \end{bmatrix} = \begin{bmatrix} 1 \\ 9 \\ 8 \end{bmatrix}.$$

-2.1 Show (i.e., verify) that the first GE matrix G_1 , which zeros out all entries in the first column is given by

$$G_1 = \begin{bmatrix} 1 & 0 & 0 \\ -3 & 1 & 0 \\ -1 & 0 & 1 \end{bmatrix}.$$

Identify the elementary row operations that this matrix performs.

- -2.2 Find a second GE matrix, G_2 , to put G_1A in upper triangular form. Identify the elementary row operations that this matrix performs.
- -2.3 Find a third GE matrix G_3 that scales each row so that its leading term is 1. Identify the elementary row operations that this matrix performs.
- -2.4: Find the last GE matrix, G_4 , which subtracts a scaled version of row 3 from row 2, and scaled versions of rows 2 and 3 from row 1, such that you are left with the identity matrix $(G_4G_3G_2G_1A = I)$.
- -2.5: Solve for $\{x_1, x_2, x_3\}^T$ using the augmented matrix format $G_4G_3G_2G_1\{A|b\}$ (where $\{A|b\}$ is the augmented matrix). Note that if you've performed the preceding steps correctly, $x = G_4G_3G_2G_1b$.
- -2.6: Find the pivot matrix G that rescales the second row of the augmented matrix A|b by 1/3.

3.7.3 Two Linear Equations

Problem #3 In this problem we transition from a general pair of equations

$$f(x, y) = 0$$
$$q(x, y) = 0$$

3.7 Problems AE-2 137

to the important case of two linear equations

$$y = ax + b$$
$$y = \alpha x + \beta.$$

Note that to help keep track of the variables, roman coefficients (a, b) are used for the first equation and Greek (α, β) for the second.

- -3.1: What does it mean, graphically, if these two linear equations have (1) a unique solution, (2) a nonunique solution, or (3) no solution?
- -3.2: Assuming the two equations have a unique solution, find the solution for x and y.
 - -3.3: When will this solution fail to exist (for what conditions on a, b, α , and β)?
- -3.4: Write the equations as a 2 × 2 matrix equation of the form A**x** = **b**, where **x** = {x, y} T .
- -3.5: Find the inverse of the 2 \times 2 matrix, and solve the matrix equation for x and y.
- -3.6: Discuss the properties of the determinant of the matrix (Δ) in terms of the slopes of the two equations (a and α).

Problem #4 The application of *linear functional relationships* between *two variables* We use 2×2 matrices to describe two-port networks, as discussed in Sect. 3.8. Transmission lines are a great example: Both voltage and current must be tracked as they travel along the line. Figure 3.10 shows an example segment of a transmission line.

Suppose you are given the following pair of linear relationships between the input (source) variables V_1 and I_1 and the output (load) variables V_2 and I_2 of the transmission line:

$$\begin{bmatrix} V_1 \\ I_1 \end{bmatrix} = \begin{bmatrix} J & 1 \\ 1 & -1 \end{bmatrix} \begin{bmatrix} V_2 \\ I_2 \end{bmatrix}.$$

- -4.1: Let the output (the load) be $V_2=1$ and $I_2=2$ (i.e., $V_2/I_2=1/2$ { Ω }). Find the input voltage and current, V_1 and I_1 .
- -4.2: Let the input (source) be $V_1 = 1$ and $I_1 = 2$. Find the output voltage and current, V_2 and I_2 .

3.7.4 Integer Equations: Applications and Solutions


Any equation for which we seek only integer solutions is called a *Diophantine* equation.

Problem #5 A practical example of using a Diophantine equation:

"A merchant had a 40-pound weight that broke into four pieces. When the pieces were weighed, it was found that each piece was a whole number of pounds and

that the four pieces could be used to weigh every integral weight between 1 and 40 pounds. What were the weights of the pieces?" - *Bachet de Bèziriac* (1623).²⁴

Here, weighing is performed using a balance scale that has two pans, with weights on either pan. Thus, given weights of 1 and 3 pounds, one can weigh a 2-pound weight by putting the 1-pound weight in the same pan with the 2-pound weight, and the 3-pound weight in the other pan. Then the scale will be balanced. A solution to the four weights for Bachet's problem is 1 + 3 + 9 + 27 = 40 pounds.



-5.1: Show how the combination of 1-, 3-, 9-, and 27-pound weights can be used to weigh 1, 2, 3, ..., 8, 28, and 40 pounds of milk (or something else, such as flour). Assuming that the milk is in the *left* pan, provide the position of the weights using a negative sign — to indicate the left pan and a positive sign + to indicate the right pan. For example, if the left pan has 1-pound of milk, then 1-pound of milk in the right pan, +1, will balance the scales.

Hint: It is helpful to write the answer in matrix form. Set the vector of values to be weighed equal to a matrix indicating the pan assignments, multiplied by a vector of the weights $[1, 3, 9, 27]^T$. The pan assignments matrix should contain only the values -1 (left pan), +1 (right pan), and 0 (leave out). You can indicate these using -, +, and blanks.

3.7.5 *Vector Algebra in* \mathbb{R}^3

Definitions of the scalar (also called a dot product) $A \cdot B$, cross $A \times B$ and triple product $A \cdot (B \times C)$, may be found in Appendix A, where A, B, C in $\mathbb{R}^3 \subset \mathbb{C}^3$), as shown in Fig. 3.4. A fourth "double-cross" (2) vector product is:²⁵

$$\mathbf{A} \times (\mathbf{B} \times \mathbf{C}) = \alpha_o \mathbf{B} - \beta_o \mathbf{C}$$

where $\alpha_o = A \cdot C$ and $\beta_o = A \cdot B$ (Note: $A \times (B \times C) \neq (A \times B) \times C$).

Problem #6 Scalar product A · B

-6.1: If $\mathbf{A} = a_x \hat{\mathbf{x}} + a_y \hat{\mathbf{y}} + a_z \hat{\mathbf{z}}$ and $\mathbf{B} = b_x \hat{\mathbf{x}} + b_y \hat{\mathbf{y}} + b_z \hat{\mathbf{z}}$, write out the definition of $\mathbf{A} \cdot \mathbf{B}$.

²⁴Taken from Rotman (1996, p. 50).

²⁵Greenberg p. 694, Eq. 8.

3.7 Problems AE-2 139




Fig. 3.6 This is figure is identical to Fig. 3.4, Sect.3.5. Definitions of vectors A, B, C (vectors in \mathbb{R}^3) used in the definition of $A \cdot B$, $A \times B$ and $A \cdot (B \times C)$. There are two algebraic vector products, the scalar(dot) product $A \cdot B \in \mathbb{R}$ and the vector(cross) product $A \times B \in \mathbb{R}^3$. Note that the result of the dot product is a scalar, while the vector product yields a vector, which is \bot to the plane containing A, B

-6.2: The dot product is often defined as $||A|| ||B|| \cos(\theta)$, where $||A|| = \sqrt{A \cdot A}$ and θ is the angle between A, B. If ||A|| = 1, describe how the dot product relates to the vector \mathbf{B} .

Problem #7 Vector (cross) product $A \times B$

-7.1: If $\mathbf{A} = a_x \hat{\mathbf{x}} + a_y \hat{\mathbf{y}} + a_z \hat{\mathbf{z}}$ and $\mathbf{B} = b_x \hat{\mathbf{x}} + b_y \hat{\mathbf{y}} + b_z \hat{\mathbf{z}}$, write out the definition of $\mathbf{A} \times \mathbf{B}$.

-7.2: Show that the cross-product is equal to the area of the parallelogram formed by A, B, namely, $||A|| \, ||B|| \sin(\theta)$, where $||A|| = \sqrt{A \cdot A}$ and θ is the angle between A and B.

Problem #8 Triple product $A \cdot (B \times C)$

Let $\mathbf{A} = [a_1, a_2, a_3]^T$, $\mathbf{B} = [b_1, b_2, b_3]^T$, $\mathbf{C} = [c_1, c_2, c_3]^T$ be three vectors in \mathbb{R}^3 .

-8.1: Starting from the definition of the dot and cross-product, explain using a

diagram and/or words, how one shows that: $\mathbf{A} \cdot (\mathbf{B} \times \mathbf{C}) = \begin{vmatrix} a_1 & a_2 & a_3 \\ b_1 & b_2 & b_3 \\ c_1 & c_2 & c_3 \end{vmatrix}$.

- -8.2: Describe why $|A \cdot (B \times C)|$ is the volume of parallelepiped generated by A, B, and C.
- -8.3: Explain why three vectors **A**, **B**, **C** are in one plane if and only if the triple product $\mathbf{A} \cdot (\mathbf{B} \times \mathbf{C}) = 0$.

Problem #9 Given two vectors \mathbf{A} , \mathbf{B} in the $\hat{\mathbf{x}}$, $\hat{\mathbf{y}}$ plane shown in Fig. 3.6 (same as Fig. 3.4), with $\mathbf{B} = \hat{\mathbf{y}}$ (i.e., $||\mathbf{B}|| = 1$).

-9.1: Show that A may be split into two orthogonal parts, one in the direction of B and the other perpendicular (\bot) to B. Hint: Express the vector products of A and B (dot and cross) in polar coordinates (Greenberg 1988).

$$A = (A \cdot B)B + B \times (A \times B)$$
$$= A_{\parallel} + A_{\perp}.$$

3.7.6 Ohm's Law

In general, impedance is defined as the ratio of a force to a flow. For electrical circuits, the voltage is the force and the current is the flow. Ohm's law states that the voltage across and the current through a circuit element are related by the impedance of that element (which may be a function of frequency). For resistors, the voltage over the current is called the *resistance* and is a constant (e.g., the simplest case is V/I = R). For inductors and capacitors, the voltage over the current is a frequency-dependent impedance (e.g., V/I = Z(s), where s is the complex frequency $s \in \mathbb{C}$).

As shown in Table 3.2, the impedance concept also holds in mechanics and acoustics. In mechanics, the force is equal to the mechanical force on an element (e.g., a mass, dashpot, or spring) and the flow is the velocity. In acoustics, the force is pressure and the flow is the volume velocity or particle velocity of air molecules.

Problem #10 The resistance of an incandescent (filament) lightbulb, measured cold, is about 100 ohms. As the bulb lights up, the resistance of the metal filament increases. Ohm's law says that the current

$$\frac{V}{I} = R(T),$$

where *T* is the temperature. In the United States, the voltage is 120 volts (RMS) at 60 [Hz].

Problem #11 The power in watts is the product of the force and the flow. What is the power of the lightbulb of Problem #10?

Problem #12 State the impedance Z(s) of each of the following circuit elements: (1) a resistor with resistance R, (2) an inductor with inductance L, and (3) a capacitor with capacitance C.

Problem #13 Consider what happens at the triple point of water. As water freezes or thaws, the temperature remains constant at 0 (C°). Once all the water is frozen and more heat is removed, the temperature drops below 0° . As heat is added, water thaws but the temperature remains at 0° . Once all the ice has melted, what is the temperature as more heat is added?

Model the triple point using a Zener diode, a resistor, and a capacitor. A Zener diode holds the voltage constant independent of current. For the case of water's triple point, the voltage represents the temperature of water at the triple point, clamped at 0 [C°]. The current represents the heat flux. The latent heat of water at the triple point is 32 Cal/gm. Thus as the temperature rises from below freezing, the water is

3.7 Problems AE-2 141

clamped at 0° once the triple point is reached. At that point, adding more heat flux has no effect on the temperature until all the ice melts. Once the ice has melted, the temperature again begins to rise until it hits the boiling point, where it again stays at 100° until all the water has evaporated.

3.7.7 Nonlinear (Quadratic) to Linear Equations

In the following problems we deal with algebraic equations in more than one variable that are not linear equations. For example, the circle $x^2 + y^2 = 1$ may be solved for $y(x) = \pm \sqrt{1 - x^2}$. If we let $z_+ = x + y_J = x + J\sqrt{1 - x^2} = e^{\theta J}$, we obtain the equation for half a circle (y > 0). The entire circle is described by the magnitude of z as $|z|^2 = (x + y_J)(x - y_J) = 1$.

Problem #14 Give the curve defined by the equation:

$$x^2 + xy + y^2 = 1$$

- -14.1: Find the function y(x).
- -14.2: Using MATLAB/Octave, plot y(x) and describe the graph.
- -14.3: What is the name of this curve?
- -14.4: Find the solution (in x, p, and q) to these equations:

$$x + y = p$$
$$xy = q.$$

-14.5: Find an equation that is linear in y starting from equations that are quadratic (second-degree) in the two unknowns x and y:

$$x^2 + xy + y^2 = 1 (AE-2.1)$$

$$4x^2 + 3xy + 2y^2 = 3. (AE-2.2)$$

-14.6: Compose the following two quadratic equations and describe the results.

$$x^2 + xy + y^2 = 1$$
$$2x^2 + xy = 1$$

3.7.8 Nonlinear Intersection in Analytic Geometry

Euclid's formula for Pythagorean triplets (Eq. 2.6.6) can be derived by intersecting a circle and a secant line. Consider the nonlinear equation of a unit circle having radius 1, centered at (x, y) = (0, 0),




Fig. 3.7 Derivation of Euclid's formula for the Pythagorean triplets (PT) [a, b, c], based on a composition of a line, having a rational slope $t = p/q \in \mathbb{F}$, and a circle $c^2 = a^2 + b^2$, $[a, b, c] \in \mathbb{N}$. This analysis is attributed to Diophantus (Di·o·phan'·tus) (250 CE), and today such equations are called Diophantine (Di·o·phan'·tine) *equations*. PTs have applications in architecture and scheduling, and many other practical problems. Most interesting is their relation to Rydberg's formula for the eigenstates of the hydrogen atom (Appendix I)

$$x^2 + y^2 = 1,$$

and the secant line through (-1, 0),

$$y = t(x+1),$$

a linear equation having slope t and intercept x=-1. If the slope 0 < t < 1, the line intersects the circle at a second point (a,b) in the positive x, y quadrant. The goal is to find $a,b \in \mathbb{N}$ and then show that $c^2 = a^2 + b^2$. Since the construction gives a right triangle with short sides $a,b \in \mathbb{N}$, then it follows that $c \in \mathbb{N}$.

Problem #15 Derive Euclid's formula, following the arguments provided in Fig. 3.7. -15.1: Draw the circle and the line, given a positive slope 0 < t < 1.

Problem #16 Next define y = t(x + 1) (the line equation) into the equation for the circle, and solve for x(t).

Hint: Because the line intersects the circle at two points, you will get two solutions for x. One of these solutions is the trivial solution x = -1.

-16.1: Substitute the x(t) you found back into the line equation, and solve for y(t).

-16.2: Let t = q/p be a rational number, where p and q are integers. Find x(p,q) and y(p,q).]

3.7 Problems AE-2 143

-16.3: Substitute x(p, q) and y(p, q) into the equation for the circle, and show how Euclid's formula for the Pythagorean triples is generated.

For full points you must show that you understand the argument. Explain the meaning of the comment "magic happens" when t^4 cancels.

3.8 Transmission (ABCD) Matrix Composition Method

Matrix composition: Matrix multiplication represents a composition of 2×2 matrices because the input to the second matrix is the output of the first [this follows from the definition of composition: $f(x) \circ g(x) = f(g(x))$]. Thus the ABCD matrix is also known as the *transmission matrix* or occasionally the *chain matrix*. The general expression for the transmission matrix $\mathcal{T}(s)$ is

$$\begin{bmatrix} V_1 \\ I_1 \end{bmatrix} = \begin{bmatrix} \mathcal{A}(s) \ \mathcal{B}(s) \\ \mathcal{C}(s) \ \mathcal{D}(s) \end{bmatrix} \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix} = \mathcal{T}(s) \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix}. \tag{3.8.1}$$

The four coefficients $\mathcal{A}(s)$, $\mathcal{B}(s)$, $\mathcal{C}(s)$, $\mathcal{D}(s)$ are all complex analytic functions of the Laplace frequency $s = \sigma + j\omega$ (see Sects. 3.1–3.4). Typically they are polynomials in s. For example, $\mathcal{C}(s) = s^2 + 1$. A sum and parallel combination of inductors (masses), capacitors (springs), and resistors (dashpots) results in an Brune impedance, defined as the ratio of two polynomials. Thus such methods are called lumped-element networks. A symbolic eigenanalysis of 2×2 matrices may be found in Appendix B.3.

It is a standard convention to always define the current (flow) into the node. Since the input current on the left of Eq. 3.8.1 is the same as the output current on the right (I_2) , we need the negative sign on I_2 to match the sign convention of current into every node. When we use this construction, all the currents will all agree.

We have already used 2×2 matrix composition for: (1) representing complex numbers (see Sect. 2.2), (2) computing the gcd(m, n) of $m, n \in \mathbb{N}$ (see Sect. F), (3) computing Pell's equation (see Sect. 2.6.2), and (4) computing the Fibonacci sequence (see Sect. 2.6.3). Thus it appears that 2×2 complex analytic matrices have high utility.

Definitions of A, B, C, D: By writing the equations that correspond to Eq. 3.8.1, we see that

$$\mathcal{A}(s) = \frac{V_1}{V_2}\Big|_{I_2=0}, \ \mathcal{B}(s) = -\frac{V_1}{I_2}\Big|_{V_2=0}, \ \mathcal{C}(s) = \frac{I_1}{V_2}\Big|_{I_2=0}, \ \mathcal{D}(s) = -\frac{I_1}{I_2}\Big|_{V_2=0}.$$
(3.8.2)

Example: Figure 3.8 shows two examples of networks that may be analyzed using the ABCD transmission matrix method.

Each equation has a physical interpretation and a corresponding name. Functions \mathcal{A} and \mathcal{C} are said to be *blocked* because the output current I_2 is zero. Functions \mathcal{B} and \mathcal{D} are said to be *short-circuited* because the output voltage V_2 is zero. These two




Fig. 3.8 Left: A low-pass RC electrical filter. The circuit elements R_1 , R_2 , and C are defined. Right: A band-pass acoustic filter. Here, the pressure P is analogous to voltage, and the velocity U is analogous to current. The circuit elements are labeled with their L and C values as integers, to make the algebra simple

terms (blocked vs. short-circuited) are electrical engineering—centric, arbitrary, and fail to generalize to other cases; thus we should avoid these terms.

For example, in a mechanical system *blocked* would correspond to an output isometric (no length change) velocity of zero. In mechanics the *isometric force* is defined as the maximum applied force conditioned on zero velocity (the blocked force). Thus the *short-circuited* force (\mathcal{B}) would correspond to zero force, which is nonsense. These engineering-centric terms do not gracefully generalize, so better terminology is needed. Much of this was sorted out by Thévenin in about 1883 (Van Valkenburg 1964a; Johnson 2003; Kennelly 1893).

 \mathcal{A} and \mathcal{D} are called voltage (force) and current (velocity) transfer functions, since they are ratios of voltages and currents, whereas \mathcal{B} and \mathcal{C} are known as the transfer impedance and transfer admittance. For example, the unloaded (blocked) ($I_2=0$) output voltage $V_2=I_1/\mathcal{C}$ corresponds to the isometric force in mechanics. In this way each term expresses an output (port 2) in terms of an input (port 1) for a given load condition.

Exercise #2 Derive the formula for C in terms of the input and output currents and voltages. Hint: See Eq. 3.8.2.

Solution Writing out the lower equation gives $I_1 = \mathcal{C}V_2 - \mathcal{D}I_2$ and setting $I_2 = 0$, we may obtain the equation for $\mathcal{C} = I_1/V_2|_{I_2=0}$.

Exercise #3 Can C = 0?

Solution: Yes, if $I_2 = 0$ and $I_1 = I_2$, then C = 0. In such cases the 2-port is ill-conditioned as shown in Appendix B.3, Eq. B.3.1. For $C \neq 0$, there needs to be a finite shunt impedance across V_1 , so that $I_1 \neq I_2 = 0$.

3.8.1 Thévenin Parameters of a Source

An important concept in circuit theory is that of the Thévenin parameters: the blocked force (zero flow) and the blocked flow (zero force). Their ratio defines the Thévenin

impedance (Johnson 2003). The open-circuit voltage is defined as the voltage V_2 when the load current is zero ($I_2 = 0$), which was shown in Eq. 3.8.2 to be $V_2/I_1|_{I_2=0} = 1/\mathcal{C}$.

Thévenin Voltage: From Eq. 3.8.1 there are two definitions for the Thévenin voltage $V_{\text{Thev}} = V_2$, conditioned on the source on the left:

$$\frac{V_{\text{Thev}}}{I_1}\Big|_{I_2=0} = \frac{1}{\mathcal{C}} \text{ and } \frac{V_{\text{Thev}}}{V_1}\Big|_{I_2=0} = \frac{1}{\mathcal{A}}.$$
 (3.8.3)

A more general expression is needed when the source impedance is mixed.

Thévenin impedance The Thévenin impedance is the impedance looking into port 2 with $V_1 = 0$; thus

$$Z_{\text{Thev}} = \frac{V_2}{I_2} \bigg|_{V_1 = 0} \,. \tag{3.8.4}$$

From the upper equation of Eq. 3.8.1, with $V_1 = 0$, we obtain $AV_2 = BI_2$; thus

$$Z_{\text{Thev}} = \frac{\mathcal{B}}{\mathcal{A}}.\tag{3.8.5}$$

3.8.2 The Impedance Matrix

With a bit of algebra, we can find the impedance matrix in terms of $\mathcal{A}, \mathcal{B}, \mathcal{C}, \mathcal{D}$ (Van Valkenburg 1964a, p. 310):

$$\begin{bmatrix} V_1 \\ V_2 \end{bmatrix} = \begin{bmatrix} z_{11} & z_{12} \\ z_{21} & z_{22} \end{bmatrix} \begin{bmatrix} I_1 \\ I_2 \end{bmatrix} = \mathcal{Z}(s) \begin{bmatrix} I_1 \\ I_2 \end{bmatrix} = \frac{1}{\mathcal{C}} \begin{bmatrix} \mathcal{A} & \Delta_{\mathcal{T}} \\ 1 & \mathcal{D} \end{bmatrix} \begin{bmatrix} I_1 \\ -I_2 \end{bmatrix}. \tag{3.8.6}$$

The determinate of the transmission matrix is $\Delta_T = \pm 1$, and if C = 0, the impedance matrix does not exist (see Exercise #42).

Definitions of $z_{11}(s)$, $z_{12}(s)$, $z_{21}(s)$, $z_{22}(s)$: The definitions of the matrix elements are easily read off of the equation as

$$z_{11} \equiv \frac{V_1}{I_1}\Big|_{I_2=0}, \ z_{12} \equiv -\frac{V_1}{I_2}\Big|_{I_1=0}, \ z_{21} \equiv \frac{V_2}{I_1}\Big|_{I_2=0}, \ z_{22} \equiv -\frac{V_2}{I_2}\Big|_{I_1=0}.$$
 (3.8.7)

These definitions follow trivially from Eq. 3.8.6 and each element has a physical interpretation. For example, the unloaded $(I_2=0)$, also called blocked or isometric) input impedance is $z_{11}(s) = \mathcal{A}(s)/\mathcal{C}(s)$, while the unloaded transfer impedance is $z_{21}(s) = 1/\mathcal{C}(s)$. For reciprocal systems (Postulate P6, Sect. 3.10.2), $z_{12} = z_{21}$, since $\Delta_{\mathcal{T}} = 1$. For antireciprocal systems, such as dynamic (also called magnetic) loudspeakers and microphones (Kim and Allen 2013), $\Delta_{\mathcal{T}} = -1$; thus $z_{21} = -z_{12} = 1/\mathcal{C}$. Finally z_{22} is the impedance looking into port 2 with port 1 open/blocked ($I_1=0$).




Fig. 3.9 Equivalent circuit for a transmission matrix. This allows us to better visualize the matrix elements in terms of complex impedances $z_a(s)$, $z_c(s)$, $y_b(s)$, as defined in this figure

To understand the meaning of the four impedance variables we analyze the transmission matrix of Fig. 3.9

$$\begin{bmatrix} V_1 \\ I_1 \end{bmatrix} = \begin{bmatrix} 1 + z_a y_b \ z_c (1 + z_a y_b) + z_a \\ y_b \ 1 + y_b z_c \end{bmatrix} \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix}.$$
(3.8.8)

Note that it is easy to invert the T(s) matrix because $\Delta_T = \pm 1$.

From the circuit elements defined in Fig. 3.9 (i.e., z_a , z_c , y_b) we can compute the impedance matrix elements of Eq. 3.8.6 (i.e., z_{11} , z_{12} , z_{21} , z_{22}). For example, the impedance matrix element z_{11} , in terms of z_a and y_b , is easily read off of Fig. 3.9 as the sum of the series and shunt impedances:

$$|z_{11}(s)|_{I_2=0} = z_a + 1/y_b = \frac{A}{C}.$$

Given the impedance matrix, we can then compute transmission matrix T(s)—namely, from Eq. 3.8.6,

$$\frac{1}{\mathcal{C}(s)} = z_{21}, \qquad \frac{\mathcal{A}(s)}{\mathcal{C}(s)} = z_{11}.$$

The theory is best modeled using the transmission matrix (Eq. 3.8.1), while experimental data are best modeled using the impedance matrix (Eq. 3.8.6).

Rayleigh reciprocity: Figure 3.9 is particularly helpful in understanding the Rayleigh reciprocity Postulate P6 ($\mathcal{B}(s) = \pm \mathcal{C}(s)$, Sect. 3.10.2, G):

$$\left. \frac{V_2}{I_1} \right|_{I_2=0} = \left. \frac{V_1}{I_2} \right|_{I_1=0}.$$

This says that the unloaded output voltage over the input current is symmetric, which is obvious from Fig. 3.9.

Potential Case Flow Impedance Units ohms $[\Omega]$ Electrical Voltage (V) $Z = -\nabla V/I$ $[\Omega]$ Current (I) $Z = -\nabla F/U$ Mechanics Force (F) Velocity (U) Mechanical $[\Omega]$ $Z = -\nabla P/V$ Particle velocity Acoustics Pressure (P) Specific $[\Omega]$ (V) $Z = -\nabla \mathcal{P}/\mathcal{V}$ Acoustics Mean pressure Volume velocity Acoustic [Ω] (\mathcal{P}) Entropy ($Z = -\nabla T/\dot{\varsigma}$ Thermal Temperature (T) Thermal $[\Omega]$

Table 3.2 The *generalized impedance* is defined as the ratio of a force to a flow, a concept that also holds in mechanics and acoustics. In mechanics, the force is the mechanical force on an element (e.g., a mass, dashpot, or spring) and the flow is the velocity. In acoustics, the force is the gradient of the pressure, and the flow is the volume velocity or particle velocity of air molecules

Ed:

3.8.3 Network Power Relationships

Impedance is a general concept, closely tied to the definition of power $\mathcal{P}(t)$ (and energy). *Power* is defined as the product of the effort (force) and the flow (current). As described in Table 3.2, these concepts are very general, applying to mechanics, electrical circuits, acoustics, thermal circuits, and any other case where conservation of energy applies. Two basic variables are defined, generalized force and generalized flow, also called *conjugate variables*. The product of the conjugate variables is the power, and the ratio is the impedance. For example, for the case of voltage and current,

$$\mathcal{P}(t) \equiv v(t)i(t), \quad v(t) = z(t) \star i(t), \quad i(t) = v(t) \star v(t)$$

where \star represents convolution (Sect. 4.7.4)

$$v(t) = z(t) \star i(t) \equiv \int_{t=0}^{\infty} z(\tau)i(t-\tau)d\tau \leftrightarrow Z(\omega)I(\omega).$$

Power versus power series, linear versus nonlinear Another place where second-degree equations appear in physical applications is in energy and power calculations. The electrical power is given by the product of the voltage v(t) and current i(t) (or in mechanics as the force times the velocity). For example, if we define $\mathcal{P} = v(t)i(t)$ to be the power \mathcal{P} [watts], then the total energy [joules] at time t is (Van Valkenburg 1964a, Sect. 14)

$$\mathcal{E}(t) = \int_0^t v(t)i(t)dt.$$

From this observe that the power is the rate of change of the total energy

$$\mathcal{P}(t) = \frac{d}{dt}\mathcal{E}(t),$$

reminiscent of the fundamental theorem of calculus (Eq. 4.2.2).

3.8.4 Ohm's Law and Impedance

The ratio of voltage to current is called the *impedance* and it has units of [ohms]. For example, given a resistor of R = 10 [ohms],

$$v(t) = R i(t);$$

namely, 1 [amp] flowing through the resistor would give 10 [volts] across it. Merging the linear relationship due to Ohm's law with the definition of power shows that the instantaneous power in a resistor is quadratic in voltage and current:

$$\mathcal{P}(t) = v(t) \cdot i(t) = v(t)^2 / R = i(t)^2 R, \qquad \mathcal{E}(t) = \int_{-\infty}^t \mathcal{P}(t) dt.$$
 (3.8.9)

Note that Ohm's law is linear in its relationship between voltage and current, whereas power and energy are quadratic nonlinear functions.

Ohm's law generalizes the $I(\omega)$, $V(\omega)$ relation in a very important way, resulting in a linear complex analytic function of complex frequency $s = \sigma + \omega J$ (Kennelly 1893; Brune 1931a). Impedance is a fundamental concept in many fields of engineering. For example: 26 Newton's second law F = ma obeys Ohm's law, with mechanical impedance Z(s) = sm. Hooke's law F = kx for a spring is described by a mechanical impedance Z(s) = k/s. In mechanics a resistor is called a *dashpot* and its impedance is a positive-real constant.

Kirchhoff's laws: KCL and KVL: The laws of electricity and mechanics may be written using Kirchhoff's current and voltage laws (KCL and KVL), which lead to linear systems of equations in the currents and voltages (velocities and forces) of the system under study, with complex coefficients having positive-real parts.

Transfer functions (transfer matrix): The most common standard reference is a physical system that has an input x(t) and an output y(t). If the system is linear, then it may be represented by its impulse response h(t). In such cases, the system equation is

$$y(t) = h(t) \star x(t) \leftrightarrow Y(\omega) = H(s)|_{\sigma=0} X(\omega),$$

namely, the convolution of the input with the impulse response gives the output. This relationship may be written in the frequency domain as a product of the Laplace

²⁶ In acoustics the pressure is a potential, like voltage. The force per unit area is given by $f = -\nabla p$; thus $F = -\int \nabla p \, dS$. Velocity is analogous to a current. In terms of the velocity potential, the velocity per unit area is $v = -\nabla \phi$.

transform of the impulse response evaluated on the ω_J -axis and the Fourier transform of the input $X(\omega) \leftrightarrow x(t)$ and output $Y(\omega) \leftrightarrow y(t)$.

If the system is nonlinear, then the output is not given by a convolution, and the Fourier and Laplace transforms have no obvious meaning.

The question that must be addressed is why the *power* is nonlinear, whereas a *power series* of H(s) is linear: Both have powers of the underlying variables. This is confusing and rarely, if ever, addressed. The quick answer is that powers of the Laplace frequency s correspond to derivatives, which are linear operations, whereas the product of the voltage v(t) and current i(t) is nonlinear. It is confusing because the work power has two different meanings. The important and interesting question will be addressed on Sect. 3.10.2 in terms of the system postulates of physical systems. **Ohm's law:** In general, impedance is defined as the ratio of a force to a flow. For electrical circuits (Table 3.2), the voltage difference is the force and the current is the flow. Ohm's law states that the voltage across and the current through a circuit element are linearly related by the impedance of that element (which is typically a complex function of the complex Laplace frequency $s = \sigma + \omega_J$). For resistors, the voltage over the current is called the *resistance* and is a constant (e.g., the simplest case is $V/I = R \in \mathbb{R}$). For inductors and capacitors, the impedance depends on the Laplace frequency $s = \sigma + \omega_J$.

As shown in Table 3.2, the impedance concept also holds for mechanics and acoustics. In mechanics, the force is equal to the mechanical force on an element (e.g., a mass, dashpot, or spring) and the flow is the velocity. In acoustics, the force density is the negative of the gradient of the pressure, and the flow is the volume velocity (or particle velocity) of air molecules.

In this section we shall derive the method of the linear composition of systems, also known as the *ABCD transmission matrix method*, or in the mathematical literature, the *Möbius (bilinear) transformation*. With the method of matrix composition, we can use a linear system of 2×2 matrices to represent a significant family of networks. By the application of Ohm's law to the circuit shown in Fig. 3.10, we can model a cascade of such cells, which characterize transmission lines (Campbell 1903).

Example of the use of the ABCD matrix composition: Figure 3.10 shows a network composed of a series inductor (mass) that has an impedance $Z_l = sL$ and a shunt capacitor (compliance) that has an admittance $Y_c = sC \in \mathbb{C}$. As determined by Ohm's law, each equation describes a linear relationship between the current and the voltage. For the inductive impedance, applying Ohm's law gives

$$Z_l(s) = (V_1 - V_2)/I_1,$$

where $Z_l(s) = Ls \in \mathbb{C}$ is the complex impedance of the inductor. For the capacitive impedance, applying Ohm's law gives

$$Y_c(s) = (I_1 + I_2)/V_2$$

where $Y_c = sC \in \mathbb{C}$ is the complex admittance of the capacitor.




Fig. 3.10 A single LC cell of the LC transmission line. Every cell of any transmission line may be modeled by the ABCD method as the product of two matrices. For the example shown here, the inductance L of the coil and the capacitance C of the capacitor are in units of [henry/m] and [farad/m]; thus they depend on length Δ_x [m] that the cell represents. Note the flows are always defined as into the + node.

Each of these linear impedance relationships may be written in a 2 × 2 matrix format. The series inductor (C = 0) equation gives ($I_1 = -I_2$)

$$\begin{bmatrix} V_1 \\ I_1 \end{bmatrix} = \begin{bmatrix} 1 & Z_1 \\ 0 & 1 \end{bmatrix} \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix}, \tag{3.8.10}$$

while the shunt capacitor (L = 0) equation yields $(V_1 = V_2)$

$$\begin{bmatrix} V_1 \\ I_1 \end{bmatrix} = \begin{bmatrix} 1 & 0 \\ Y_c & 1 \end{bmatrix} \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix}. \tag{3.8.11}$$

When the second matrix equation for the shunt admittance (Eq. 3.8.11) is substituted into the series impedance equation (Eq. 3.8.10), we find that the ABCD matrix composition ($\mathcal{T}_{12} = \mathcal{T}_1 \circ \mathcal{T}_2$) for the cell is the product of two matrices:

$$\begin{bmatrix} V_1 \\ I_1 \end{bmatrix} = \begin{bmatrix} 1 & Z_l \\ 0 & 1 \end{bmatrix} \begin{bmatrix} 1 & 0 \\ Y_c & 1 \end{bmatrix} \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix} = \begin{bmatrix} 1 + Z_l Y_c & Z_l \\ Y_c & 1 \end{bmatrix} \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix}.$$
(3.8.12)

Note that the determinant of the matrix $\Delta_T = \mathcal{AD} - \mathcal{BC} = 1$. This is not an accident, since the determinants of the two matrices are each 1; thus the determinant of their product is 1. Every cascade of series and shunt elements will always have $\Delta_T = \pm 1$.

For the case of Fig. 3.10, Eq. 3.8.12 has $A(s) = 1 + s^2LC$, B(s) = sL, C(s) = sC, and D = 1. These equations characterize the four possible relationships of the cell's input and output voltage and current. For example, the ratio of the output to input voltage, with the output unloaded, is

$$\frac{V_2}{V_1}\Big|_{t=0} = \frac{1}{\mathcal{A}(s)} = \frac{1}{1 + Z_1 Y_c} = \frac{1}{1 + s^2 LC}.$$

This is known as the *voltage divider relationship*. To derive the *current divider relationship*, we use the lower equation with $V_2 = 0$:

$$\frac{-I_2}{I_1}\bigg|_{V_2=0} = 1.$$

Exercise #4 What happens if the order of Z and Y are reversed? Solution:

$$\begin{bmatrix} V_1 \\ I_1 \end{bmatrix} = \begin{bmatrix} 1 & 0 \\ Y_c & 1 \end{bmatrix} \begin{bmatrix} 1 & Z_l \\ 0 & 1 \end{bmatrix} \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix} = \begin{bmatrix} 1 & Z_l \\ Y_c & 1 + Z_l Y_c \end{bmatrix} \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix}$$
(3.8.13)

This is the same network, reversed in direction.

Exercise #5 What happens if the series element is a capacitor and the shunt an inductor?

Solution:

$$\begin{bmatrix} V_1 \\ I_1 \end{bmatrix} = \begin{bmatrix} 1 & 1/Y_c \\ 0 & 1 \end{bmatrix} \begin{bmatrix} 1 & 0 \\ 1/Z_l & 1 \end{bmatrix} \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix} = \begin{bmatrix} 1 + 1/Z_l Y_c & 1/Y_c \\ 1/Z_l & 1 \end{bmatrix} \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix}$$
(3.8.14)

This circuit is a high-pass filter rather than a low-pass.

Properties of the transmission matrix: The transmission matrix is always constructed from the product of elemental matrices of the form

$$\begin{bmatrix} 1 & Z(s) \\ 0 & 1 \end{bmatrix} \quad \text{or} \quad \begin{bmatrix} 1 & 0 \\ Y(s) & 1 \end{bmatrix}.$$

Thus for the case of reciprocal systems (Postulate P6, Sect. 3.10),

$$\Delta_{\mathcal{T}} = \det \begin{bmatrix} \mathcal{A}(s) \ \mathcal{B}(s) \\ \mathcal{C}(s) \ \mathcal{D}(s) \end{bmatrix} = 1,$$

since the determinant of the product of each elemental matrix is 1 and the determinant of their product is 1. An antireciprocal system may be synthesized by the use of a gyrator, and for such cases $\Delta_T = -1$.

The eigenvalue and vector equations for a T matrix are summarized in Appendix B and discussed in Appendix B.3. The basic postulates of network theory also apply to the matrix elements $\mathcal{A}(s)$, $\mathcal{B}(s)$, $\mathcal{C}(s)$, $\mathcal{D}(s)$, which place restrictions on their functional relationships. For example, Postulate P1 (Sect. 3.10.2) places limits on the poles and/or zeros of each function, since the time response must be causal.

3.9 Signals: Fourier Transforms

The two most fundamental tools for dealing with differential equations in engineering mathematics are the Fourier and the Laplace transforms, which deal with time-frequency analysis (Papoulis 1962).

The Fourier transform $(\mathcal{F}T)$ takes a time-domain signal $f(t) \in \mathbb{R}$ and transforms it to the frequency domain by taking the scalar product (also called dot product) of f(t) with the complex time vector $e^{-j\omega t}$:

$$f(t) \leftrightarrow F(\omega) = f(t) \cdot e^{-j\omega t}$$

where $F(\omega)$ and $e^{-J\omega t} \in \mathbb{C}$ and $\omega, t \in \mathbb{R}$. Here f(t) and $e^{J\omega t}$ are in a Hilbert space, as discussed in Sect. 3.5.1. The scalar product between two vectors results in a scalar (number), as discussed in Appendix A.3.

Definition of the Fourier transform: The forward transform takes f(t) to $F(\omega)$, while the inverse transform takes $F(\omega)$ to $\widetilde{f}(t)$. The tilde indicates that, in general, the recovered inverse transform signal can be slightly different from f(t). Examples are presented in Table 3.6.

$$F(\omega) = \int_{-\infty}^{\infty} f(t)e^{-j\,\omega t}dt \qquad \qquad \widetilde{f}(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} F(\omega)e^{j\,\omega t}d\omega \qquad (3.9.1)$$

$$F(\omega) \leftrightarrow f(t) \qquad \qquad \widetilde{f}(t) \leftrightarrow F(\omega).$$

It is accepted in the engineering and physics literature to use the case of the variable to indicate the type of argument. A time-domain function is f(t), where t has units of seconds [s] and is lowercase. Its Fourier transform is uppercase $F(\omega)$ and is a function of frequency, having units of either hertz [Hz] or radians per second [2π Hz]. This case convention helps the reader parse the variable under consideration. This notation is helpful but not agree with the notation used in mathematics, where units are rarely cited.

Table 3.3 The general rule is that if a function is discrete in one domain (time or frequency) it is periodic in the other. Abbreviations: $\mathcal{F}T$: Fourier Transform; FS: Fourier Series; DTFT: Discrete-time Fourier transform; DFT: Discrete Fourier transform (the FFT is a "fast" DFT)

FREQUENCY \ TIME	Continuous t	Discrete t _k	Periodic $((t))_{T_o}$
Continuous ω	FT	_	_
Discrete ω_k	-	DFT (FFT)	FS
Periodic $((\omega))_{\Omega_o}$	-	DTFT	DFT (FFT)

Types of Fourier transforms: As summarized in Table 3.3, each \mathcal{FT} type is determined by symmetries in time and frequency. A time function f(t) may be continuous in time, with $-\infty < t < \infty$, discrete in time, $f_n = f(t_n)$ with $t_k = kT_s$, where T_o is called the Nyquist sample period, or periodic in time, $f((t))_{T_p} = f(t + kT_p)$, where T_p is called the period. Here $k, n \in \mathbb{Z}$ and $T_o, T_p \in \mathbb{R}$. When time is discrete it is commonly represented as either x[n] or $x(t_n)$.

A general rule is that if a function is discrete in one domain (time or frequency), it is periodic in the other domain (frequency or time). For example, the discrete-time function f_n must have a periodic frequency response—namely, $f_n \leftrightarrow F((\omega))_{T_p}$. This is the case of the discrete-time Fourier transform (DTFT). Alternatively, when the time function is periodic, the frequencies must be discrete—namely, $f((t))_{T_p} \leftrightarrow F(\omega_k)$. This is the case of the Fourier series (FS). When both the time and frequencies are discrete, both the time and frequencies must be periodic. This is the case of the discrete Fourier transform (DFT). These four cases are summarized in Table 3.3.

Table 3.4 As summarized in this table of scalar products (dot products), the four types of Fourier transforms differ in their support in time and frequency. These four are the (1) *Fourier transform*, (2) *Fourier series*, (3) *discrete-time Fourier transform*, and (4) *discrete Fourier transform*. The support in time and frequency defines the form of the inner product. In this way all the various forms of Fourier transforms may be reduced to differences in the scalar product, as dictated by the support of the signals in time and frequency. In the above $t_n = nT_s$, $f_k = k/T_s$ represent discrete-time and frequency samples, where T_s is one sample period. The signal period for the Fourier series (FS) is T [s]. For the discrete Fourier transform (DFT) the signal period is NT, where N is the length of the DFT. Typically the transform length is taken to be a power of 2, such as N = 1024 samples. This is done to improve the speed of the transform, known as the fast Fourier transform (FFT). The term *form* provides the mathematical form of the scalar product which depends on the signal symmetry (finite-duration, periodic, causal/one-sided, discrete-time/frequency, continuous-time/frequency, etc.). *ON* stands for *ortho-normal*. This column shows the signals that are used when taking the transform. The signal is projected onto these vectors by the scalar product

Name	Domain	Scalar product	Form	ON
(1) FT	$-\infty < t \in \mathbb{R} < \infty$	$x(t) \cdot y(t)$	$\int_{-\infty}^{\infty} x(t)y(t)dt$	$e^{-j2\pi ft}$
	$-\infty < f \in \mathbb{R} < \infty$	$X(f) \cdot Y(f)$	$\int_{-\infty}^{\infty} X(f)Y(f)\frac{d\omega}{2\pi}$	$e^{j2\pi ft}$
(2) FS	$0 \le t \in \mathbb{R} \le T$	$x((t)) \cdot y((t))$	$\begin{array}{c c} \frac{1}{T} \int\limits_{t=0}^{T} x(t)y(t)dt \\ \hline \end{array}$	$e^{-j2\pi f_k t}$
	$-\infty < f_k = \frac{k}{T} \in \mathbb{N} < \infty$	$X_k \cdot Y_k$	$\sum_{k=-\infty}^{\infty} X_k Y_k$	$e^{j2\pi f_k t}$
(3) DTFT	$-\infty < t_n < \infty$	$x_n \cdot y_n$	$\sum_{n=-\infty}^{\infty} x_n y_n$	$e^{-j2\pi t_n\Omega}$
	$-\pi < \Omega < \pi$	$X((\Omega)) \cdot Y((\Omega))$	$\int_{-\pi}^{\pi} X(e^{j\Omega}) Y(e^{j\Omega}) \frac{d\Omega}{2\pi}$	$e^{j2\pi t_n\Omega}$
(4) DFT	$0 \le t_n = nT \le (N-1)T$	$x_n y_n$	$\sum_{n=0}^{N-1} x_n y_n$	$e^{-J2\pi t_n f_k}$
	$0 \le f_k = \frac{k}{NT} \le \frac{(N-1)}{NT}$	$X_k Y_k$	$\frac{1}{N} \sum_{n=0}^{N-1} X_k Y_k$	$e^{j2\pi t_n f_k}$

3.9.1 Properties of the Fourier Transform

- 1. Both time t and frequency ω are real.
- 2. When a function is periodic in one domain (t, f), it must be discrete in the other (Table 3.3).
- 3. For the forward transform (time to frequency), the sign of the exponential is negative.
- 4. The limits on the integrals in both the forward and reverse FTs are $[-\infty, \infty]$.
- 5. When we take the inverse Fourier transform, the scale factor of $1/2\pi$ is required to cancel the 2π in the frequency differential $d\omega = 2\pi df$.
- 6. The Fourier step function is defined by the use of superposition of 1 and sgn(t) = t/|t| as

$$\widetilde{u}(t) \equiv \frac{1 + \operatorname{sgn}(t)}{2} = \begin{cases} 1 & t > 0 \\ 1/2 & t = 0 \\ 0 & t < 0 \end{cases}$$

Taking the FT of a delayed step function, we get

$$\widetilde{u}(t-T_o) \leftrightarrow \frac{1}{2} \int_{-\infty}^{\infty} \left[1 - \operatorname{sgn}(t-T_o) \right] e^{-j\omega t} dt = \pi \widetilde{\delta}(\omega) + \frac{e^{-j\omega T_o}}{j\omega}.$$

Thus the FT of the step function has the term $\pi\delta(\omega)$ due to the 1 in the definition of the Fourier step. This term introduces a serious flaw with the FT of the step function: While it appears to be causal, it is not. Compare this to the convolution $u(t) \star u(t)$ in Table 3.9.

- 7. The convolution $\widetilde{u}(t)\star\widetilde{u}(t)$ is not defined because both $1\star 1$ and $\widetilde{\delta}^2(\omega)$ are not defined.
- 8. The inverse $\mathcal{F}T$ has convergence issues whenever there is a discontinuity in the time response. We indicate this with a hat over the reconstructed time response. The error between the target time function and the reconstructed is zero in the root-mean sense, but not point-wise.
 - Specifically, at the discontinuity point for the Fourier step function (t = 0) $\widetilde{u}(t) \neq u(t)$, yet $\int |\widetilde{u}(t) u(t)|^2 dt = 0$. At the point of the discontinuity, the reconstructed function displays Gibbs ringing (it oscillates around the step and hence does not converge at the jump). The \mathcal{LT} does not exhibit Gibbs ringing and is exact.
- 9. The \mathcal{FT} is not always analytic in ω , as in this example of the step function. The step function cannot be expanded in a Taylor series about $\omega=0$ because $\widetilde{\delta}(\omega)$ is not analytic in ω .
- 10. The Fourier δ function is denoted $\widetilde{\delta}(t)$ to differentiate it from the Laplace delta function $\delta(t)$. They differ because the step functions differ due to the convergence problem.

FT	Functional properties
$\frac{d}{dt}v(t) \leftrightarrow j\omega V(\omega)$	deriv
$\int_{-\infty}^{\infty} f(t - \tau)g(\tau)d\tau = f(t) \star g(t) \leftrightarrow F(\omega)G(\omega)$	conv
$f(t)g(t) \leftrightarrow \frac{1}{2\pi}F(\omega) \star G(\omega)$	mult
$f(at) \leftrightarrow \frac{1}{a} F\left(\frac{\omega}{a}\right)$	scale

Table 3.5 Functional relationships between signals and their \mathcal{FT} 's

11. One may define

$$\widetilde{u}(t) = \int_{-\infty}^{t} \widetilde{\delta}(t)dt$$

and the somewhat questionable notation

$$\widetilde{\delta}(t) = \frac{d}{dt}\widetilde{u}(t),$$

since the Fourier step function is not analytic.

12. The rec(t) function is defined as

$$\operatorname{rec}(t) = \frac{\widetilde{u}(t) - \widetilde{u}(t - T_o)}{T_o} = \begin{cases} 0 & t < 0 \\ 1/T_o & 0 < t < T_o \\ 0 & t > T_0 \end{cases}.$$

It follows that $\widetilde{\delta}(t) = \lim_{T \to 0}$. Like $\widetilde{\delta}(t)$, the rec(t) has unit area (Table 3.5).

Periodic signals: As shown in Table 3.3 there are four variants of the $\mathcal{F}T$ that depend on the symmetry in time and frequency. For example, when the time signal is sampled (discrete in time), the frequency response becomes periodic, leading to the DTFT. When a time response is periodic, the frequency response is sampled (discrete in frequency), leading to the FS. These two symmetries may be simply characterized only as *periodic in time* \Rightarrow discrete in frequency and *periodic in frequency* \Rightarrow discrete in time. When a function is discrete in both time and frequency, it is necessarily periodic in time and frequency, leading to the DFT. The DFT is typically computed with an algorithm called the FFT, which can dramatically speed up the calculation when the data are a power of 2 in length.

Exercise #6 Consider the Fourier series scalar (dot) product (Eq. 3.5.2) between "vectors" $f(t)_{T_a}$ and $e^{-j\omega_k t}$:

$$F(\omega_k) = f((t))_{T_o} \cdot e^{-j\omega_k t}$$

$$\equiv \frac{1}{T_o} \int_0^{T_o} f(t) e^{-j\omega_k t} dt,$$

Table 3.6 Basic (Level I) Fourier transforms. Note that $a > 0 \in \mathbb{R}$ has units [rad/s]. To flag this necessary condition, we use |a| to ensure this condition will be met. The other constant $T_o \in \mathbb{R}$ [s] has no restrictions, other than being real. Complex constants may not appear as the argument to a delta function, since complex numbers do not have the order property

$f(t) \leftrightarrow F(\omega)$	Name
$\widetilde{\delta}(t) \leftrightarrow 1(\omega) \equiv 1 \ \forall \ \omega$	Delta
$1(t) \equiv 1 \forall t \leftrightarrow 2\pi \widetilde{\delta}(\omega)$	Step
$\frac{\operatorname{sgn}(t) = \frac{t}{ t } \leftrightarrow \frac{2}{j\omega}}{\widetilde{u}(t) = \frac{1(t) + \operatorname{sgn}(t)}{2} \leftrightarrow \pi\widetilde{\delta}(\omega) + \frac{1}{j\omega} \equiv \widetilde{U}(\omega)}$	
$\widetilde{u}(t) = \frac{1(t) + \operatorname{sgn}(t)}{2} \leftrightarrow \pi \widetilde{\delta}(\omega) + \frac{1}{I\omega} \equiv \widetilde{U}(\omega)$	Step
$\widetilde{\delta}(t-T_o) \leftrightarrow e^{-J\omega T_o}$	Delay
$\widetilde{\delta}(t-T_o) \star f(t) \leftrightarrow F(\omega) e^{-J\omega T_o}$	Delay
$\widetilde{u}(t)e^{- a t} \leftrightarrow \frac{1}{ \omega+ a }$	Exp
$rec(t) = \frac{1}{T_o} \left[\widetilde{u}(t) - \widetilde{u}(t - T_o) \right] \leftrightarrow$	Pulse
$\frac{1}{T_o}\left(1-e^{-J\omega T_o}\right)$	
$\widetilde{u}(t)\star\widetilde{u}(t)\leftrightarrow\widetilde{\delta}^2(\omega)$ Not defined	NaN

where $\omega_0 = 2\pi/T_o$ and f(t) has period T_o —that is, $f(t) = f(t + nT_o) = e^{j\omega_n t}$ with $n \in \mathbb{N}$ and $\omega_k = k\omega_o$. What is the value of the Fourier series scalar product? **Sol:** Evaluating the scalar product, we find

$$\begin{split} e^{J\omega_n t} \cdot e^{-J\omega_k t} &= \frac{1}{T_o} \int_0^{T_o} e^{J\omega_n t} e^{-J\omega_k t} dt \\ &= \frac{1}{T_o} \int_0^{T_o} e^{2\pi J(n-k)t/T_o} dt = \begin{cases} 1 & n=k \\ 0 & n \neq k \end{cases}. \end{split}$$

The two signals (vectors) are orthogonal.

Exercise #7 Consider the discrete-time $\mathcal{F}\mathcal{T}$ (DTFT) as a scalar (dot) product (Eq. 3.5.2, between "vectors" $f_n = f(t)|_{t_n}$ and $e^{-J\omega t_n}$, where $t_n = nT_s$ and $T_s = 1/2F_{\text{max}}$ is the sample period (Tables 3.4 and 3.6).

Sol: The scalar product over $n \in \mathbb{Z}$ is

$$F((\omega))_{2\pi} = f_n \cdot e^{-j\omega t_n}$$

$$\equiv \sum_{n=-\infty}^{\infty} f_n e^{-j\omega t_n},$$

where $\omega_0 = 2\pi/T_o$ and $\omega_k = k\omega_o$ is periodic (i.e., $F(\omega) = F(\omega + k\omega_o)$).

3.10 Systems: Laplace Transforms

The Laplace transform $\mathcal{L}\mathcal{T}$ takes real causal signals $f(t)u(t) \in \mathbb{R}$, as a function of real time $t \in \mathbb{R}$, that are strictly zero for negative time (f(t) = 0 for t < 0), and transforms them into complex analytic functions $(F(s) \in \mathbb{C})$ of complex frequency $s = \sigma + \omega J$. As we did for the Fourier transform, we use the same upper–lowercase notation: $f(t) \leftrightarrow F(s)$.

When a signal is zero for negative time f(t < 0) = 0, it is said to be *causal*, and the resulting transform F(s) must be complex analytic over significant regions of the s plane. For a function of time to be causal, time *must* be real $(t \in \mathbb{R})$, since if it were complex, it would lose the order property (thus it could not be causal). It is helpful to emphasize the causal nature of f(t)u(t) to force causality, with the Heaviside step function u(t). Any restriction on a function (e.g., real, causal, periodic, positive-real part, etc.) is called a *symmetry property*. There are many forms of symmetry. The concept of symmetry is very general and widely used in both mathematics and physics, where it is more generally known as *group theory*. One-sided periodic transforms also exist, such as the system shown in Fig. 3.3.

Definition of the Laplace transform: The forward and inverse Laplace transforms are defined in Eq. 3.10.1. Here $s = \sigma + j\omega \in \mathbb{C}$ [$2\pi Hz$] is the complex Laplace frequency in radians and $t \in \mathbb{R}$ [s] is the time in seconds.

Forward and inverse Laplace transforms (Table 3.7):

$$F(s) = \int_{0^{-}}^{\infty} f(t)e^{-st}dt \qquad f(t) = \frac{1}{2\pi J} \int_{\sigma_{o} - \infty J}^{\sigma_{o} + \infty J} F(s)e^{st}ds \qquad (3.10.1)$$

$$F(s) \leftrightarrow f(t) \qquad f(t) \leftrightarrow F(s).$$

Tables of functional properties are shown in Table 3.8, while basic transforms are provided in Appendix C, Table 3.9. Properties of more advanced $\mathcal{L}Ts$ are in Table C.2. When we deal with engineering problems, it is convenient to separate the *signals* we use from the *systems* that process them. We do this by treating signals, such as speech and music, differently from a system, such as a filter. In general, signals may

Table 3.7 Laplace transforms are complementary to the class of Fourier transforms $\mathcal{F}\mathcal{T}$ because the time function must be a causal function. All $\mathcal{L}\mathcal{T}s$ are *complex analytic* in the complex frequency $s = \sigma + \omega_J$ domain. As an example, a causal function that is continuous but one-sided in time is the *step function* u(t), which has the $\mathcal{L}\mathcal{T}u(t) \leftrightarrow 1/s$. When a function is discrete in time but one-sided, it has a zeta-transform. The discrete-time step function is $u_n = u[n] \leftrightarrow 1/(1 - z^{-n})$

FREQUENCY \ TIME	Continuous t	Discrete $t[k]$	Causal-periodic $((t))_{T_o}$
Continuous s	LT	_	_
Discrete $\omega[k]$	_	_	Unknown
Periodic $ z e^{\theta J}$	_	z-Transform	-

LT Functional properties		
$\frac{d}{dt}f(t) = \delta'(t) \star f(t)$	$\leftrightarrow sF(s)$	Deriv
$f(t) \star g(t) = \int_{t=0}^{t} f(t - \tau)g(\tau)d\tau$	$\leftrightarrow F(s)G(s)$	causal convolution
$\int_{t=0}^{t} f(t-\tau)g(\tau)d\tau$		
$u(t) \star f(t) = \int_{0^{-}}^{t} f(t)dt$	$\leftrightarrow \frac{F(s)}{s}$	convolution with step
f(at)u(at)	$\Leftrightarrow \frac{1}{a}F\left(\frac{s}{a}\right) a \in \mathbb{R} \neq 0$	Scaling
$f(t)e^{-at}u(t)$	$\leftrightarrow F(s+a)$	Damped
$f(t-T)e^{-a(t-T)}u(t-T)$	$\leftrightarrow e^{-sT}F(s+a)$	Damped and delayed
f(-t)u(-t)	$\leftrightarrow F(-s)$	Reverse time
$f(-t)e^{-at}u(-t)$	$\leftrightarrow F(a-s)$	Time-reversed and damped
$\frac{\sin(t)u(t)}{t}$	$\leftrightarrow \tan^{-1}(1/s)$	Half-sync

Table 3.8 Functional relationships between systems and their LTs

start and end at any time. The concept of causality has no mathematical meaning in signal space. Systems, on the other hand, obey rigid rules (to ensure that they remain physical). These physical restrictions are described in terms of the system postulates, which we present on Sect. 3.10.2. There is a question as to why postulates are needed and which ones are the best choices. These questions are discussed in lectures by Feynman (1968, 1970a). The original video is also available online in many places, including YouTube.²⁷ There may be no definitive answers to these questions, but having a set of postulates is a useful way of thinking about physics.

Types of Laplace transforms: As shown in Table 3.7 there are three types of $\mathcal{L}Ts$. The function may be continuous in time, in which it is also continuous in the Laplace frequency s. It may be discrete in time and therefore periodic in frequency θ , which is called the z-transform. Or it may be causal-periodic in time and therefore discrete in frequency. This transform has no name ("unknown," as best I know). An example is the Riemann zeta function (Fig. C.1).

3.10.1 Properties of the Laplace Transform

The following is a summary description of the LT:

- 1. Time $t \in \mathbb{R}$ [s] and the Laplace frequency [rad] are defined as $s = \sigma + \omega_I \in \mathbb{C}$.
- 2. Given a Laplace transform (\mathcal{LT}) pair $f(t) \leftrightarrow F(s)$, in the engineering literature, the time domain is always lowercase [f(t)] and causal [i.e., f(t < 0) = 0], and the *frequency domain* is uppercase [F(s)]. Maxwell's venerable equations are the unfortunate exception to this otherwise universal rule.
- 3. The target time function f(t < 0) = 0 (i.e., it must be causal). The time limits are $0^- < t < \infty$. Thus the integral must start from slightly below t = 0 to integrate over a delta function at t = 0. For example, if $f(t) = \delta(t)$, the integral must

²⁷https://www.youtube.com/watch?v=JXAfEBbaz_4, https://www.youtube.com/watch?v=YaUlq XRPMmY, https://www.youtube.com/watch?v=xnzB_IHGyjg.

Table 3.9 Laplace transforms of f(t), $\delta(t)$, u(t), $\operatorname{rect}(t)$, t_0 , $p, e \in \mathbb{R}$ and F(s), G(s), $s, a \in \mathbb{C}$. Given a *Laplace transform* (LT) pair $f(t) \leftrightarrow F(s)$, the frequency domain is always uppercase [e.g., F(s)] and the time-domain lowercase [f(t)] and causal (i.e., f(t < 0) = 0). An extended list of transforms is given in Appendix C, Table C.2

8 11	
$f(t) \leftrightarrow F(s)$ $t \in \mathbb{R}; \ s, F(s) \in \mathbb{C}$	Name
$\delta(t) \leftrightarrow 1$	Dirac
$\delta(a t) \leftrightarrow \frac{1}{ a } \qquad \qquad a \neq 0$	Time-scaled Dirac
$\delta(t-t_0) \leftrightarrow e^{-st_0}$	Delayed Dirac
$\delta(t-t_0) \star f(t) \leftrightarrow F(s)e^{-st_0}$	_
$\sum_{n=0}^{\infty} \delta(t - nt_0) = \frac{1}{1 - \delta(t - t_0)} \leftrightarrow \frac{1}{1 - e^{-st_0}} =$	One-sided impulse train
$\sum_{n=0}^{\infty} e^{-snt_0}$	
$u(t) \leftrightarrow \frac{1}{s}$	Heaviside step
$u(-t) \leftrightarrow -\frac{1}{s}$	Anticausal step
$u(at) \leftrightarrow \frac{a}{s} a \neq 0 \in \mathbb{R}$	Dilated or reversed step
$e^{at}u(-t)\leftrightarrow \frac{1}{-s+a}$	Anticausal damped step
$e^{-at}u(t) \leftrightarrow \frac{1}{s+a}$ $a > 0 \in \mathbb{R}$	Damped step
$\cos(at)u(t) \leftrightarrow \frac{1}{2}\left(\frac{1}{s-a} + \frac{1}{s+a}\right) \qquad a \in \mathbb{R}$	cos
$\sin(at)u(t) \leftrightarrow \frac{1}{2J}\left(\frac{1}{s-a} - \frac{1}{s+a}\right) \qquad a \in \mathbb{C}$	Damped sin
$u(t-t_0) \leftrightarrow \frac{1}{s}e^{-st_0}$ $t_0 > 0 \in \mathbb{R}$	Time delay
$rect(t) = \frac{1}{t_0} [u(t) - u(t - t_0)] \leftrightarrow \frac{1}{t_0} (1 - e^{-st_0})$	Rect-pulse
$u(t) \star u(t) = tu(t) \leftrightarrow 1/s^2$	ramp
$u(t) \star u(t) \star u(t) = \frac{1}{2}t^2u(t) \leftrightarrow 1/s^3$	Double ramp
$\frac{1}{\sqrt{t}}u(t) \leftrightarrow \sqrt{\frac{\pi}{s}}$	
$t^p u(t) \leftrightarrow \frac{\Gamma(p+1)}{s^{p+1}}$	$\Re p > -1, q \in \mathbb{C}$

include both sides of the impulse. If we want to include noncausal functions such as $\delta(t+1)$, we must extend the lower time limit. In such cases we simply set the lower limit of the integral to $-\infty$ and let the integrand (f(t)) determine the limits.

- 4. When we take the forward transform $(t \to s)$, the sign of the exponential is negative. This is necessary to ensure that the integral converges when the integrand $f(t) \to \infty$ as $t \to \infty$. For example, if $f(t) = e^t u(t)$ (i.e., without the negative σ exponent), the integral does not converge.
- 5. The limits on the integrals of the reverse $\mathcal{L}Ts$ are $[\sigma_o \infty_J, \sigma_o + \infty_J] \in \mathbb{C}$. These limits are further discussed in Sect. 4.7.4.
- 6. When we take the inverse Laplace transform, the normalization factor of $1/2\pi J$ is required to cancel the $2\pi J$ in the differential ds of the integral.
- 7. The frequencies for the LT must be complex, and in general F(s) is complex analytic for $\sigma > \sigma_o$. It follows that the real and imaginary parts of F(s) are related by the Cauchy–Riemann conditions. Given $\Re\{F(s)\}$, it is possible to find $\Im\{F(s)\}$ (Boas 1987). Read more on this in Sect. 4.2.3.

- 8. To take the inverse Laplace transform, we must learn how to integrate in the complex *s* plane. This is explained on Sect. 4.5–4.7.4.
- 9. The Laplace Heaviside step function is defined as

$$u(t) = \int_{-\infty}^{t} \delta(t)dt = \begin{cases} 1 & \text{if } t > 0 \\ \text{NaN if } t = 0 \\ 0 & \text{if } t < 0 \end{cases}$$

Alternatively, we can define $\delta(t) = du(t)/dt$.

10. It is easily shown that $u(t) \leftrightarrow 1/s$ by direct integration,

$$F(s) = \int_0^\infty u(t) e^{-st} dt = -\frac{e^{-st}}{s} \bigg|_0^\infty = \frac{1}{s}.$$

With the LT step (u(t)), there is no Gibbs ringing effect.

11. The Laplace transform of a Brune impedance takes the form of a ratio of two polynomials. In such cases, the roots of the numerator polynomial are called the *zeros* while the roots of the denominator polynomial are called the *poles*. For example, the \mathcal{LT} of $u(t) \leftrightarrow 1/s$ has a pole at s=0, which represents integration, since

$$u(t) \star f(t) = \int_{-\infty}^{r} f(\tau)d\tau \leftrightarrow \frac{F(s)}{s}.$$

- 12. The $\mathcal{L}\mathcal{T}$ is quite different from the $\mathcal{F}\mathcal{T}$ in terms of its analytic properties. For example, the step function $u(t) \leftrightarrow 1/s$ is complex analytic everywhere except at s=0. The $\mathcal{F}\mathcal{T}$ of $1 \leftrightarrow 2\pi \widetilde{\delta}(\omega)$ is not analytic anywhere.
- 13. The dilated step function $(a \in \mathbb{R})$ is

$$u(at) \leftrightarrow \int_{-\infty}^{\infty} u(at)e^{-st}dt = \frac{1}{a} \int_{-\infty}^{\infty} u(\tau)e^{-(s/a)\tau}d\tau = \frac{a}{|a|} \frac{1}{s} = \pm \frac{1}{s},$$

where we have made the change of variables $\tau = at$. The only effect that a has on u(at) is the sign of t, since u(t) = u(2t). However, $u(-t) \neq u(t)$, since $u(t) \cdot u(-t) = 0$, and u(t) + u(-t) = 1, except at t = 0, where it is not defined. Once complex integration in the complex plane has been defined (see Sect. 4.2.3), we can justify the definition of the inverse \mathcal{LT} (Eq. 3.10.1).

Causal-periodic signals: This is a special symmetry that occurs due to functions that are causal *and* periodic in frequency. The best example is the *z*-transform, which applies to causal (one-sided in time) discrete-time signals. The harmonic series (Eq. 3.2.10) is the *z*-transform of the discrete-time step function and is thus, due to symmetry, analytic within the RoC in the complex frequency (*z*) domain.

²⁸https://en.wikipedia.org/wiki/Laplace_transform#Table_of_selected_Laplace_transforms.

The double brackets on $f((t))_{T_o}$ indicate that f(t) is periodic in t with period T_o —that is, $f(t) = f(t + kT_o)$ for all $k \in \mathbb{N}$. Averaging over one period and dividing by T_o give the average value.

3.10.1.1 Inverse LT

As we will discuss on Sect. 3.10, to invert the $\mathcal{L}\mathcal{T}$ one must use the Cauchy residue theorem (CT-3), which requires closure of the contour \mathcal{C} at $\omega_J \to \pm j\infty$,

$$\oint_{\mathcal{C}} = \int_{\sigma_0 - j\infty}^{\sigma_0 + j\infty} + \int_{\subset_{\infty}},$$

where the path represented by \subset_{∞} is a semicircle of infinite radius. For a causal, stable (e.g., doesn't "blow up" in time) signal, all of the poles of F(s) must be inside of the Laplace contour, in the left half s-plane.

Example: Hooke's law for a spring states that the force f(t) is proportional to the displacement x(t)—that is, f(t) = Kx(t). The formula for a dashpot is f(t) = Rv(t), and Newton's famous formula for mass is f(t) = d[Mv(t)]/dt, which for a constant mass M_o is $f(t) = M_o dv/dt$.

The equation of motion for the mechanical oscillator in Fig. 3.11 is given by Newton's second law; the sum of the forces must balance to zero:

$$M_o \frac{d^2}{dt^2} x(t) + R_o \frac{d}{dt} x(t) + K_o x(t) = f(t) \Leftrightarrow (M_o s^2 + R_o s + K_o) X(s) = F(s).$$
(3.10.2)

These three constants—mass M_o , resistance R_o , and stiffness K_o ($\in \mathbb{R} \ge 0$)—are real and nonnegative. The dynamical variables are the driving force $f(t) \leftrightarrow F(s)$, the position of the mass $x(t) \leftrightarrow X(s)$, and its velocity $v(t) \leftrightarrow V(s)$, with $v(t) = dx(t)/dt \leftrightarrow V(s) = sX(s)$.

Newton's second law (ca.1650) is the mechanical equivalent of Kirchhoff's (ca.1850) voltage law (KVL), which states that the sum of the voltages around a loop must be zero. The gradient of the voltage results in a force on a charge (i.e., $F = q_0 E$). The current may be thought of as the flow of charge.

Equation 3.10.2 may be re-expressed in the frequency domain in terms of an impedance (i.e., Ohm's law), defined as the ratio of the force F(s) to velocity V(s) = sX(s), and the sum of three impedances:

$$Z(s) = \frac{F(s)}{V(s)} = \frac{Ms^2 + Rs + K}{s} = Ms + R + \frac{K}{s}.$$
 (3.10.3)

Example: The divergent series

$$e^{t}u(t) = \sum_{n=0}^{\infty} \frac{1}{n!} t^{n} \leftrightarrow \frac{1}{s-1}$$




Fig. 3.11 Three-element mechanical resonant circuit consisting of a spring, mass, and dashpot (e.g., viscous fluid)

is a valid description of $e^tu(t)$, with an unstable pole at s=1. For values of $|x-x_o|<1$ ($x\in\mathbb{R}$), the analytic function P(x) is said to have a *region of convergence* (RoC). For cases where the argument is complex ($s\in\mathbb{C}$), this is called the *radius of convergence* (RoC). We will call the region $|s-s_o|>1$ the *region of divergence* (RoD) and $|s-s_o|=0$ the *singular circle*. Typically the underlying function P(s), defined by the series, has a pole on the singular circle.

Summary: While the definitions of the $\mathcal{F}\mathcal{T}$ and $\mathcal{L}\mathcal{T}$ may appear similar, they are not. The key difference is that the time response of the Laplace transform is causal, leading to a complex analytic frequency response. The frequency response of the Fourier transform is complex but not complex analytic, since the frequency ω is real. Fourier transforms do not have poles.

The concept of symmetry is helpful in understanding the many different types of time-frequency transforms. The two most fundamental types of symmetry are causality and periodicity.

The $\mathcal{F}\mathcal{T}$ characterizes the steady-state response, while the $\mathcal{L}\mathcal{T}$ characterizes both the transient and steady-state responses. Given a causal system force response (Eq. 3.10.3), $F(s) \leftrightarrow f(t)$ with input velocity $V(s) \leftrightarrow v(t)$, the response is

$$f(t) = z(t) \star v(t) \leftrightarrow Z(\omega) = F(s) \Big|_{s=j\omega} V(\omega),$$

which says that the force is the convolution of the mechanical impedance z(t) with the input velocity v(t).

3.10.2 System Postulates

Solutions of differential equations, such as the wave equation, are conveniently described in terms of mathematical properties, which we present here in 11 system postulates (see Appendix 3.10, for greater detail):

(P1) Causality (noncausal/acausal): Causal systems respond when acted upon. All physical systems obey causality. An example of a causal system is an integrator, which has a response of a step function. Filters are also examples of causal systems. Signals represent acausal responses. They do not have a clear beginning or end, such as the sound of the wind or traffic noise. A causal

- linear system is typically complex analytic and is naturally represented in the complex *s* plane via Laplace transforms. A nonlinear system may be causal but not complex analytic.
- (P2) Linearity (nonlinear): Linear systems obey superposition. Let two signals x(t) and y(t) be the inputs to a linear system, producing outputs x'(t) and y'(t). When the inputs are presented together as ax(t) + by(t) with constant weights $a, b \in \mathbb{C}$, the output is ax'(t) + by'(t). If either a or b is zero, the corresponding signal is removed from the output. Nonlinear systems mix the two inputs, thereby producing signals that are not present in the input. For example, if the inputs to a nonlinear system are two sine waves, the output contains distortion components that have frequencies not present at the input. One example of a nonlinear system is one that multiplies the two inputs. A second is a diode, which rectifies a signal, letting current flow in only one direction. Most physical systems have some degree of
- (P3) *Passive* (active): An active system has a power source, such as a battery, while a passive system has no power source. Although you may consider a transistor amplifier to be active, it is so only when connected to a power source. Brune impedances satisfy the positive-real condition (Eq. 3.2.19).

to be nonlinear, such as the diode example.

nonlinear response, but this is not always desired. Other systems are designed

- (P4) Real (complex) time response: All physical systems are Real in = Real out. They do not naturally have complex responses (real and imaginary parts). While a Fourier transform takes real inputs and produces complex outputs, this is not an example of a complex time response. This postulate is a characterization of the input signal, not its Fourier transform.
- (P5) *Time-invariant* (time varying): For a system to be a time-varying system, the output must depend on when the input signal starts or stops. If the output, relative to the input, is independent of the starting time, then the system is said to be *time-invariant*.
- (P6) Reciprocal (non- or antireciprocal): In many ways this is the most difficult postulate to understand. It is best characterized by the ABCD matrix (see Sect. 3.8). If $\Delta_T = 1$, the system is said to be reciprocal. If $\Delta_T = -1$, it is said to be antireciprocal. The impedance matrix is reciprocal when $z_{12} = z_{21}$ and antireciprocal when $z_{12} = -z_{21}$. Dynamic loudspeakers are antireciprocal and must be modeled by a gyrator, which may be thought of as a transformer that swaps the force and flow variables (Kim and Allen 2013). For example, the input impedance of a gyrator terminated by an inductor is a capacitor. This property is best explained by Fig. 3.9. For an extended discussion on reciprocity, see Appendix G.
- (P7) Reversibility (nonreversible): If swapping the input and output of a system leaves the system invariant, it is said to be reversible. When A = D, the system is reversible. Note the distinction between reversible and reciprocal.
- (P8) *Space-invariant* (space-variant): If a system operates independently as a function of where it physically is in space, then it is space-invariant. When the parameters that characterize the system depend on position, it is space-variant.

- (P9) *Deterministic* (random): Given the wave equation along with the boundary conditions, the system's solution may be deterministic, or not, depending on its extent. Consider a radar or sonar wave propagating out into uncharted territory. When the wave hits an object, the reflection can return waves that are not predicted due to unknown objects. This is an example where the boundary condition is not known in advance.
- (P-10) Quasistatic (ka < 1): Quasistatics follows the Nyquist sampling theorem for systems that have dimensions that are small compared to the local wavelength (Nyquist 1924). This assumption fails when the frequency is raised (the wavelength becomes short). Thus this is also known as the long-wavelength approximation. Quasistatics is typically stated as ka < 1, where $k = 2\pi/\lambda = \omega/c_o$ and a is the smallest dimension of the system. See Sect. 3.10.2 for a method on how to integrate the transmission matrix and Nyquist sampling. Postulate P10 is closely related to the Feynman lecture The "underlying unity" of nature, where Feynman asks (Feynman 1970b, Ch. 12-7): "Why do we need to treat the fields as smooth?" His answer is related to the wavelength of the probing signal relative to the dimensions of the object being probed. This raises the fundamental question: Are Maxwell's equations a band-limited approximation to reality? Today we have no definite answer to this question. The following quote seems relevant 29 :

The Lorentz force formula and Maxwell's equations are two distinct physical laws, yet the two methods yield the same results.

Why the two results coincide was not known. In other words, the flux rule consists of two physically different laws in classical theories. Interestingly, this problem was also a motivation behind the development of the theory of relativity by Albert Einstein. In 1905, Einstein wrote in the opening paragraph of his first paper on relativity theory, "It is known that Maxwell's electrodynamics—as usually understood at the present time—when applied to moving bodies, leads to asymmetries which do not appear to be inherent in the phenomena." But Einstein's argument moved away from this problem and formulated special theory of relativity, thus the problem was not solved.

Richard Feynman once described this situation in his famous lecture (The Feynman Lectures on Physics, Vol. II, 1964), "we know of no other place in physics where such a simple and accurate general principle requires for its real understanding an analysis in terms of two different phenomena. Usually such a beautiful generalization is found to stem from a single deep underlying principle. ... We have to understand the "rule" as the combined effects of two quite separate phenomena."

(P11) *Periodic* ↔ *discrete*: When a function is discrete in one domain (e.g., time or frequency), it is periodic in the other (frequency or time).

Summary of the 11 system postulates: Each postulate has at least two categories. For example, (P1) is causal, noncausal, or acausal, while (P2) is linear or nonlinear. (P6) and (P9) apply to only two-port algebraic networks (those that have an input and an output). The others apply to both two- and one-port networks (e.g., an impedance

²⁹https://www.sciencedaily.com/releases/2017/09/170926085958.htm.

is a one-port). An important example of a two-port is the antireciprocal transmission matrix of a dynamic (EM) loudspeaker (see Sect. 3.10).

Related forms of these postulates may be found in the network theory literature (Van Valkenburg 1964a, b; Ramo et al. 1965). Postulates P1–P6 were introduced by Carlin and Giordano (1964), and Postulates P7–P9 were added by Kim et al. (2016). While linearity (P2), passivity (P3), realness (P4), and time-invariant (P5) are independent, causality (P1) is a consequence of linearity (P2) and passivity (P3) (Carlin and Giordano 1964, p. 5).

3.10.3 Probability

Many things in life follow rules we don't understand, and thus are unpredictable, yet they have structure due to some underlying poorly understood physics (e.g., quantum mechanics). Unlike mathematicians, engineers are taught to deal with uncertainty in terms of random processes using probability theory. For many this starts out as a large set of boring incomprehensible definitions, but once you begin to understand, it becomes interesting mathematics. It needs to be *in your skin*. If you don't have an intuition for it, either keep working on it or else find another job. Don't memorize a bunch of formulas, because that won't work over the long run.

A friend was once told "You're amazing in how you think outside the box." He responded "There is no box."

Some view probability as combinatorics and permutations. In my view probability is much more. Probability is about the signal processing of noise and signals (i.e., not combinatorics). The units of probability are [certainty] (Fry (1928)). An important goal in using probability is to find correlations in observations, such as the relative frequency of observations in sequential observations of events. Hamming (2004) presents an insightful discussion on probability.

3.10.3.1 Definitions:

1. An *event* is an unpredictable outcome (Papoulis and Pillai 2002). For example, measuring the temperature $T(x, t) \in \mathbb{R}$ with $x \in \mathbb{R}^3$ at time t [s] is an event. Measuring the temperature every hour gives 24 events per day [degrees/h]. Also, the single toss of a coin, resulting in $\{H, T\}$, is an event.

Exercise #8 What are the units of a temperature event?

Solution: Although we might think the answer is degrees, that unit is not the data that are being observed. Rather, the *relative frequency* of temperatures is the observable. For example, how many times was the event between 20° and 21° or between 22° and 27°? Events are dimensionless numbers with unit of [certainty].

2. A trial is N events.

- 3. An experiment $\{M, N\}$ is M trials of N events.
- 4. We must always keep track of the *number of events* so that we can compute the mean (i.e., average) and the uncertainty of an observable outcome.
- 5. The *mean* of many trials is the average.
- 6. A random variable X is the outcome from an experiment. A random variable rarely has stated units. For example, flipping a coin N=8 times defines the number of trials.

Exercise #9 What are the units of coin flips?

$$X \equiv \{H, H, H, T, H, T, T, T\}$$

Solution: The random variable $\{H, T\}$ has units of [certainty], best measured in terms of odds, the ratio of the number of tails to heads.

Exercise #10 How do you identify the meaning of a variable that is dimensionless (has no units)?

Solution: One must get creative. We can let H = 1 and T = -1 so that the mean can be zero.

Exercise #11 What are the mean and standard deviation of the coin toss?

Solution: To compute the mean (or standard deviation) we assign numbers to H and T. For example, we let H=1 and T=0. Then we use the usual formula to compute the numerical values.

7. The *expected value* is the mean of *N* events.

Exercise #12 What is the difference between the mean, the expected value, and the average?

Solution: These terms all mean the same thing. Having several terms that mean the same thing is one of the many things that make probability theory so arbitrary. It is sloppy to have unclear terminology.

Exercise #13 How do you assign a numerical mean to random outcomes $\{H, T\}$? **Solution:** If we let H = 1 and T = 0, then the mean is

$$\mu = (1 + 1 + 1 + 0 + 1 + 0 + 1 + 0)/8 = 5/8.$$

The odds are defined as the ratio of either P_T/P_H or P_H/P_T .

It is critically important to keep track of the number of events (N = 8 in the Exercise 13). In some sense N is more important than the actual measured sequence. It is helpful to think of N as the independent variable and X as the dependent variable; that is, think of X(N), not N(X).

Example: We define a trial by flipping a coin N = 10 times. We form an experiment by M repeated trials (M = 1000).

Exercise #14 A measure of the quantization in the estimate of the probability density due to the sample size N is defined as the magnitude of *sampling noise*.

Solution: When we compute the average (the mean μ_N) of N samples the error is bounded by 1/N; thus the variance σ_N^2 from the mean is quantized to 1/N. It follows that the root-mean-square (RMS) sample error must be bounded by $\sigma_N < \sqrt{2/N}$, independent of frequency (i.e., the \mathcal{FT} of the N-sample probability density function).

3.11 Complex Analytic Mappings (Domain-Coloring)

One of the most difficult aspects of complex functions of a complex variable is visualizing the mappings from the z = x + yJ to w(z) = u + vJ planes. For example, $w(z) = \sin(x)$ is trivial;

$$\sin(yJ) = \frac{e^{-y} - e^y}{2J} = -J\sinh(y)$$

is pure imaginary. However, the more general case

$$w(z) = \sin(z) \in \mathbb{C}$$

when z = x + yJ is real (i.e., y = 0) because $\sin(x)$ is real. Likewise, the case where x = 0 is not easily visualized. And when u(x, y) and v(x, y) are less well-known functions, w(z) can be even more difficult to visualize. For example, if $w(z) = J_0(z)$, then u(x, y) and v(x, y) are the real and imaginary parts of the Bessel function.

Visualizing complex functions: The mapping from $s = \sigma + \omega_J$ to $w(s) = u(\sigma, \omega_J) + \iota v(\sigma, \omega_J)$ is difficult to visualize because for each point in the domain $s = \sigma + \omega_J$, we would like to represent both the magnitude and phase (or real and imaginary parts) of w(s). The accepted way to visualize these mappings is to use color (hue) to represent the phase and intensity (dark to light) to represent the magnitude.

Fortunately with computer software today, this mapping problem can be solved by adding color to the chart. An Octave/MATLAB script³⁰ zviz.m has been devised to make the charts shown in Fig. 3.12. Such charts are known as *domain-coloring*.

In Fig. 3.12, rather than plotting u(x, y) and v(x, y) separately, domain-coloring allows us to display the entire function on one color chart (i.e., colorized plot). For this visualization we see the complex polar form of $w(s) = |w|e^{j \angle w}$ rather than the 2×2 (four-dimensional) Cartesian graph w(x + yj) = u(x, y) + v(x, y)j. On the left is the reference condition, the identity mapping (w = s), and on the right the origin has been shifted to the right and up by $\sqrt{2}$.

Mathematicians typically use the abstract (i.e., non-physical) notation w(z), where w = u + vi and z = x + yi. Engineers typically work in terms of a physical com-

³⁰https://jontalle.web.engr.illinois.edu/uploads/298/zviz.zip.




Fig. 3.12 Left: Domain-colorized map showing the complex mapping from the $s = \sigma + \omega_J$ plane to the $w(s) = u(\sigma, \omega) + v(\sigma, \omega)_J$ plane. This mapping may be visualized by the use of intensity (light/dark) to indicate magnitude, and color (hue) to indicate angle (phase) of the mapping. Right: The $w(s) = s - \sqrt{J}$ plane shifted to the right and up by $\sqrt{2}/2 = 0.707$. The white and black lines are the iso-real and iso-imaginary contours of $u(\sigma, \omega)$ and $v(\sigma, \omega)$.

plex impedance Z(s) = R(s) + jX(s) that has resistance R(s) and reactance X(s) [ohms] as a function of the complex Laplace radian frequency $s = \sigma + \omega j$ [rad], as used, for example, with the Laplace transform (see Sect. 3.10). In Fig. 3.12 we use a mixed notation, with Z(s) = s on the left and $w(s) = s - \sqrt{j}$ on the right, where we show this color code as a 2×2 dimensional domain-coloring graph. Intensity (dark to light) represents the magnitude of the function, while hue (color) represents the phase, where red is 0° , sea-green is 90° , blue-green is 135° , blue is 180° , and violet is -90° (or 270°).³¹

The function $w = s = |s|e^{j\theta}$ has a dark spot (zero) at s = 0 and becomes brighter away from the origin. On the right is $w(s) = s - \sqrt{j}$, which shifts the zero (dark spot) to $s = \sqrt{j}$. Thus domain-coloring gives the full 2×2 complex analytic function mapping w(x, y) = u(x, y) + v(x, y)j in colorized polar coordinates.

Example: Figure 3.13 shows a colorized plot of $w(z) = \sin(\pi(s - j)/2)$ resulting from the MATLAB/Octave command zviz $\sin(\text{pi*}(s-j)/2)$. The abscissa (horizontal axis) is the real σ -axis and the ordinate (vertical axis) is the complex $j\omega$ -axis. The graph is offset along the ordinate axis by 1j, since the argument s-j causes a shift of the sine function by 1 in the positive imaginary direction.

The visible zeros of w(s) appear as dark regions at (-2, 1), (0, 1), (2, 1). As a function of σ , $w(\sigma + 1j)$ oscillates between red (phase is zero degrees), meaning the function is positive and real, and sea-green (phase is 180°), meaning the function is negative and real.

To use the program, we use the syntax, for example, zviz s.^2). Note the period between s and ^2. This will render a domain-coloring (colorized) version of the function. Examples you can render with zviz are given in the comments at the

³¹Hue depends on both the display medium and the eye.




Fig. 3.13 Plot of $\sin(0.5\pi(z - j))$

top of the zviz.m program. A good example for testing is zviz z-sqrt(j), which has a dark spot (zero) at $(1+1j)/\sqrt{2} = 0.707(1+1j)$.

Along the vertical axis, the displayed function is either $\cosh(y)$ or $\sinh(y)$, depending on the value of x. The intensity becomes lighter as |w| increases.

What is being plotted? The axes are either $s = \sigma$ and ω , or z = x and y. Superimposed on the s-axis is the function $w(s) = u(\sigma, \omega) + v(\sigma, \omega) j$, represented in polar coordinates by the intensity and color of w(s). The density (dark vs. light) displays the magnitude |w(s)|, while the color (hue) displays the angle $(\angle w(s))$ as a function of s. Thus the intensity becomes darker as |w| decreases and lighter as |w(s)| increases. The angle $\angle (w)$ to color map is defined by Fig. 3.12. For example, 0° is red, 90° is green, -90° is purple, and 180° is blue-green.

Example: Additional examples are given in Fig. 3.14 using the notation $w(s) = u(\sigma, \omega) + v(\sigma, \omega) j$. We see the two complex mappings $w = e^s$ (left) and its inverse $s = \ln(w)$. The exponential is relatively to understand because $w(s) = |e^{\sigma}e^{\omega j}| = e^{\sigma}$.

The red region is where $\omega \approx 0$, in which case $w \approx e^{\sigma}$. As σ becomes large and negative, $w \to 0$; thus the entire field becomes dark on the left. The field is becoming light on the right where $w = e^{\sigma} \to \infty$. If we let $\sigma = 0$ and look along the ω -axis, we see that the function is changing phase: sea-green (90°) at the top and violet (-90°) at the bottom.

In the right panel note the zero for $s(z) = \ln|z| + \omega_J$ at z = 1. The root of the $\log(z)$ function is $\log(z_r) = 0$, $w_r = 1$, $\angle z = \phi = 0$, since $\log(1) = 0$. More generally, the $\log(z)$ of $z = |z|e^{\phi_J}$ is $s(z) = \ln|z| + \phi_J$. Thus s(w) can be zero only when the angle of w is zero.

The $\ln(z)$ function has a branch cut along the $\phi(z) = \angle z = 180^{\circ}$ axis. As one crosses over the cut, the phase goes above 180° and the plane changes to the next sheet of the log function. The only sheet with a zero is the principal value, as shown. For all others, the log function is either increasing or decreasing monotonically, and there is no zero.




Fig. 3.14 This domain-color map allows us to visualize complex mappings by the use of intensity (light/dark) to indicate magnitude and color (hue) to indicate angle (phase). The white and black lines are the iso-real and iso-imaginary contours of the complex mapping. Left: The domain-color map for the complex mapping from the $s = \sigma + \omega J$ plane to the $w(s) = u + vJ = e^{\sigma + \omega J} = e^{\sigma}e^{\omega J}$ plane, which goes to zero as $\sigma \to -\infty$, causing the domain-color map to become dark for $\sigma < -2$. The white and black lines are always perpendicular because e^s is complex analytic everywhere. Right: The *principal value* of the inverse function $s(z) = u(x, y) + v(x, y)J = \log(z)$, which has a zero (dark) at x = 1, since there $\log(1) = 0$ and the imaginary part is zero. Note the branch cut, where the color is discontinuous, from $x = [0, -\infty_J)$. On branches other than the one shown, there are no zeros, since the phase $(\angle s = 2\pi n \in \mathbb{Z})$ is not zero. n = 1 is called the *branch index*. See Sect. 4.4.3 for a discussion of branch cuts and multivalued functions

3.11.1 The Riemann Sphere

Once algebra was formulated, in about 830 CE, mathematicians were able to expand beyond the limits set by geometry on the real plane and the verbose descriptions of each problem in prose (Stillwell 2010, p. 93). The geometry of Euclid's *Elements* had paved the way, but after 2000 years, the addition of the language of algebra changed everything. The analytic function was a key development, heavily used by both Newton and Euler. Also Cauchy made important headway with his investigation of complex variables. Of special note were integration and differentiation in the complex plane of complex analytic functions, which is the topic of Chap. 4. It was Riemann, working with Gauss in the final years of Gauss's life, who made the breakthrough with the concept of the extended complex plane.³² This concept was based on the composition of a line with the sphere, similar in concept to the derivation of Euclid's formula for Pythagorean triplets (see Sect. 3.7.8). While the importance

³²"Gauss did lecture to Riemann but he was only giving elementary courses and there is no evidence that at this time he recognized Riemann's genius."Then "In 1849 he [Riemann] returned to Göttingen and his Ph.D. thesis, supervised by Gauss, was submitted in 1851." See https://www-groups.dcs.st-and.ac.uk/~history/Biographies/Riemann.html.




Fig. 3.15 The left panel shows how the real line may be composed with the circle. Each real x value maps to a corresponding point $x\prime$ on the unit circle. The point $x\to\infty$ maps to the north pole N. This simple idea may be extended with the composition of the complex plane with the unit sphere, thus mapping the plane onto the sphere. As with the circle, the point on the complex plane $z\to\infty$ maps onto the north pole N. This construction is important because, while the plane is open (does not include $z\to\infty$), the sphere is analytic at the north pole. Thus the sphere defines the *closed extended plane*. Figure adapted from Stillwell (2010, pp. 299–300)

of the extended complex plane was unforeseen, it changed analytic mathematics forever, along with the physics it supported. It unified and thus simplified many important integrals to the extreme. The basic idea is captured by the fundamental theorem of complex integral calculus (see Table 4.1).

The idea is outlined in Fig. 3.15. On the left is a circle and a line. The difference between this case and the derivation of the Pythagorean triplets is that the line starts at the north pole and ends on the real $x \in \mathbb{R}$ axis at point x. At point x', the line cuts through the circle. Thus the mapping from x to x' takes every point on \mathbb{R} to a point on the circle. For example, the point x=0 maps to the south pole (not indicated). To express x' in terms of x one must compose the line and the circle, similar to the composition used in the derivation of Euclid's formula (see Sect. 3.7.8). The points on the circle, indicated here by x', require a traditional polar coordinate system, with a unit radius and an angle defined between the radius and a vertical line passing through the north pole. When $|x| \to \infty$, the point $x' \to N$, known as the *point at infinity*. But this idea goes much further, as shown on the right of Fig. 3.15.

Here the real tangent line is replaced by a tangent complex plane $z \in \mathbb{C}$ and the complex puncture point $z' \in \mathbb{C}$ —in this case on the complex sphere, called the *extended complex plane*. This is a natural extension of the chord/tangent method on the left, but with significant consequences. The main difference between the complex plane z and the extended complex plane, other than the coordinate system, is what happens at the north pole. The point at $|z| = \infty$ is not defined on the plane, whereas on the sphere, the point at the north pole is simply another point, like every other point on the sphere.

Open versus closed sets: Mathematically the plane is said to be an *open set*, since the limit $z \to \infty$ is not defined, whereas on the sphere, the point z' is a member of a *closed set*, since the north pole *is* defined. The distinction between an open and closed sets is important because the closed set allows the function to be complex

analytic at the north pole, which it cannot be on the plane (since the point at infinity is not defined).

The z plane may be replaced with another tangent plane—say, the $w = F(z) \in \mathbb{C}$ plane, where w is some function F of $z \in \mathbb{C}$. For the moment we shall limit ourselves to complex analytic functions of z—namely, $w = F(z) = u(x, y) + v(x, y)_J = \sum_{n=0}^{\infty} c_n z^n$.

In summary, given a point z = x + yj on the open complex plane, we map it to $w = F(z) \in \mathbb{C}$, the complex w = u + vj plane, and from there to the closed extended complex plane w'(z). The point of doing this is that it allows the function w'(z) to be analytic at the north pole, meaning it can have a convergent Taylor series at the point at infinity $z \to \infty$.

Since we have not yet defined dw(z)/dz, the concept of a complex Taylor series remains undefined.

3.11.2 Bilinear Transformation

In mathematics the bilinear transformation has special importance because it is linear in its action on both the input and output variables. Since we are engineers, we shall stick with the engineering terminology. But if you wish to read about this on the Internet, be sure to also search for the mathematical term *Möbius transformation*.

When a point on the complex plane z = x + yj is composed with the bilinear transformation $(a, b, c, d \in \mathbb{C})$, the result is w(z) = u(x, y) + v(x, y)j (this is related to the Möbius transformation, Sect. 2.2):

$$w = \frac{az+b}{cz+d}. (3.11.1)$$

The transformation $z \to w$ is a cascade of four independent compositions:

- 1. Translation $(w = z + b; a = 1, b \in \mathbb{C}, c = 0, d = 1)$
- 2. Scaling $(w = |a|z: a \in \mathbb{R}, b = 0, c = 0, d = 1)$
- 3. Rotation $(w = \frac{a}{|a|}z : a \in \mathbb{C}, b = 0, c = 0, d = |a|)$
- 4. Inversion $(w = \frac{1}{z}: a = 0, b = 1, c = 1, d = 0)$

Each of these transformations is a special case of Eq. 3.11.1, with inversion being the most complicated. I highly recommend a video showing the effect of the bilinear (Möbius) transformation on the plane (Arnold and Rogness 2019).³³

The bilinear transformation is the most general way to move the expansion point in a complex analytic expansion. For example, when we start from the harmonic series, the bilinear transformation gives

³³ https://www.youtube.com/watch?v=0z1fIsUNhO4.

$$\frac{1}{1-w} = \frac{1}{1 - \frac{az+b}{cz+d}}$$

$$= \frac{cz+d}{(c-a)z + (d-b)}$$

$$= \frac{1}{1 - \frac{a}{c}} \cdot \frac{z + \frac{d}{c}}{z - \frac{a-b}{c-a}}.$$

The RoC is transformed from |w| < 1 to |(az - b)/(cz - d)| < 1. An interesting application might be to move the expansion point until it is on top of the nearest pole, so that the RoC goes to zero. This might be a useful way of finding a pole, for example.

When the extended plane (Riemann sphere) is analytic at $z=\infty$, we can take the derivatives there, defining the Taylor series with the expansion point at ∞ . When the bilinear transformation rotates the Riemann sphere, the point at infinity is translated to a finite point on the complex plane, revealing the analytic nature at infinity. A second way to transform the point at infinity is by the bilinear transformation $\zeta=1/z$, mapping a zero (or pole) at $z=\infty$ to a pole (or zero) at $\zeta=0$. Thus this construction of the Riemann sphere and the Möbius (bilinear) transformation allows us to understand the point at infinity and treat it like any other point. If you felt that you never understood the meaning of the point at ∞ (likely), this should help.

3.12 Problems AE-3

3.12.1 Topics of This Homework

Visualizing complex functions, bilinear/Möbius transformation, Riemann sphere. Deliverables: Answers to problems

3.12.2 Two-Port Network Analysis

Problem #1 Perform an analysis of electrical two-port networks, shown in Fig. 3.8. This can be a mechanical system if the capacitors are taken to be springs and inductors taken as mass, as in the suspension of the wheels of a car. In an acoustical circuit, the low-pass filter could be a car muffler. While the physical representations will be different, the equations and the analysis are exactly the same.

The definition of the ABCD transmission matrix (T) is

$$\begin{bmatrix} V_1 \\ I_1 \end{bmatrix} = \begin{bmatrix} \mathcal{A} \ \mathcal{B} \\ \mathcal{C} \ \mathcal{D} \end{bmatrix} \begin{bmatrix} V_2 \\ -I_2 \end{bmatrix}. \tag{AE-3.1}$$

The *impedance matrix*, where the determinant $\Delta_T = AD - BC$, is given by

$$\begin{bmatrix} V_1 \\ V_2 \end{bmatrix} = \frac{1}{\mathcal{C}} \begin{bmatrix} \mathcal{A} \ \Delta_{\mathcal{T}} \\ 1 \ \mathcal{D} \end{bmatrix} \begin{bmatrix} I_1 \\ I_2 \end{bmatrix}. \tag{AE-3.2}$$

-1.1: Derive the formula for the impedance matrix (Eq. AE-3.2) given the transmission matrix definition (Eq. AE-3.1). Show your work.

Problem #2 Consider a single circuit element with impedance Z(s).

- -2.1: What is the ABCD matrix for this element if it is in series?
- -2.2: What is the ABCD matrix for this element if it is in shunt?

Problem #3 Find the ABCD matrix for each of the circuits of Fig. 3.8.

For each circuit, (i) show the cascade of transmission matrices in terms of the complex frequency $s \in \mathbb{C}$, then (ii) substitute s = 1j and calculate the total transmission matrix at this single frequency.

- -3.1: Left circuit (let $R_1 = R_2 = 10$ kilo-ohms and C = 10 nano-farads)
- -3.2: Right circuit (use L and C values given in the figure), where the pressure P is analogous to the voltage V, and the velocity U is analogous to the current I.
- -3.3: Convert both transmission (ABCD) matrices to impedance matrices using Eq. AE-3.2. Do this for the specific frequency $s = 1_J$ as in the previous part (feel free to use MATLAB/Octave for your computation).
 - -3.4: Right circuit: Repeat the analysis as in Question 3.3.

3.12.3 Algebra

Problem #4 Fundamental theorem of algebra (FTA).

-4.1: State the fundamental theorem of algebra (FTA).

3.12.4 Algebra with Complex Variables

Problem #5 Order and complex numbers: One can always say that 3 < 4—namely, that real numbers have order. One way to view this is to take the difference and compare it to zero, as in 4-3>0. Here we will explore how complex variables may be ordered. Define the complex variable $z = x + y \in \mathbb{C}$.

- -5.1: Explain the meaning of $|z_1| > |z_2|$.
- -5.2: If $x_1, x_2 \in \mathbb{R}$ (are *real* numbers), define the meaning of $x_1 > x_2$. *Hint: Take the difference.*
 - -5.3: Explain the meaning of $z_1 > z_2$.
 - −5.4: If time were complex, how might the world be different?

3.12 Problems AE-3 175

Problem #6 It is sometimes necessary to consider a function $w(z) = u + v_J$ in terms of the real functions u(x, y) and v(x, y) (e.g., separate the real and imaginary parts). Similarly, we can consider the inverse $z(w) = x + y_J$, where x(u, v) and y(u, v) are real functions.

-6.1: Find u(x, y) and v(x, y) for w(z) = 1/z.

Problem #7 Find u(x, y) and v(x, y) for $w(z) = c^z$ with complex constant $c \in \mathbb{C}$ for Questions #7, #7, and #7:

- -7.1: c = e
- -7.2: c = 1 (recall that $1 = e^{j/2\pi k}$ for k = 0, 1, 2, ...)

Ed: rm k

- $-7.3: c = j. Hint: j = e^{j\pi/2 + j2\pi m}, m \in \mathbb{Z}.$
- -7.4: Find u(x, y) for $w(z) = \sqrt{z}$. Hint: Begin with the inverse function $z = w^2$.

Problem #8 Convolution of an impedance z(t) and its inverse y(t): In the frequency domain a Brune impedance is defined as the ratio of a numerator polynomial N(s) to a denominator polynomial D(s).

- -8.1: Consider a Brune impedance defined by the ratio of numerator and denominator polynomials, Z(s) = N(s)/D(s). Since the admittance Y(s) is defined as the reciprocal of the impedance, the product must be 1. If $z(t) \leftrightarrow Z(s)$ and $y(t) \leftrightarrow Y(s)$, it follows that $z(t) \star y(t) = \delta(t)$. What property must $n(t) \leftrightarrow N(s)$ and $d(t) \leftrightarrow D(s)$ obey for this to be true?
- -8.2: The definition of a minimum phase function is that it must have a causal inverse. Show that every impedance is minimum phase.

3.12.5 Schwarz Inequality

Problem #9 Figure 3.16 shows three vectors for an arbitrary value of $\alpha \in \mathbb{R}$ and a specific value of $\alpha = \alpha^*$.

- –9.1: Find the value of $\alpha \in \mathbb{R}$ such that the length (norm) of \mathbf{E} (i.e., $||\mathbf{E}|| \ge 0$) is minimum. Show your derivation, not the answer ($\alpha = \alpha^*$).
- -9.2: Find the formula for $||E(\alpha^*)||^2 \ge 0$. *Hint: Substitute* α^* *into Eq.* 3.5.9) and show that this results in the Schwarz inequality (Fig. 3.16)

$$|\mathbf{U} \cdot \mathbf{V}| < ||\mathbf{U}||||\mathbf{V}||.$$

Problem #10 Geometry and scaler products

- -10.1: What is the geometrical meaning of the dot product of two vectors?
- -10.2: Give the formula for the dot product of two vectors. Explain the meaning based on Fig. 3.4.
- -10.3: Write the formula for the dot product of two vectors $\mathbf{U} \cdot \mathbf{V}$ in \mathbb{R}^n in polar form (e.g., assume the angle between the vectors is θ).
 - −10.4: How is the Schwarz inequality related to the Pythagorean theorem?
 - -10.5: Starting from ||U + V||, derive the triangle inequality




Fig. 3.16 This figure shows how to derive the Schwarz inequality, by finding the value of $\alpha = \alpha^*$ corresponding to min[$E(\alpha)$]. It is identical to Fig. 3.5

$$||U + V|| \le ||U|| + ||V||.$$

- -10.6: The *triangle inequality* $||\mathbf{U} + \mathbf{V}|| \le ||\mathbf{U}|| + ||\mathbf{V}||$ is true for two and three dimensions: Does it hold for five-dimensional vectors?
 - -10.7: Show that the wedge-product $\mathbf{U} \wedge \mathbf{V} \perp \mathbf{U} \cdot \mathbf{V}$.

3.12.6 Probability

Problem #11 Basic terminology of experiments

- -11.1: What is the *mean* of a trial, and what is the average over all trials?
- -11.2: What is the *expected value* of a random variable X?
- −11.3: What is the *standard deviation* about the mean?
- −11.4: What is the definition of *information* of a random variable?
- -11.5: How do you combine events? Hint: If the event is the flip of a biased coin, the events are H=p, T=1-p, so the event is $\{p,1-p\}$. To solve the problem, you must find the probabilities of two independent events.
- -11.6: What does the term *independent* mean in the context of question #11? Give an example.
 - -11.7: Define odds.

Chapter 4 Stream 3A: Scalar Calculus



Stream 3 is ∞ , a concept that typically means unbounded (immeasurably large), but in the case of calculus, ∞ means infinitesimal (immeasurably small), since taking a limit requires small numbers. Taking a limit means you may never reach the target, a concept that the Greeks called *Zeno's paradox* (Stillwell 2010, p. 76).

When we speak of the class of *ordinary* (versus *vector*) differential equations, the term *scalar* is preferable, since the term ordinary is vague, if not meaningless. For scalar calculus, a special subset of fundamental theorems about integration is summarized in Table 4.1, starting with Leibniz's theorem.

Following our discussion of the integral theorems on scalar calculus, those on vector calculus, without which there can be no understanding of Maxwell's equations. Of these, the fundamental theorem of vector calculus (also known as Helmholtz decomposition), Gauss's law, and Stokes's theorem form the three cornerstones of modern vector field analysis. These theorems allow us to connect the differential (point) and macroscopic (integral) relationships. For example, we can write Maxwell's equations either as vector differential equations, as shown by Heaviside (along with Gibbs and Hertz), or in integral form. It is helpful to place these two forms side by side to fully

Table 4.1 The fundamental theorems of integral calculus, each of which deals with integration. At least two main theorems relate to scalar calculus, and three more to vector calculus

Name	Mapping	Section	Description
Leibniz (FTC)	$\mathbb{R}^1 o \mathbb{R}^0$	4.2	Area under a real curve
Cauchy (FTCC)	$\mathbb{C}^1 \to \mathbb{R}^0$	4.2	Area under a complex curve
Cauchy's theorem	$\mathbb{C}^1 \to \mathbb{C}^0$	4.5	Close integral over analytic region is zero
Cauchy's integral formula	$\mathbb{C}^1 \to \mathbb{C}^0$	4.5	Fundamental theorem of complex integral calculus
Residue theorem	$\mathbb{C}^1 \to \mathbb{C}^0$	4.5	Residue integration
Helmholtz's theorem			

appreciate their significance. To understand the differential (microscopic) view, one must fully understand the integral (macroscopic) view (see Figs. 5.5 and 5.6).

4.1 The Beginning of Modern Mathematics

As shown in Fig. 1.2, mathematics as we know it today began in the sixteenth to eighteenth centuries, arguably starting with Galileo, Descartes, Fermat, Newton, the Bernoulli family, and most important Euler. Galileo was formidable because of his fame, fortune, and "successful" stance against the powerful Catholic establishment. His creativity in scientific circles was certainly well known due to his many skills and accomplishments. Descartes and Fermat were at the forefront of merging algebra and geometry. While Fermat kept meticulous notebooks, he did not publish and tended to be secretive. Thus Descartes's contributions were more widely acknowledged, though not necessarily deeper.

Regarding the development of calculus, much was yet to be developed by Newton and Leibniz using term by term integration of functions based on Taylor series representation. This was a powerful technique but, as stated earlier, incomplete because the Taylor series can represent only single-valued functions within the RoC. More important, Newton (and others) failed to recognize (i.e., rejected) the powerful generalization to complex analytic functions. The first major breakthrough was Newton's publication of *Principia* (1687), and the second was by Riemann (1851), advised by Gauss but possibly more influenced by Cauchy.

Following both Galileo's and Newton's lead, the secretive and introverted behavior of the typical mathematician dramatically changed with the Bernoulli family (Fig. 3.1). The oldest brother Jacob taught his much younger brother Johann, who then taught his son Daniel. But Johann's star pupil was Leonhard Euler. Euler first mastered all the tools and then published with a prolifically previously unknown.

Euler and the circular functions: Euler's first major task was to understand the family of analytic circular functions (e^x , $\sin(x)$, $\cos(x)$, and $\log(x)$), a task begun by the Bernoulli family. Euler sought relationships among these many functions, some of which may not be thought of as being related, such as the log and sin functions. The connection that may "easily" be made is through their complex Taylor series representation (Eq. 3.2.9). By the manipulation of the analytic series representations, the relationship between e^x and $\sin(x)$ and $\cos(x)$ was precisely captured with the equation

$$e^{j\omega} = \cos(\omega) + j\sin(\omega) \tag{4.1.1}$$

and its analytic inverse (Greenberg 1988, p. 1135)

$$\tan^{-1}(z) = \frac{1}{2J} \ln \left(\frac{1J - z}{1J + z} \right) = \frac{J}{2} \ln \left(\frac{1 - zJ}{1 + zJ} \right). \tag{4.1.2}$$

Exercise #1 Starting from Eq. 4.1.1, derive Eq. 4.1.2.

Solution: We let $z(\omega) = \tan \omega$; then

$$z(\omega) = \tan(\omega) = \frac{\sin \omega}{\cos \omega} = -J \frac{e^{\omega J} - e^{-\omega J}}{e^{\omega J} + e^{-\omega J}} = -J \frac{e^{2\omega J} - 1}{e^{2\omega J} + 1}.$$
 (4.1.3)

Solving for $e^{-2\omega J}$, we get

$$e^{-2\omega J} = \frac{1 - zJ}{1 + zJ}. (4.1.4)$$

Taking ln() of both sides and using the definition of $z(\omega)$ gives Eq. 4.1.2:

$$\omega = \tan^{-1}(z) = \frac{J}{2} \ln \frac{1 - zJ}{1 + zJ},$$

as shown in Fig. 4.1.

These equations are the basis of transmission lines (TL). Here $z(\omega)$ of Eq. 4.1.3 is the TL's input impedance and Eq. 4.1.4 is the reflectance.

Although many high school students memorize Euler's relationship, it seems unlikely that they appreciate the utility of the complex analytic function.

History of complex analytic functions: Newton (ca.1650) famously ignored imaginary numbers and called them imaginary in a disparaging (pejorative) way. Given Newton's prominence, his view must have keenly attenuated interest in complex algebra, even though it had been described by Bombelli in 1526, likely based on his serendipitous finding of Diophantus's book *Arithmetic* in the Vatican library.




Fig. 4.1 Colorized plots of $z(s) = tan^{-1}(s)$ and $s(z) = \frac{1}{2} \ln(1 - z_J)/(1 + z_J)$, verifying that they are the same complex analytic function

Euler did not appreciate the role of complex analytic functions. They were first fully appreciated well after his death in 1785 by Augustin-Louis Cauchy (1789–1857), and then extended by Riemann in 1851.

Euler derived his relationships using real-power series (i.e., real-analytic functions). While Euler was fluent with $j = \sqrt{-1}$, he did not consider functions to be complex analytic. That concept was first explored by Cauchy almost a century later. The missing link to the concept of complex analytic functions is the definition of the derivative with respect to the complex argument

$$F'(s) = \frac{dF(s)}{ds},\tag{4.1.5}$$

where $s = \sigma + \omega_J$, without which the complex analytic Taylor coefficients are not defined.

4.2 Fundamental Theorem of Scalar Calculus

History of scalar calculus: It some sense the story of calculus begins with the fundamental theorem of calculus (Table 4.1), also known generically as *Leibniz's formula*. The simplest integral is the length of a line $L = \int_0^L dx$. If we label a point on a line as x = 0 and wish to measure the distance to any other point x, we form the line integral between the two points. If the line is straight, this integral is the Euclidean length given by the difference between the two ends (Eq. 3.5.3).

If $F(\chi) \in \mathbb{R}$ describes a height above the line $\chi \in \mathbb{R}$, then

$$f(x) - f(0) = \int_{x=0}^{x} F(\chi) d\chi$$
 (4.2.1)

may be viewed as the *antiderivative* of $F(\chi)$. Here χ is a dummy variable of integration. Thus the area under $F(\chi)$ depends on only the difference in the area evaluated at the end points.

This property of the area as an integral over an interval, depending on only the end points, has important consequences in physics in terms of conservation of energy, allowing for important generalizations. For example, as long as $\chi \in \mathbb{R}$, we can let $F(\chi) \in \mathbb{C}$ with no loss of generality, due to the linear Postulate P1 of the integral (see Sect. 3.10.2).

4.2.1 Fundamental Theorem of Real Calculus

If f(x) is analytic (Eq. 3.2.8), then

$$F(x) = \frac{d}{dx}f(x) \tag{4.2.2}$$

is an exact real differential. It follows that F(x) is analytic. This is known as the fundamental theorem of (real) calculus (FTC). Thus Eq. 4.2.2 may be viewed as an exact real differential. This is easily shown by evaluating

$$\frac{d}{dx}f(x) = \lim_{\delta \to 0} \frac{f(x+\delta) - f(x)}{\delta} = F(x)$$

starting from the antiderivative, Eq. 4.2.1. If f(x) is not analytic then the limit may not exist, so this is a necessary condition.

There are many important variations on this very basic theorem (see Table 4.1). For example, the limits could depend on time. Also when we take Fourier transforms, the integrand depends on both time $t \in \mathbb{R}$ and frequency $\omega \in \mathbb{R}$ via a complex exponential "kernel" function $e^{\pm j\omega t} \in \mathbb{C}$, which is analytic in both t and ω .

4.2.2 The Fundamental Theorem of Complex Calculus

The fundamental theorem of complex calculus (FTCC) states (Greenberg 1988, p. 1197) that for any complex analytic function $F(s) \in \mathbb{C}$ with $s = \sigma + \omega j \in \mathbb{C}$,

$$f(s) - f(s_o) = \int_{s_o}^{s} F(\zeta)d\zeta. \tag{4.2.3}$$

Equations 4.2.1 and 4.2.3 differ because the path of the integral is complex. Thus the line integral is over $s \in \mathbb{C}$ rather than a real integral over $\chi \in \mathbb{R}$. The FTCC states that the integral depends on only the end points, since

$$F(s) = \frac{d}{ds}f(s). \tag{4.2.4}$$

Comparing exact differentials, Eq. 4.1.5 (FTCC) and Eq. 4.2.2 (FTC), we see that $f(s) \in \mathbb{C}$ must be complex analytic and have a Taylor series in powers in $s \in \mathbb{C}$. It follows that F(s) is also complex analytic.

Complex analytic functions: The definition of a *complex analytic function* F(s) of $s \in \mathbb{C}$ is that the function may be expanded in a Taylor series (Eq. 3.2.20) about an expansion point $s_o \in \mathbb{C}$. This definition follows the same logic as the FTC. Thus we need a definition for the coefficients $c_n \in \mathbb{C}$, which most naturally follow from Taylor's formula

$$c_n = \frac{1}{n!} \frac{d^n}{ds^n} F(s) \bigg|_{s=s_o}$$
 (4.2.5)

The requirement that F(s) has a Taylor series naturally follows by taking derivatives with respect to s at s_o . The problem is that both integration and differentiation of functions of complex Laplace frequency $s = \sigma + \omega j$ have not yet been defined.

Thus the question: What does it mean to take the derivative of a function $F(s) \in \mathbb{C}$, $s = \sigma + \omega_J \in \mathbb{C}$, with respect to s, where s defines a plane rather than a real line? We learned how to form the derivative on the real line. Can the same derivative concept be extended to the complex plane?

The answer is affirmative. The question may be resolved by applying the rules of the real derivative when defining the derivative in the complex plane. However, for the complex case, there is an issue regarding direction. Given any analytic function F(s), is the partial derivative with respect to σ different from the partial derivative with respect to ωJ ? For complex analytic functions, the FTCC states that the integral is independent of the path in the s plane. Based on the chain rule, the derivative must also be independent of the direction at s_o . This directly follows from the FTCC. If the integral of a function of a complex variable is to be independent of the path, then the derivative of a function with respect to a complex variable must be independent of the direction. This follows from Taylor's formula for the coefficients of the complex analytic formula (Eq. 4.2.5).

The Cauchy–Riemann conditions: The FTC defines the area as an integral over a real differential $(dx \in \mathbb{R})$, while the FTCC relates an integral over a complex function $F(s) \in \mathbb{C}$ along a complex interval (i.e., path) $(ds \in \mathbb{C})$. For the FTC the area under the curve depends on only the end points of the antiderivative f(x). But what is the meaning of an "area" along a complex path? The Cauchy–Riemann conditions provide the answer.

4.2.3 Cauchy-Riemann Conditions

For the integral of $Z(s) = R(\sigma, \omega) + jX(\sigma, \omega)$ to be independent of the path, the derivative of Z(s) must also be independent of the path. This requirement leads to a pair of equations known as the *Cauchy–Riemann conditions*.

To define

$$\frac{d}{ds}Z(s) = \frac{d}{ds}\left[R(\sigma,\omega) + jX(\sigma,\omega)\right],$$

we take partial derivatives of Z(s) with respect to σ and $j\omega$, and equate them:

$$\frac{\partial Z}{\partial \sigma} = \frac{\partial R}{\partial \sigma} + J \frac{\partial X}{\partial \sigma} \qquad \equiv \qquad \frac{\partial Z}{\partial J \omega} = \frac{\partial R}{\partial J \omega} + J \frac{\partial X}{\partial J \omega}.$$

This says that a horizontal derivative, with respect to σ , is equivalent to a vertical derivative, with respect to ω_J . Taking the real and imaginary parts gives the two equations

$$\frac{\partial R(\sigma,\omega)}{\partial \sigma} = f \frac{\partial X(\sigma,\omega)}{\partial \omega f} \quad \text{(CR-1)} \quad \text{and} \quad \frac{\partial R(\sigma,\omega)}{\partial \omega f} = -f \frac{\partial X(\sigma,\omega)}{\partial \sigma} \quad \text{(CR-2)},$$
(4.2.6)

known as the Cauchy–Riemann (CR) conditions. The j cancels in CR-1 but introduces a $j^2 = -1$ in CR-2. They may also be written in polar coordinates ($s = re^{\theta j}$) as

$$\frac{\partial R}{\partial r} = \frac{1}{r} \frac{\partial X}{\partial \theta}$$
 and $\frac{\partial X}{\partial r} = -\frac{1}{r} \frac{\partial R}{\partial \theta}$.

The FTCC (Eq. 4.2.3) follows from CR-1 and CR-2 (Eq. 4.2.6).

You may wonder what would happen if we took a derivative at 45° . To do this we only need to multiply the function by $e^{J\pi/4}$. But doing so will not change the derivative. Thus we may take the derivative in any direction by multiplying by $e^{\theta J}$, and the CR conditions will not change.

The CR conditions are necessary so that the integral of Z(s), and thus its derivative, is independent of the path, expressed in terms of conditions on the real and imaginary parts of Z. This is a very strong condition on Z(s), which follows assuming that Z(s) may be written as a Taylor series in s:

$$Z(s) = Z_0 + Z_1 s + \frac{1}{2} Z_2 s^2 + \cdots,$$
 (4.2.7)

where $Z_n \in \mathbb{C}$ are complex constants given by the Taylor series formula (Eq. 4.2.5). As with the real Taylor series, there is the convergence condition that |s| < 1, called the *radius of convergence* (RoC). This is an important generalization of the region of convergence (RoC) for real s = x.

Every function that may be expressed as a Taylor series in $s-s_o$ about point $s_o \in \mathbb{C}$ is said to be *complex analytic* at s_o . This series, which is single-valued, is said to converge within a radius of convergence (RoC). This highly restrictive condition has significant physical consequences. For example, every impedance function Z(s) obeys the CR conditions over large regions of the s plane, including the entire *right half s plane* (RHP) ($\sigma > 0$). This condition is summarized by the Brune condition $\Re\{Z(\sigma > 0)\} \ge 0$, or alternatively $\angle Z(s) < \angle s$

When the CR conditions are generalized to volume integrals, this is called either Gauss's Law or Green's theorem, which is used in the solution of boundary value problems in engineering and physics (Kusse and Westwig 2010).

We may merge these equations into a pair of second-order equations by taking a second round of partials. Specifically, eliminating the real part $R(\sigma, \omega)$ of Eq. 4.2.6 gives

$$\frac{\partial^2 R(\sigma,\omega)}{\partial \sigma \partial \omega} = \frac{\partial^2 X(\sigma,\omega)}{\partial^2 \omega} = -\frac{\partial^2 X(\sigma,\omega)}{\partial^2 \sigma}, \quad (CR-3)$$

which may be written compactly as $\nabla^2 X(\sigma, \omega) = 0$. Eliminating the imaginary part gives

$$\frac{\partial^2 X(\sigma,\omega)}{\partial \omega \partial \sigma} = \frac{\partial^2 R(\sigma,\omega)}{\partial^2 \sigma} = -\frac{\partial^2 R(\sigma,\omega)}{\partial^2 \omega}, \quad (CR-4)$$

which may be written as $\nabla^2 R(\sigma, \omega) = 0$.

In summary, for a function Z(s) to be complex analytic, the derivative dZ/ds must be independent of direction (path), which requires that the real and imaginary parts of the function obey Laplace's equation; that is,

$$\nabla^2 R(\sigma, \omega) = 0$$
 and $\nabla^2 X(\sigma, \omega) = 0$. (4.2.10)

Equations CR-1 and CR-2 are easy to work with because they are first order, but the intuition behind them best follows from the properties of Laplace's equation (Eq. 4.2.10). Note two facts: (1) the derivative of a complex analytic function is independent of its direction, and (2) the real and imaginary parts of the function obey Laplace's equation. Such relationships are known as *harmonic functions*.

As we shall see in the next few sections, complex analytic functions must be smooth, since every analytic function may be differentiated an infinite number of times within the RoC. The magnitude must attain its maximum and minimum on the boundary. For example, when you stretch a rubber sheet over a jagged frame, the height of the rubber sheet obeys Laplace's equation. Nowhere can the height of the sheet rise above or below its value at the boundary.

Harmonic functions define *conservative fields*, which means that energy (like a volume or area) is conserved. The work done in moving a mass from a to b in such a field is conserved. If you return the mass from b back to a, the stored energy is retrieved, thus zero network is consumed.

4.3 Problems DE-1

4.3.1 Topics of This Homework

Complex numbers and functions (ordering and algebra), complex power series, fundamental theorem of calculus (real and complex); Cauchy–Riemann conditions, multivalued functions (branch cuts and Riemann sheets)

4.3.2 Complex Power Series

Problem #1 In each case derive (e.g., using Taylor's formula) the power series of w(s) about s=0 and give the RoC of your series. If the power series doesn't exist, state why! Hint: In some cases, you can derive the series by relating the function to another function for which you already know the power series at s=0.

$$-1.1$$
: $1/(1-s)$
 -1.2 : $1/(1-s^2)$
 -1.3 : $1/(1+s^2)$.

4.3 Problems DE-1 185

$$-1.4$$
: $1/s$
 -1.5 : $1/(1-|s|^2)$

Problem #2 Consider the function w(s) = 1/s

-2.1: Expand this function as a power series about s = 1. Hint: Let 1/s = 1/(1 - 1 + s) = 1/(1 - (1 - s)).

- -2.2: What is the RoC?
- -2.3: Expand w(s) = 1/s as a power series in $s^{-1} = 1/s$ about $s^{-1} = 1$.
- -2.4: What is the RoC?
- *−2.5:* What is the residue of the pole?

Problem #3 Consider the function w(s) = 1/(2-s)

- -3.1: Expand w(s) as a power series in $s^{-1} = 1/s$. State the RoC as a condition on $|s^{-1}|$. Hint: Multiply top and bottom by s^{-1} .
- -3.2: Find the inverse function s(w). Where are the poles and zeros of s(w), and where is it analytic?

Problem #4 Summing the series

The Taylor series of functions have more than one region of convergence.

-4.1: Given some function f(x), if a = 0.1, what is the value of

$$f(a) = 1 + a + a^2 + a^3 + \cdots$$
?

Show your work.

-4.2: Let a = 10. What is the value of

$$f(a) = 1 + a + a^2 + a^3 + \cdots$$
?

4.3.3 Cauchy-Riemann Equations

Problem #5 For this problem $J = \sqrt{-1}$, $s = \sigma + \omega J$, and $F(s) = u(\sigma, \omega) + J$ $v(\sigma, \omega)$. According to the fundamental theorem of complex calculus (FTCC), the integration of a complex analytic function is independent of the path. It follows that the derivative of F(s) is defined as

$$\frac{dF}{ds} = \frac{d}{ds} \left[u(\sigma, \omega) + j v(\sigma, \omega) \right]. \tag{DE-1.1}$$

If the integral is independent of the path, then the derivative must also be independent of the direction:

$$\frac{dF}{ds} = \frac{\partial F}{\partial \sigma} = \frac{\partial F}{\partial J\omega}.$$
 (DE-1.2)

The Cauchy-Riemann (CR) conditions

$$\frac{\partial u(\sigma,\omega)}{\partial \sigma} = \frac{\partial v(\sigma,\omega)}{\partial \omega} \quad and \quad \frac{\partial u(\sigma,\omega)}{\partial \omega} = -\frac{\partial v(\sigma,\omega)}{\partial \sigma}$$

may be used to show where Eq. DE-1.2 holds.

- -5.1: Assuming Eq. DE-1.2 is true, use it to derive the CR equations.
- -5.2: Merge the CR equations to show that u and v obey Laplace's equations

$$\nabla^2 u(\sigma, \omega) = 0$$
 and $\nabla^2 v(\sigma, \omega) = 0$.

What can you conclude?

Problem #6 Apply the CR equations to the following functions. State for which values of $s = \sigma + i\omega$ the CR conditions do or do not hold (e.g., where the function F(s) is or is not analytic). Hint: Review where CR-1 and CR-2 hold.

- -6.1: $F(s) = e^s$
- -6.2: F(s) = 1/s

4.3.4 Branch Cuts and Riemann Sheets

Problem #7 Consider the function $w^2(z) = z$. This function can also be written as $w_{\pm}(z) = \sqrt{z_{\pm}}$. Assume $z = re^{\phi_J}$ and $w(z) = \rho e^{\theta_J} = \sqrt{r}e^{\phi_J/2}$.

- -7.1: How many Riemann sheets do you need in the domain (z) and the range (w) to fully represent this function as single-valued?
- -7.2: Indicate (e.g., using a sketch) how the sheet(s) in the domain map to the sheet(s) in the range.
- -7.3: Use zviz.m to plot the positive and negative square roots $+\sqrt{z}$ and $-\sqrt{z}$. Describe what you see.
- -7.4: Where does zviz.mplace the branch cut for this function?
- −7.5: Must the branch cut necessarily be in this location?

Problem #8 Consider the function $w(z) = \log(z)$. As in Problem #7, let $z = re^{\phi J}$ and $w(z) = \rho e^{\theta J}$.

- -8.1: Describe with a sketch and then discuss the branch cut for f(z).
- -8.2: What is the inverse of the function z(f)? Does this function have a branch cut? If so, where is it?
- -8.3: Using zviz.m, show that

$$\tan^{-1}(z) = -\frac{J}{2}\log\frac{J-z}{J+z}.$$
 (DE-1.3)

In Fig. 4.1 these two functions are shown to be identical.

-8.4: Algebraically justify Eq. DE-1.3. Hint: Let $w(z) = \tan^{-1}(z)$ and $z(w) = \tan w = \sin w / \cos w$; then solve for e^{wj} .

4.3 Problems DE-1 187

4.3.5 A Cauer Synthesis of any Brune Impedance

Problem #9 One may synthesize a transmission line (ladder network) from a positive-real impedance Z(s) by using the continued fraction method. To obtain the series and shunt impedance values, we can use a residue expansion. Here we shall explore this method.

- -9.1: Starting from the Brune impedance $Z(s) = \frac{1}{s+1}$, find the impedance network as a ladder network.
- -9.2: Use a residue expansion in place of the CFA floor function (Sect. 2.4.4) for polynomial expansions. Find the residue expansion of $H(s) = s^2/(s+1)$ and express it as a ladder network.
- -9.3: Discuss how the series impedance Z(s,x) and shunt admittance Y(s,x) determine the wave velocity $\kappa(s,x)$ and the characteristic impedance $z_o(s,x)$ when (1) Z(s) and Y(s) are both independent of x; (2) Y(s) is independent of x, Z(s,x) depends on x; (3) Z(s) is independent of x, Y(s,x) depends on x; and (4) both Y(s,x), Z(s,x) depend on x.

4.4 Complex Analytic Brune Admittance

It is rarely stated that the variable that we are integrating over, either x (space) or t (time), is real $(x, t \in R)$, since that fact is implicit, due to the physical nature of the formulation of the integral. But this intuition must be refined once complex numbers are included with $s \in \mathbb{C}$, where $s = \sigma + \omega_I$.

That time and space are real variables and are more than an assumption: it is a requirement that follows from the *order property*. Real numbers have order. For example, if t = 0 is now (the present), then t < 0 is the past and t > 0 is the future. Since time and space are real $(t, x \in \mathbb{R})$, they obey this order property. To have time travel, time and space would need to be complex (they are not), since if the space axis were complex the order property would be invalid.

Interestingly, it was shown by d'Alembert (1747) that time and space are related by the pure delay. To obtain a solution to the governing wave equation, which d'Alembert first proposed for sound waves, $x, t \in \mathbb{R}$ may be functionally combined as

$$\zeta_{+} = t \pm x/c_{o}$$

where $c_o \in \mathbb{R}$ [m/s] is the wave phase velocity. The d'Alembert solution to the wave equation, describing waves on a string under tension, is

$$u(x,t) = f(t - x/c_o) + g(t + x/c_o), \tag{4.4.1}$$

which describes the transverse velocity (or displacement) of two independent waves $f(\zeta_-)$, $g(\zeta_+) \in \mathbb{R}$ on the string, which represent forward and backward traveling

waves.¹ For example, starting with a string at rest, if one displaces the left end, at x = 0, by a step function u(t), then that step displacement will propagate to the right as $u(t - x/c_o)$, arriving at location x_o [m], at time x_o/c_o [s]. Before this time, the string will not move to the right of the wavefront, at x_o [m], and after t_o [s] it will have a nonzero displacement. Since the wave equation obeys superposition (postulate P2, Sect. 3.10.2), it follows that the "plane-wave" eigenfunction of the wave equation for $\mathbf{x}, \mathbf{k} \in \mathbb{R}^3$ is given by

$$\psi_{+}(\mathbf{x},t) = \delta(t \mp \mathbf{k} \cdot \mathbf{x}) \leftrightarrow e^{st \pm j \mathbf{k} \cdot \mathbf{x}}, \tag{4.4.2}$$

where $|\mathbf{k}| = 2\pi/|\mathbf{i}| = \omega/c_o$ is the wave number, $|\lambda|$ is the wavelength, and $s = \sigma + \omega J$, the Laplace frequency.

Complex propagation function $\kappa(s)$: When propagation dispersion and losses are considered, we must replace the *wave number* $j\mathbf{k} \in \mathbb{C}$ with a complex analytic vector wave number $\kappa(s) = \mathbf{k}_r(s) + j\mathbf{k}(s)$. This is known by several names: (1) the *complex propagation function*, (2) the *dispersion relation*, and (3) the *propagation function*. Function $\kappa(s)$ is a subtle and important generalization of the scalar wave number $k = 2\pi/\lambda$.

An interesting example is the exact solution to the acoustic wave equation, including viscous and thermal losses, as discussed in Appendix D Eq. D.1.5, where it is shown that the eigenvalues are

$$\kappa_{\pm}(s) = \frac{s \pm 2\beta_o \sqrt{s}}{c_o} = \frac{(\beta_o \pm \sqrt{s})^2 - {\beta_o}^2}{c_o},$$

with $\beta_o \in \mathbb{R} \geq 0$.

Forms of energy loss, which include viscosity and radiation, require $\kappa(s) \in \mathbb{C}$. Physical examples include acoustic plane waves, electromagnetic wave propagation, antenna theory, and one of the most difficult cases, that of 3D electron wave propagating in crystals (e.g., silicon), where electrons and electromagnetic (EM) waves are in a state of quantum mechanical equilibrium.

Even when we cannot solve these more difficult problems, we can still appreciate their qualitative solutions. One of the principles that allows us to do that is the causal nature of $\kappa(s)$. Namely, the $\mathcal{L}\mathcal{T}^{-1}$ of $\kappa(s)$ must be causal, thus Eq. 4.4.2 must be causal. The *group delay* then describes the nature of the frequency dependent causal delay. For example, if the group delay is large at some frequency, then the solutions will have the largest causal delay at that frequency (Brillouin 1953; Papoulis 1962). Qualitatively this gives a deep insight into the solutions, even when if we cannot compute them.

Electrons and photons are simply different EM states, and $\kappa(x, s)$ describes the crystal's dispersion relations as functions of both frequency and direction, famously known as *Brillouin zones*. Dispersion is a property of the medium such that the wave

¹d'Alembert's solution is valid for functions that are not differentiable, such as $\delta(t - x/c_o)$.

²Recall that for lossless plane waves $\lambda f = c_o$, and $k = 2\pi/\lambda$.

velocity is a function of frequency and direction, as in silicon.³ Highly readable discussions on the history of this topic may be found in Brillouin (1953).

4.4.1 Generalized Admittance/Impedance

The most elementary examples of Brune admittance and impedance are those made of resistors, capacitors, and inductors. Such discrete element circuits arise not only in electrical networks but in mechanical, acoustical, and thermal networks as well (Table 3.2). These lumped-element networks can always be represented by ratios of polynomials in *s*. This gives them a similar structure, with easily classified properties. Such circuits are called *Brune admittances* (or impedances).⁴ An example of a special symmetry is when the degrees of the numerator and denominator polynomials cannot differ by more than one. This restriction on the degrees comes about because the real part of the admittance/impedance must be positive, due to physical constraints.

But there is a much broader class of admittances that comes from transmission lines and other physical structures, which we refer to as *generalized admittances*. An interesting example is an admittance of the form $1/\sqrt{s}$, called a *semicapacitor*, and \sqrt{s} , called a *semiinductor*. Generalized admittance/impedance is not the ratio of two polynomials. As a result, they are more difficult to characterize.

When a generalized admittance Y(s) or its impedance Z(s) = 1/Y(s) is transformed into the time domain, it must have a real and positive surge admittance $\mathcal{Y}_r \in \mathbb{R}$ or surge impedance $Z_r \in \mathbb{R}$, followed by the residual response $\nu(t)$, $\zeta(t)$. We define the following notation for the admittance (both frequency and time responses),

$$Y(s) = \gamma_r + \nu(s) \leftrightarrow \nu(t) = \gamma_r \delta(t) + \nu(t), \tag{4.4.3}$$

and the impedance,

$$Z(s) = Z_{c} + Z_{t}(s) \leftrightarrow z(t) = Z_{c}\delta(t) + \zeta(t). \tag{4.4.4}$$

The complexity of the notation is necessary and follows from the fact that $z(t) \leftrightarrow Z(s)$ and $y(t) \leftrightarrow Y(s)$ are positive-real and thus minimum phase.

When we are dealing with a transmission line (i.e., wave-guides), the generalized admittance is defined as the ratio of the flow to the force. For an electrical system (voltage Φ , current I), the input admittance looking to the right from location x is

$$Y_{in}^{+}(x > 0, s) = \frac{I^{+}(x, \omega)}{\Phi^{+}(x, \omega)},$$

³In case you missed it, what I'm suggesting is that photons (propagating waves) and electrons (evanescent waves) are different EM wave "states" (Jaynes 1991). This difference depends on the medium, which determines the dispersion relation (Papasimakis et al. 2018).

⁴Some texts prefer the term *immittance* to include both admittance and impedance.

and looking to the left is

$$Y_{in}^{-}(x < 0, s) = \frac{I^{-}(x, \omega)}{\Phi^{-}(x, \omega)}.$$

In general these two admittances $Y_{in}^{\pm}(x, s)$ are different.

Generalized reflectance: A function related to the generalized impedance is the *reflectance* $\Gamma(s)$, defined as the ratio of a reflected wave to the incident wave. For the case of acoustics (pressure \mathcal{P} , volume velocity \mathcal{V}),

$$Y_{in}(x,s) \equiv \frac{\mathcal{V}(\omega)}{\mathcal{P}(\omega)} = \frac{\mathcal{V}^{+} - \mathcal{V}^{-}}{\mathcal{P}^{+} + \mathcal{P}^{-}}$$
(4.4.5)

 $= \frac{v^{+}}{v^{+}} \frac{1 - v^{-}/v_{+}}{1 + v^{-}/v^{+}}$ (4.4.6)

When the area function is not constant the forward and reverse reflectance are not equal. Look at Sarah's thesis for clues.

$$= g_r^+ \frac{1 - \Gamma(x, s)}{1 + \Gamma(x, s)}. (4.4.7)$$

When the physical system is continuous at the measurement point x, $\mathcal{Y}_r^+(x) = \mathcal{Y}_r^-(x) \in \mathbb{R}$. The reflectance $\Gamma(x,s)$ depends on the area function, the boundary conditions, or both.

There is a direct relationship between a transmission line's area function $A(x) \in \mathbb{R}$, its characteristic impedance $\mathcal{Y}_r(x) \in \mathbb{R}$, and its eigenfunctions. We shall provide specific examples as they arise in our analysis of transmission lines (e.g., Fig. 5.3).

A few papers that deal with the relationship between $Y_{in}(s)$ and the area function A(x) are Youla (1964), Sondhi and Gopinath (1971), Rasetshwane et al. (2012). However, the general theory of this important and interesting problem is beyond the scope of this text (See homework DE-3, Problem # 2), as well as Appendix D.

4.4.1.1 Complex Analytic $\Gamma(s)$ and $Y_{in}(s) = Z_{in}^{-1}(s)$

When we define the complex reflectance $\Gamma(s)$, we make a key assumption: Even though $\Gamma(s)$ is defined by the ratio of two functions of real (radian) frequency ω , like the impedance, the reflectance must be causal (Postulate P1, Sect. 3.10.2). That $\gamma(t) \leftrightarrow \Gamma(s)$ and $\zeta(t) \leftrightarrow Z_{in}(s) = 1/Y_{in}(s)$ are causal is required by the physics.

4.4.2 Complex Analytic Impedance

Conservation of energy (or power) is a cornerstone of modern physics. It may first have been under consideration by Galileo Galilei (1564–1642) and Marin Mersenne (1588–1648). Today the question is not whether it is true, but why. Specifically, what is the physics behind conservation of energy? Surprisingly, the answer is straightfor-

ward, based on its definition and the properties of impedance. Recall that the power is the product of the force and the flow, and impedance is their ratio.

The power is given by the product of two variables, sometimes called *conjugate* variables, the force and the flow. In electrical terms, these are voltage (force) $(v(t) \leftrightarrow V(\omega))$ and current (flow) $(i(t) \leftrightarrow I(\omega))$; thus, the electrical power at any instant of time is⁵

$$\mathcal{P}(t) = v(t)i(t). \tag{4.4.8}$$

The total energy $\mathcal{E}(t)$ is the integral of the power, since $\mathcal{P}(t) = d\mathcal{E}/dt$. Thus if we start with all the elements at rest (no currents or voltages), then the energy as a function of time is always positive

$$\mathcal{E}(t) = \int_0^t \mathcal{P}(t)dt \ge 0 \tag{4.4.9}$$

and is simply the total energy applied to the network (Van Valkenburg 1964a, p. 376). Since the voltage and current are related by either an impedance or an admittance, conservation of energy depends on the property of impedance. From Ohm's law and Postulate P1 (every impedance is causal), and we have

$$v(t) = z(t) \star i(t)$$

$$= \int_{\tau=0}^{t} z(\tau)i(t-\tau)d\tau$$

$$\Leftrightarrow V(s) = Z(s)I(s).$$

Example: Let $i(t) = \delta(t)$ (a perfect impulse). Then

$$I_{xx}(t) = \int_{\tau=0}^{t} z(t-\tau)\delta(\tau)d\tau = \int_{0}^{t} z(-\tau)d\tau.$$

Every Brune impedance always has the form $z(t) = r_o \delta(t) + \zeta(t)$. The *characteristic impedance* r_o (also called *surge impedance*) may be defined as (Lundberg et al. 2007)

$$r_o = \int_{0^-}^{\infty} z(t)dt.$$

This definition requires that the integral of $\zeta(t)$ is zero, a conclusion that warrants further investigation.

These ideas are perhaps easier to visualize if we work in the Laplace frequency domain. Then the total energy, equal to the integral of the real part of the power, is

⁵The voltage is sometimes called the electromotive force (EMF). However v(t) is relative to a reference ground. The actual EMF is $-\nabla v(t)$.

$$\frac{1}{s}\Re VI = \frac{1}{2s}(V^*I + VI^*) = \frac{1}{2s}(Z^*I^*I + ZII^*) = \frac{1}{s}\Re Z(s)|I|^2 \ge 0.$$

Mathematically this is called a *positive-definite operator*, since the positive and real resistance is sandwiched between the current, forcing the "definiteness."

In conclusion, conservation of energy is totally dependent on the properties of the impedance. Thus one of the most important and obvious applications of complex analytic functions of a complex variable is the impedance function. This seems to be the ultimate example of the FTCC applied to z(t).

Every impedance must obey conservation of energy (Postulate P3): The impedance function Z(s) has resistance R and reactance X as a function of complex frequency $s = \sigma + j\omega$. From the causality postulate P1, z(t < 0) = 0. Every impedance is defined by a Laplace transform pair

$$z(t) \leftrightarrow Z(s) = R(\sigma, \omega) + jX(\sigma, \omega),$$

with $R, X \in \mathbb{R}$.

According to postulate P3 a system is passive if it does not contain a power source. Drawing power from an impedance violates conservation of energy. This property is also called *positive-real*, which was defined by Brune (1931b, a)

$$\Re\{Z(s \ge 0)\} \ge 0. \tag{4.4.10}$$

Positive-real systems cannot draw more power than is stored in the impedance. The region $\sigma \le 0$ is called the *left half s plane* (LHP), and the complementary region $\sigma > 0$ is called the *right half s plane* (RHP). According to the Brune condition, the real part of every impedance must be nonnegative (the RHP).

It is easy to construct examples of second-order poles or zeros in the RHP such that Postulate P3 is violated. Thus Postulate P3 implies that the impedance may *not* have more than simple (first-order) poles and zeros, strictly in the LHP. But there is more: These poles and zeros in the LHP must meet a *minimum phase condition*, a condition that is easily stated:

$$\angle Z(s) < \angle s$$
 (4.4.11)

but difficult to prove. There seems to be no proof that second-order poles and zeros (e.g., second-order roots) are not allowed.⁶ However, such roots must violate a requirement that the poles and zeros must alternate on the $\sigma=0$ axis, which follows from Postulate P3. In the complex plane the concept of "alternate" is not defined (complex numbers cannot be ordered). What *has* been proved (i.e., Foster's reactance theorem), that says that if the poles are on the real or imaginary axis, they must alternate, leading to simple poles and zeros (Van Valkenburg 1964a). The restriction on poles is sufficient but not necessary, as $Z(s) = 1/\sqrt{s}$ is a positive-real impedance

⁶As best I know, this is an open problem in network theory (Brune 1931a; Van Valkenburg 1964a).

but is less than a first-degree pole (Kim and Allen 2013). The corresponding condition in the LHP, and its proof, remains elusive (Van Valkenburg 1964a).

For example, a series resistor R_o and capacitor C_o have an impedance given by (Table 3.9)

$$Z(s) = R_o + 1/sC_o \leftrightarrow R_o\delta(t) + \frac{1}{C_o}u(t) = z(t), \tag{4.4.12}$$

with constants R_o , $C_o \in \mathbb{R} \ge 0$. In mechanics, an impedance composed of a dashpot (damper) and a spring has the same mathematical form.

A full 2d order resonant system has an inductor, resistor, and capacitor, with an impedance given by

$$Z(s) = \frac{sC_o}{1 + sC_oR_o + s^2C_oM_o} \leftrightarrow C_o\frac{d}{dt}\left(c_+e^{s_+t} + c_-e^{s_-t}\right) = z(t), \quad (4.4.13)$$

which is a second-degree polynomial with two complex resonant frequencies s_{\pm} . When $R_o > 0$, these roots are in the LHP, with $z(t) \leftrightarrow Z(s)$.

Systems (networks) that contain many elements and transmission lines can be much more complicated, yet still have a simple frequency-domain representation. This is the key to understanding how these physical systems work, as we describe next.

Poles and zeros of positive-real functions must be first-degree: The definition of positive-real (PR) functions requires that the poles and zeros of the impedance function be simple (only first-degree). Second-degree poles would have a reactive "secular" response of the form $h(t) = t \sin(\omega_k t + \phi)u(t)$, and these terms would not average to zero, depending on the phase, as is required of an impedance. As a result, only single-degree poles are possible. I believe that no one has ever reported an impedance that has second-degree poles and zeros. Network analysis books never report second-degree poles and zeros in their impedance functions. Nor has there ever been any guidance about where the poles and zeros might lie in the LHP. Understanding the exact relationships between pairs of poles and zeros, to assure that the real part of the impedance is real, would resolve this longstanding unsolved problem (Van Valkenburg 1964b). It is the residues that determine the LHP simple pole degree.

Calculus on Complex analytic functions: To solve a differential equation or integrate a function, Newton used the Taylor series to integrate one term at a time. However, he used only real functions of a real variable due to his fundamental lack of appreciation of the complex analysis. This same method is how one finds solutions to scalar differential equations today, but using an approach that makes the solution method less obvious. Rather than working directly with the Taylor series, today we use the complex exponential, since the complex exponential is an eigenfunction of the derivative

⁷Secular terms result from second-degree poles, since $u(t) \star u(t) = tu(t) \leftrightarrow 1/s^2$.

$$\frac{d}{dt}e^{st} = se^{st}.$$

Since e^{st} may be expressed as a Taylor series that has coefficients $c_n = 1/n!$, in some real sense the modern approach is a compact way of doing what Newton did. Thus every linear constant coefficient differential equation in time may be simply transformed into a polynomial in complex Laplace frequency s, by looking for solutions of the form $F(s)e^{st}$ and transforming the differential equation into polynomial F(s) in complex frequency.

For example

$$\frac{d}{dt}f(t) + af(t) = \delta(t) \leftrightarrow (s+a)F(s) = 1.$$

The pole of $F(s_r)$ is $s_r + a = 0$ is the eigenvalue of the differential equation. Thus a powerful tool for understanding the solutions of differential equations, both scalar and vector, is to work in the Laplace frequency domain using their eigenvalues (i.e., $s_r = -a$) and their eigenfunctions.

The Taylor series may be replaced by e^{st} , which transforms Newton's real Taylor series into the complex exponential eigenfunction. In some sense, these are the same methods, since

$$e^{s_r t} = \sum_{n=0}^{\infty} \frac{(s_r t)^n}{n!}.$$
 (4.4.14)

Taking the derivative with respect to time gives

$$\frac{d}{dt}e^{st} = se^{st} = s\sum_{n=0}^{\infty} \frac{(st)^n}{n!},$$
(4.4.15)

which is also complex analytic. Thus if the series for F(s) is valid (i.e., it converges), then its derivative is also valid. This was a very powerful concept, exploited by Newton for real functions of a real variable, and later by Cauchy and Riemann for complex functions of a complex variable. The key question is "Where does the series fail to converge?" This is the main concept behind the FTCC (Eq. 4.2.3).

The FTCC (Eq. 4.2.3) is formally the same as the FTC (Eq. 4.2.2) (Leibniz's formula), the key (and significant) difference being that the argument of the integrand $s \in \mathbb{C}$. Thus this integration is a line integral in the complex plane. One would naturally assume that the value of the integral depends on the path of integration. And it does, but in a subtle way, as quantified by Cauchy's various theorems. If the path stays in the same RoC region, then the integral is independent of that path. If a path includes a different pole, then the integral depends on the path, as quantified by the Cauchy residue theorem. The test is to deform the path from the first to the second. If in that deformation the path crosses a pole, then the integral will change (namely, it will depend on the path). All of this follows from causality.

The FTC and FTCC are clearly distinguishable yet the reasoning is the same. If F(s) = df(s)/ds is complex analytic [i.e., has a power series $f(s) = \sum_k c_k s^k$, with $f(s), c_k, s \in \mathbb{C}$], then it may be integrated, term by term, and yet the integral does not depend on the path. At first blush, this is sort of amazing. The key is that F(s) and f(s) must be complex analytic, which means they are differentiable. This all follows from the Taylor series formula Eq. 4.2.5 for the coefficients of the complex analytic series. For Eq. 4.2.3 to hold, the derivatives must be independent of the direction (the path), as discussed in Sect. 4.2.2. The concept of a complex analytic function, therefore, has eminent consequences in the form of several key theorems on complex integration, as first discovered by Cauchy in about 1820.

Role of the Complex Taylor series: The complex Taylor series generalizes the functions it describes, with unpredictable consequences, as nicely shown by the domain-coloring diagrams in Fig. 3.12, where a simple translation of the s plane by a complex number can void the positive-real property $(s - \sqrt{j})$ cannot be a physical impedance).

Cauchy's of complex integration tools were first exploited in physics by Sommerfeld (1952), to explain the onset (e.g., causal) transients in waves, as he explained in detail in Brillouin (1960, Chap. 3).

The importance of causality: Up to 1910, when Sommerfeld first published his results using complex analytic signals and saddle point integration in the complex plane, the implications of the causal wavefront were poorly understood. It would be reasonable to say that Sommerfeld's insight changed our understanding of wave propagation for both light and sound. Unfortunately, in my view, his insight has never been fully appreciated, perhaps even to this day. If you question this summary, please read Brillouin (1960, Chap. 1).

The full power of the complex analytic function was first appreciated by Bernard Riemann (1826–1866) in his University of Göttingen PhD thesis of 1851, under the tutelage of Gauss (1777–1855), which drew heavily on the work of Cauchy (Fig. 3.1).

The key definition of a complex analytic function is that it has a Taylor series representation, over a region of the complex frequency plane $s=\sigma+j\omega$, that converges in its RoC about the expansion point, with a radius determined by the nearest pole of the function. A further surprising feature of all analytic functions is that within the RoC, the inverse of that function also has a complex analytic expansion. Thus given w(s), in theory, we can determine s(w) to any desired accuracy, critically depending on the RoC. As an example if $w(s)=e^s$ then its inverse is s(w)=log(w). Given the right software (e.g., zviz.m), this relationship may be made precise for every complex analytic function.

4.4.3 Multivalued Functions

In the field of mathematics there seems to have been a tug-of-war regarding the basic definition of a function. The accepted definition today is a single-valued (i.e.,




Fig. 4.2 The mapping for the square root function $z = \pm \sqrt{x}$, the inverse of $x = z^2$. This function has two single-valued sheets of the x plane corresponding to the two signs of the square root. The best way to view this function is in polar coordinates, with $x = |x|e^{j\phi}$ and $z = \sqrt{|x|}e^{j\phi/2}$. The color code in this figure is unrelated to that of the colorized plots. Note that the axes are not labeled. Figure from: https://en.wikipedia.org/wiki/Riemann_surface

complex analytic) mapping from the domain to the codomain (or range). This makes the discussion of complex analytic multivalued functions somewhat awkward. In 1851 Riemann (working with Gauss) resolved this problem for the complex analytic set of multivalued functions by introducing the geometric concept of single-valued sheets, delineated by branch cuts.

Two simple yet important examples of multivalued functions are the circle $z^2 = x^2 + y^2$ and $w = \log(z)$. For example, if we assume $\rho = |z|$ is the radius of the circle, then solving for y(x) gives the double-valued function

$$y(x) = \pm \sqrt{\rho^2 - x^2}.$$

The related function $z = \pm \sqrt{x}$, with $x \in \mathbb{C}$, is shown in Fig. 4.2 as a three-dimensional display in polar coordinates, with z(r) as the vertical axis, as a function of the angle and radius of $x \in \mathbb{C}$.

If we accept the modern injective definition of a function, as the mapping from one set to a second set, then y(x) is not a function, or even two functions. For example, what if x > z? Or worse, what if z = 2j with |x| < 1? Riemann's construction, using branch cuts for multivalued function, resolves all these difficulties (as best I know).

To proceed, we need definitions and classifications of the various types of complex singularities:

1. Poles of degree 1 are called *simple poles*. Their amplitude is called the *residue* (e.g., α/s has residue α). Simple poles are special (see Eq. 4.5.3); they play a key role in mathematical physics, since their inverse Laplace transform defines a causal eigenfunction.

- 2. When the numerator and denominator of a rational function (i.e., ratio of two polynomials) have a common root (i.e., factor), that root is said to be *removable*.
- 3. A singularity that is not removable, a pole, or a branch point is called *essential*.
- 4. A complex analytic function (except for isolated poles) is called *meromorphic* (Boas 1987). Meromorphic functions can have any number of poles, even an infinite number. The poles need not be simple.
- 5. When the first derivative of a function Z(s) has a simple pole at a, then a is said to be a *branch point* of Z(s). An important example is the logarithmic derivative:

$$d \ln(s-a)^{\alpha}/ds = \alpha/(s-a), \ \alpha \in \mathbb{I}.$$

However, the converse does not necessarily hold.

6. I am not clear about the interesting case of an irrational pole ($\alpha \in \mathbb{I}$). In some cases (e.g., $\alpha \in \mathbb{F}$) this may be simplified with the logarithmic derivative operation, as mentioned in Sect. 3.1.2.

More complex topologies are being researched today, and progress is expected to accelerate due to modern computing technology.⁸ It is helpful to identify the physical meaning of these more complex surfaces, to guide us in their interpretation and possible applications.⁹

Branch cuts: Up to this point we have considered only poles of degree $\alpha \in \mathbb{N}$ of the form $1/s^{\alpha}$. The concept of a branch cut allows us to manipulate (and visualize) multivalued functions for which $\alpha \in \mathbb{F}$. This is done by breaking each region into single-valued sheets, as shown in Fig. 4.3 (right). The branch cut is a curve $\in \mathbb{C}$ that separates the various single-valued sheets of a multivalued function. The concepts of branch cuts, sheets, and the extended plane were first devised by Riemann, as described in his thesis of 1851. It was these three mathematical and geometrical constructions that provided deep insight into complex analytic functions, greatly extending the important earlier work of Cauchy (1789–1857) on the calculus of complex analytic functions. For an alternative helpful discussion of Riemann sheets and branch cuts, see Boas (1987, pp. 221–25), Kusse and Westwig (2010), and Greenberg (1988).

To study the properties of multivalued functions and branch cuts, we look at $w(s) = \sqrt{s}$ and $w(s) = \log(s)$, along with their inverse functions $w(s) = s^2$ and $w(s) = e^s$. For uniformity we refer to the *complex abscissa* $(s = \sigma + \omega_J)$ and the *complex ordinate* $(w(s) = u + v_J)$. When the complex domain and range are swapped, by taking the inverse of a function, multivalued functions are a common consequence. For example, $f(t) = \sin(t)$ is single-valued and analytic in t and thus has a Taylor series. The inverse function t(f) is multivalued.

The best way to explore the complex mapping from the complex planes $s \to w(s)$ is to master the single-valued function $s = w^2(s)$ and its double-valued inverse $w(s) = \sqrt{s}$.

⁸ https://www.maths.ox.ac.uk/about-us/departmental-art/theory.

 $^{^{9}} https://www.quantamagazine.org/secret-link-uncovered-between-pure-math-and-physics-20171201.$




Fig. 4.3 Here we use Cartesian coordinates in the domain $s = \sigma + \omega j$ and polar coordinates for the range $w(\sigma, \omega) = |w|e^{\psi j}$. The color intensity indicates the magnitude |s|, with black being |s| = 0| and bright (eventually white) indicating $|s| \to \infty$. Left: Mapping: $w(s) = s^2$. Right: Mapping of the principal branch from -s to $w(s) = -\sqrt{-s}$ (i.e., the rotated inverse of s^2). This sheet was generated by rotating w by 180°. The branch cut is on the $\psi = 0$ axis, with branch points at |w| = 0 and ∞ . Neither of these functions are Brune impedances, since they violate the positive-real condition (Eq. 3.2.19)

Figure 4.3 (left) shows the single-valued function $w(s) = s^2$, and (right) one sheet of its inverse, the double-valued mapping of $w(s) = -\sqrt{-s}$. Single-valued functions such as $w(s) = s^2$ are relatively straightforward. Multivalued functions require the concept of a branch cut, defined in the image plane (also called the codomain or range). This is a technique to render the multiple values as single-valued on each of several sheets. Each sheet is labeled in the domain (s) plane by a sheet index $k \in \mathbb{Z}$, while branch points and cuts are defined in the image (w) plane.

The sheets are indexed by a sheet index, and separated by the branch cut. It is important to understand that the path of every branch cut is not unique and may be moved. However, branch points are unique and thus not movable.

A function may be multivalued in both the domain and image planes. As an example consider $w(s) = s^{3/2}$.

The multivalued nature of $w(s) = \sqrt{s}$ is best understood by working with the function in polar coordinates. We let

$$s_k = re^{\theta_J} e^{2\pi k_J}, \tag{4.4.16}$$

where r = |s|, $\theta = \angle s$, $\in \mathbb{R}$, and $k \in \mathbb{Z}$ is the sheet index.

This concept of analytic inverses becomes important only when the function is multivalued. For example, since $w(s) = s^2$ has a period of 2, $s(w) = \pm \sqrt{w}$ is multivalued. Riemann dealt with such extensions using the concept of a branch cut with multiple sheets labeled by sheet numbers. Each sheet describes an analytic function (Taylor series) that converges within some RoC that has a radius out to the nearest pole. Thus Riemann's branch cuts and sheets explicitly deal with the need to




Fig. 4.4 Colorized plots of $s_k = |s|e^{\theta_J}e^{2\pi k_J}$ and $w_k(s) = \sqrt{s_k} = \sqrt{|s|}e^{\theta_J/2}e^{\pi k_J}$, as defined in polar coordinates by Eqs. 4.4.16 and 4.4.17. Left: Color map hue reference plane $s = |s|e^{\theta_J}e^{2\pi k_J}$. This function is a Brune impedance (it represents an inductor). Center: Sheet index k = 0, $w(s) = \sqrt{|s|}e^{J\theta/2}$ for $-\pi < \theta < +\pi$ and $\psi = \angle w(s) = \theta/2$ between $\pm \pi/2$ [rad]. This function is positivereal (Eq. 3.2.19) but is not a Brune impedance, since it is not the ratio of polynomials in s. Thus it is the generalized impedance, known as a semiinductor. Right: Sheet index k = 1, $w(s) = e^{J\theta/2}e^{J\pi}\sqrt{|s|}$ for $\pi < \theta < 3\pi$ and $\pi/2 < \psi < 3\pi/2$ [rad]. The branch cut is at $\theta = \angle s = \pm 180^\circ$ (π [rad]) where the hue of w changes abruptly from green to purple (center) and from purple back to green (right). Note how the hue matches between the center and right panels at the branch cut: in the center panel purple runs along -180° and along +180° on the right. Likewise, green runs along +180° in the: $\pm \sqrt{s}$, $e^{\pi J}\sqrt{s}$ center and along -180° on the right. Thus $w(s) = \sqrt{s}$ is analytic on the branch cut connecting the two sheets $(k = 0 \rightarrow k = 1)$. This function is not an impedance, since it is negative in the RHP

define unique single-valued inverses of multivalued functions. Since the square root function has two overlapping regions corresponding to the \pm due to the radical, there must be two connected region—sort of like mathematical Siamese twins: distinct, yet the same.

Hue: By studying Fig. 4.4, we can appreciate domain-coloring. The angle-to-hue map is shown in the left panel of Fig. 4.4. The domain angles $\angle s$ go from $-90^{\circ} < \theta < 90^{\circ}$ (purple to red to green). For $w(s) = \sqrt{s}$, the $\angle s$ is *compressed* by a factor of 2 ($\psi = \theta/2$) with purple being -180° , and green being $+180^{\circ}$.

Thus for Fig. 4.4 the principal (k=0) angle $\angle s$ $(-180^{\circ} < \theta < 180^{\circ})$ maps to $w(s) = \sqrt{s}$ (middle panel) to half the w plane $(-90^{\circ} < \psi < 90^{\circ})$ (from purple to red to green).

The k=1 branch, of $\angle s$ (+180° < θ < 180 + 360 = 520°) maps to $\angle w$ (on the right) to green to blue to purple ($\psi=\theta/2$). Note how the panel on the left matches the right half of s (green = +90°, purple = -90°). The center panel $\angle w$ is green where $\angle s=180^\circ$. Thus $\angle w=\frac{1}{2}\angle s$. Going around the s plane one more time gives the right most figure. w(s) is analytic everywhere except at the branch points s=0 and $s=\infty$.

Moving the branch cut: Furthermore we can change $\angle s$ by 180° to move the branch cut

$$w = \rho e^{J\psi} = \sqrt{r} e^{J\theta/2} e^{J\pi k}, \qquad (4.4.17)$$

where $\rho = |w|, \psi \angle w, \in \mathbb{R}$. The generic Cartesian coordinates are $s = \sigma + \omega \jmath$ and $w(s) = u(\sigma, \omega) + v(\sigma, \omega)\jmath$. For single-valued functions such as $w(s) = s^2$ on the left in Fig. 4.3 there is no branch cut, since $\psi = 2\theta$. Note how the red color $(\theta = 0^\circ)$ appears twice in this mapping. For multivalued functions, a branch cut is required, typically along the negative $v(\sigma, \omega)$ axis (i.e., $\psi = \pi$), but it may be freely distorted, as seen by comparing the right panel of Fig. 4.3 with the right panel of Fig. 4.4.

Properties of the branch cut: It is important to understand that the function is analytic on the branch cut but not at the branch points. One is free to move the branch cut (at will). It does not need to be on a line: it could be cut in almost any connected manner, such as a spiral. The only rule is that it must start and stop at the matching branch points, or at ∞ , which must have the same degree.

The location of the branch cut may be moved by rotating the s-coordinate system of Fig. 4.2. For example, $w(s) = \pm j \sqrt{s}$ and $w(s) = \pm \sqrt{-s}$ have different branch cuts, as may be verified using the Matlab/Octave commands j*zviz(s) and zviz(-s). Every function is analytic on the branch cut (since moving it does not change the function). If a Taylor series is formed on the branch cut, it will describe the function on the two different sheets. Thus the complex analytic series (i.e., the Taylor formula, Eq. 4.2.5) does not depend on the location of a branch cut, as it only describes the function uniquely (as a single-valued function), valid in its local region of convergence.

The second sheet (k=1) in Fig. 4.4 picks up at $\theta=\pi$ [rads] and continues on to $\pi+2\pi=3\pi$. The first sheet maps the angle of w (i.e., $\phi=\angle w=\theta/2$) from $-\pi/2<\phi<\pi/2$ ($w=\sqrt{r}e^{j\theta/2}$). This corresponds to $u=\Re\{w(s)\}>0$. The second sheet maps $\pi/2<\psi<3\pi/2$ (i.e., 90° to 270°), which is $\Re\{w\}=u<0$. In summary, twice around the s plane is once around the s0 plane because the angle is half due to the \sqrt{s} .

Branch cuts emanate and terminate at *branch points*, defined as singularities (poles) that can even have fractional degree, as, for example, $1/\sqrt{s}$, and terminate at one of the matching roots, which includes the possibility of ∞ .¹⁰ For example, suppose that in the neighborhood of the pole, at s_o the function is

$$f(s) = \frac{w(s)}{(s - s_o)^k},$$
(4.4.18)

where $w, s, s_o \in \mathbb{C}$ and $k \in \mathbb{Q}$. When $k = 1, s_o = \sigma_o + \omega_o J$ is a first-degree "simple pole," having degree 1 in the s plane, with residue $w(s_o)$. Typically the order and degree are positive integers, but fractional degrees and orders are common in modern engineering applications (Kirchhoff 1868; Lighthill 1978). Here we allow both the degree and the order to be fractional $(\in \mathbb{F})$. When $k \in \mathbb{F} \subset \mathbb{R}$, k = n/m is a real reduced fraction—namely, when GCD $(n,m) = 1, n \perp m$). This defines the *degree* of a fractional pole. In such cases there must be two sets of branch cuts of degrees n and

¹⁰This presumes that poles and zeros appear in pairs, one of which may be at ∞ .




Fig. 4.5 Colorized plots of two $\mathcal{L}T$ pairs: Left: $\sqrt{\pi/s} \leftrightarrow u(t)/\sqrt{t}$. Right: $\sqrt{s^2+1} \leftrightarrow \delta(t) + \frac{1}{t}J_1(t)u(t)$

m. For example, if k = 1/2, the singularity (branch cut) is of degree 1/2 and there are two Riemann sheets, as shown in Fig. 4.3.

Fractional-order Bessel function: An important example is the Bessel function and its Laplace transform (\mathcal{LT})

$$\delta(t) + \frac{1}{t} J_1(t) u(t) \leftrightarrow \sqrt{s^2 + 1},$$

as shown in Fig. 4.5, which is related to the solution to the wave equation in twodimensional cylindrical coordinates (see Table C.2). Bessel functions are the solutions (i.e., eigenfunctions) of guided acoustic waves in round pipes, or surface waves on the Earth (seismic waves), or waves on the surface of a pond (Table 5.2).

There are a limited number of possibilities for the degree, $k \in \mathbb{Z}$ or $\in \mathbb{F}$ of Eq. 4.4.18. If the degree is drawn from $\mathbb{R} \notin \mathbb{F}$, the pole cannot have a residue. According to the definition of the residue, $k \in \mathbb{F}$ has no residue. But there remains open the possibility of generalizing the concept of the Riemann integral theorem to include $k \in \mathbb{F}$. One way to do this is to use the logarithmic derivative, which transforms fractional poles to simple poles with fractional residues. (See Ex.# 9, Sect. 3.1.2).

If the singularity has an irrational degree $(k \in \mathbb{I})$, the branch point has the same irrational degree. Accordingly there are an infinite number of Riemann sheets, as in the case of the log function. An example is $k = \pi$, for which

$$F(s) = \frac{1}{s^{\pi}} = e^{-\log(s^{\pi})} = e^{-\pi \log(s)} = e^{-\pi \log(\rho)} e^{-\pi \theta J},$$

where the domain is expressed in polar coordinates $s = \rho e^{\theta_J}$. When $k \in \mathbb{F}$, it may be close (e.g., $k = \pi_{152}/\pi_{153} = \pi_{152}/(\pi_{152} + 2) = 881/883 \approx 0.99883$, or its recip-

rocal ≈ 1.0023). The branch cut could be subtle (it could even go unnoticed), but it would have a significant impact on the function and on its inverse Laplace transform.

Exercise #2 Find the poles, zeros, and residues of F(s).

1.

$$F(s) = \frac{d}{ds} \ln \frac{s+e}{s+\pi}$$

Solution:

$$F(s) = \frac{d}{ds} \left[\ln(s+e) - \ln(s+\pi) \right] = \left(\frac{1}{s+e} - \frac{1}{s+\pi} \right)$$

The poles are at $s_1 = -e$ and $s_2 = -\pi$ with respective residues of ± 1 .

2.

$$F(s) = \frac{d}{ds} \ln \frac{(s+3)^e}{(s+j)^{-\pi}}$$

Solution:

$$F(s) = \frac{d}{ds} \left(e \ln(s+3) + \pi \ln(s+j) \right) = \frac{e}{s+3} + \frac{\pi}{s+j}.$$

There is a very important take-home message here regarding the utility of the logarithmic derivative, which "linearizes" the fractional pole. ■

3.

$$F(s) = e^{\pi \ln s}$$

Solution: To simplify this expression take the log

$$\ln F(s) = \ln e^{\pi \ln s} = \pi \ln s = \ln s^{\pi}.$$

Thus $F(s) = s^{\pi}$. The only pole is $s \to \infty$. Thus the definition of the residue is to multiply by the pole and take the limit as $s \to \infty$

$$c_{-1} = \lim_{s \to \infty} \frac{s^{\pi}}{s} = 0^{\pi - 1} = 0.$$

4.

$$F(s) = \pi^{-s}$$

Solution: Converting to exponential format: $F(s) = e^{-s \ln \pi} \leftrightarrow \delta(t - \ln \pi)$. I don't think the pure time delay has poles. I'm not sure what this tells us about the residue.

Log function: Next we discuss the multivalued nature of the log function. In this case there are an infinite number of Riemann sheets, not captured by Fig. 3.14, which displays only the principal sheet. However, if we look at the formula for the log function, the nature is easily discerned. The abscissa *s* may be defined as multivalued, since

$$s_k = re^{2\pi k_J}e^{\theta_J}.$$

Here we have extended the angle of s by $2\pi k$, where k is the sheet index $\in \mathbb{Z}$. Now we take the log:

$$\log(s) = \log(r) + (\theta + 2\pi k)j.$$

When k = 0, we have the principal value sheet, which is zero when s = 1. For any other value of k, $w(s) \neq 0$, even when r = 1, since the angle is not zero, except for the k = 0 sheet.

4.5 Three Cauchy Integral Theorems

4.5.1 Cauchy's Theorems for Integration in the Complex Plane

There are three basic definitions related to Cauchy's integral formula. They are closely related and can greatly simplify integration in the complex plane. The choice of names is unfortunate, if not totally confusing. Hence I call them CT-1, CT-2, and CT-3.

1. Cauchy's (integral) theorem (CT-1):

$$\oint_{\mathcal{C}} F(s)ds = 0 \tag{4.5.1}$$

if and only if F(s) is complex analytic inside of a simple closed curve \mathcal{C} (Stillwell 2010; Boas 1987, p. 45). The FTCC (Eq. 4.2.3) says that the integral depends on only the end points if F(s) is complex analytic. With the path (contour \mathcal{C}) closed, the end points are the same and thus the integral must be zero as long as F(s) is complex analytic.

2. Cauchy's integral formula (CT-2):

$$\frac{1}{2\pi j} \oint_{\mathcal{B}} \frac{F(s)}{s - s_o} ds = \begin{cases} F(s_o), s_o \in \mathbb{C} < \mathcal{B} \text{ (inside)} \\ 0, s_o \in \mathbb{C} > \mathcal{B} \text{ (outside)}. \end{cases}$$
(4.5.2)

Here F(s) is required to be analytic everywhere within (and on) the boundary \mathcal{B} of integration (Greenberg 1988, p. 1200); (Boas 1987, p. 51); (Stillwell 2010, p. 220). When the point $s_o \in \mathbb{C}$ is within the boundary, the value $F(s_o) \in \mathbb{C}$ is the residue of the pole s_o of $F(s)/(s-s_o)$. When the point s_o lies outside the boundary, the integral is zero.

The (Cauchy) residue theorem (CT-3): (Greenberg 1988, p. 1241); (Boas 1987, p. 73)

$$\oint_{C} f(s)ds = 2\pi j \sum_{k=1}^{K} c_{k} = \sum_{k=1}^{K} \oint \frac{F(s)}{s - s_{k}} ds, \qquad (4.5.3)$$

where the residues $c_k \in \mathbb{C}$ correspond to the kth pole of f(s) enclosed by the contour C (Greenberg 1988, p. 1241); (Boas 1987, p. 73). Cauchy's integral formula (CT-2) is a special case of the residue theorem (CT-3).

How to calculate the residue: The case of first-degree poles has special significance because the Brune impedance allows only simple poles and zeros, thus increasing its utility. The residues for simple poles are $F(s_k)$, which is complex analytic in the neighborhood of the pole, but not at the pole.

Consider the function $f(s) = F(s)/(s - s_k)$, where we have factored f(s) to isolate the first-order pole at $s = s_k$, with F(s) analytic at s_k . Then the residue of the poles at $c_k = F(s_k)$. This coefficient is computed by removing the singularity, placing a zero at the pole frequency, and taking the limit as $s \to s_k$ —namely,

$$c_k = \lim_{s \to s_k} [(s - s_k) f(s)]$$
 (4.5.4)

(Greenberg 1988; Boas 1987, p. 72).

When the pole is an Nth degree, the procedure is much more complicated and requires taking N-1 order derivatives of f(s) followed by the limit process (Greenberg 1988, p. 1242). Higher degree poles are rarely encountered; thus it is good to know that this formula exists, but perhaps it is not worth the effort to learn (i.e., memorize) it.

Some open questions: Without the use of CT-3 it is hard to evaluate the inverse Laplace transform of 1/s directly. For example, how do we show that the integral (Eq. 4.5.2) is zero for negative time (or 1 for positive time)? CT-3 resolves this difficult problem by the convergence of the integral for negative and positive times. Clearly the convergence of the integral at $\omega \to \infty$ plays an important role.

4.5.2 Cauchy Integral Formula and Residue Theorem

CT-2 is an important extension of CT-1, in that a pole has been explicitly represented in the integrand at $s = s_o$. If the pole location is outside the curve C, the result of the integral is zero, in keeping with CT-1. When the pole is inside C, the integrand is no

longer complex analytic at the enclosed pole. When this pole is simple, the residue theorem applies. For the related CT-3 the same result holds, except it is assumed that there are K simple poles in the function F(s). This requires K repeated applications of CT-2. Thus it represents a minor extension of CT-2. When the integrand is $f(s)/P_K(s)$, where f(s) is analytic in C and $P_K(s)$ is a polynomial of degree K, with all of its roots $s_k \in C$, then CT-3 applies.

Nonintegral degree singularities: A key point is that this theorem applies when $k \in \mathbb{I}$, including fractionals $k \in \mathbb{F}$, but for these cases the residue is always zero, since by definition the residue is the amplitude of the 1/s term (Boas 1987, p. 73). Below are examples:

- 1. When $k \in \mathbb{F}$ (e.g., k = 2/3), the residue of s^k is zero, by definition.
- 2. The function $1/\sqrt{s}$ has a zero residue (we apply the definition of the residue, Eq. 4.5.4).
- 3. When $k \neq 1 \in \mathbb{I}$, the residue is, by definition, zero.
- 4. When k = 1, the residue is given by Eq. 4.5.4.
- 5. CT-1, CT-2, and CT-3 are essential when computing the inverse Laplace transform.

Summary and examples: These three CT theorems, all attributed to Cauchy, collectively are related to the fundamental theorems of complex calculus. The general principles are

- 1. In general it makes no sense (nor is there any need) to integrate *through* a pole; thus the poles (or other singularities) must not lie on C.
- 2. CT-1 (Eq. 4.5.1) follows trivially from the fundamental theorem of complex calculus (Eq. 4.2.3), since if the integral is independent of the path and the path returns to the starting point, the closed integral must be zero. Thus Eq. 4.5.1 holds when F(s) is complex analytic within C.
- 3. Since the real and imaginary parts of every complex analytic function obey Laplace's equation (Eq. 4.2.8), it follows that every closed integral over a Laplace field—that is, those defined by Laplace's equation—must be zero. In fact, this is the property of a conservative system, corresponding to many physical systems. If a closed box has fixed potentials on the walls, with any distribution whatsoever, and a point charge (i.e., an electron) is placed in the box, then a force equal to F = qE is required to move that charge, and thus work is done. However, if the point is returned to its starting location, the network done is zero.
- 4. Work is done in charging a capacitor, and energy is stored. However, when the capacitor is discharged, all of the energy is returned to the load.
- 5. Soap bubbles and rubber sheets on a wire frame obey Laplace's equation.
- 6. These are all cases where the fields are Laplacian, thus closed line integrals must be zero. Laplacian fields are commonly seen because they are so basic.
- 7. We have presented the impedance as the primary example of a complex analytic function. Physically, every impedance has an associated stored energy, and every system having stored energy has an associated impedance. This impedance is usually defined in the frequency *s* domain, as a force *over* a flow (i.e., voltage

over current). The power $\mathcal{P}(t)$ is defined as the force *times* the flow and the energy $\mathcal{E}(t)$ as the time integral of the power

$$\mathcal{E}(t) = \int_{-\infty}^{t} \mathcal{P}(t)dt, \qquad (4.5.5)$$

which is similar to Eq. 4.2.1 [see Sect. 3.8.3, Eq. 3.8.9]. In summary, impedance and power and energy are all fundamentally related.

4.6 Problems DE-2

4.6.1 Topics of This Homework

Integration of complex functions, Cauchy's theorem, integral formula, residue theorem, power series, Riemann sheets and branch cuts, inverse Laplace transforms, Quadratic forms.

4.6.2 Two Fundamental Theorems of Calculus

4.6.2.1 Fundamental Theorem of Calculus (Leibniz)

According to the fundamental theorem of (real) calculus (FTC),

$$f(x) = f(a) + \int_{a}^{x} F(\xi)d\xi,$$
 (DE-2.1)

where $x, a, \xi, F, f \in \mathbb{R}$. This is an indefinite integral (since the upper limit is unspecified). It follows that

$$\frac{df(x)}{dx} = \frac{d}{dx} \int_{a}^{x} F(x) dx = F(x).$$

This justifies also calling the indefinite integral the *antiderivative*.

For a closed interval [a, b], the FTC is

$$\int_{a}^{b} F(x)dx = f(b) - f(a),$$
 (DE-2.2)

thus the integral is independent of the path from x = a to x = b.

4.6 Problems DE-2 207

Fundamental Theorem of Complex Calculus

According to the fundamental theorem of complex calculus (FTCC),

$$f(z) = f(z_0) + \int_{z_0}^{z} F(\zeta)d\zeta,$$
 (DE-2.3)

where $z_0, z, \zeta, f, F \in \mathbb{C}$. It follows that

$$\frac{df(z)}{dz} = \frac{d}{dz} \int_{z_0}^{z} F(\zeta) d\zeta = F(z).$$
 (DE-2.4)

For a closed interval $[s, s_o]$, the FTCC is

$$\int_{s}^{s} F(\zeta)d\zeta = f(s) - f(s_o), \tag{DE-2.5}$$

thus the integral is independent of the path from x = a to x = b.

Problem #1 -1.1: Consider Eq. DE-2.1. What is the condition on F(x) for which this formula is true?

-1.2: Consider Eq. DE-2.3. What is the condition on F(z) for which this formula is true?

$$-1.3$$
: Let $F(z) = \sum_{k=0}^{\infty} c_k z^k$.
-1.4: Let

$$F(z) = \frac{\sum_{k=0}^{\infty} c_k z^k}{z - j}.$$

Problem #2 In the following problems, solve the integral

$$I = \int_{\mathcal{C}} F(z) dz$$

for a given path $C \in \mathbb{C}$.

-2.1: Perform the following integrals $(z = x + iy \in \mathbb{C})$:

- 1. $I = \int_0^{1+j} z dz$ 2. $I = \int_0^{1+j} z dz$, but this time make the path explicit: from 0 to 1, with y = 0, and then to y = 1, with x = 1.
- 3. Discuss whether your results agree with Eq. DE-2.4?
- -2.2: Perform the following integrals on the closed path C, which we define to be the unit circle. You should substitute $z = e^{i\theta}$ and $dz = ie^{i\theta}d\theta$, and integrate from $\{-\pi, \pi\}$ to go once around the unit circle.

Discuss whether your results agree with Eq. DE-2.4?

- 1. $\int_C z dz$
- 2. $\int_C \frac{1}{z} dz$
- 3. $\int_C \frac{1}{z^2} dz$
- 4. $I = \int_{\mathcal{C}} \frac{1}{(z+2J)^2} dz$.

Recall that the path of integration is the unit circle, starting and ending at -1.

Problem #3 FTCC and integration in the complex plane

Let the function $F(z) = c^z$, where $c \in \mathbb{C}$ is given for each question. Hint: Can you apply the FTCC?

- -3.1: For the function $f(z) = c^z$, where $c \in \mathbb{C}$ is an arbitrary complex constant, use the Cauchy–Riemann (CR) equations to show that f(z) is analytic for all $z \in \mathbb{C}$.
 - -3.2: Find the antiderivative of F(z).
 - -3.3: c = 1/e = 1/2.7183, ... where C is $\zeta = 0 → i → z$
 - -3.4: c=2, where C is $\zeta=0 \rightarrow (1+i) \rightarrow z$
- -3.5: c = i, where the path C is an inward spiral described by $z(t) = 0.99^t e^{i2\pi t}$ for $t = 0 \rightarrow t_0 \rightarrow \infty$
- -3.6: $c=e^{t-\tau_0}$, where $\tau_0>0$ is a real number and $\mathcal C$ is $z=(1-i\infty)\to (1+i\infty)$. Hint: Do you recognize this integral? If you do not, please do not spend a lot of time trying to solve it via the "brute force" method.

4.6.3 Cauchy's Theorems CT-1, CT-2, CT-3

Problem #4 Cauchy's theorems for integration in the complex plane

There are three basic definitions related to Cauchy's integral formula. They are all related and can greatly simplify integration in the complex plane. When a function depends on a complex variable, we use uppercase notation, consistent with the engineering literature for the Laplace transform.

1. Cauchy's (Integral) Theorem CT-1 (Stillwell, 2010, p. 319; Boas, 1987, p. 45)

$$\oint_{\mathcal{C}} F(z)dz = 0$$

if and only if F(z) is complex analytic inside of C. This is related to the FTCC,

$$f(z) = f(a) + \int_{a}^{z} F(z)dz,$$

where f(z) is the antiderivative of F(z)—namely, F(z) = df/dz. The FTCC requires F(z) to be complex analytic for all $z \in \mathbb{C}$. By closing the path (contour \mathcal{C}), Cauchy's theorem (and the following theorems) allows us to integrate functions that may not be complex analytic for all $z \in \mathbb{C}$.

4.6 Problems DE-2 209

2. Cauchy's Integral Formula CT-2 (Boas (1987), p. 51; Stillwell, 2010, p. 220)

$$\frac{1}{2\pi j} \oint_{\mathcal{C}} \frac{F(z)}{z - z_0} dz = \begin{cases} F(z_0), z_0 \in \mathcal{C} \ (inside) \\ 0, z_0 \notin \mathcal{C} \ (outside). \end{cases}$$

Here F(z) is required to be analytic everywhere within (and on) the contour C. $F(z_0)$ is called the *residue* of the pole.

3. (Cauchy's) Residue Theorem CT-3 (Boas (1987), p. 72)

$$\oint_{\mathcal{C}} F(z)dz = 2\pi j \sum_{k=1}^{K} Res_k,$$

where Res_k are the residues of all poles of F(z) enclosed by the contour C. **How to calculate the residues**: The residues can be rigorously defined as

$$Res_k = \lim_{z \to z_k} [(z - z_k) f(z)].$$

This can be related to Cauchy's integral formula: Consider the function F(z) = $w(z)/(z-z_k)$, where we have factored F(z) to isolate the first-order pole at $z = z_k$. If the remaining factor w(z) is analytic at z_k , then the residue of the pole at $z = z_k$ is $w(z_k)$.

-4.1: Describe the relationships between the theorems:

- 1. CT-1 and CT-2
- 2. CT-1 and CT-3
- CT-2 and CT-3
 - -4.2: Consider the function with poles at $z = \pm j$,

$$F(z) = \frac{1}{1+z^2} = \frac{1}{(z-j)(z+j)}.$$

Find the residue expansion.

-4.3: Apply Cauchy's theorems to solve the following integrals. State which theorem(s) you used and show your work.

- 1. $\oint_{\mathcal{C}} F(z)dz$, where \mathcal{C} is a circle centered at z=0 with a radius of $\frac{1}{2}$. $\oint_{\mathcal{C}} F(z)dz$, where \mathcal{C} is a circle centered at z=j with a radius of 1
- 3. $\oint_{\mathcal{C}} F(z)dz$, where \mathcal{C} is a circle centered at z=0 with a radius of 2

4.6.4 Integration of Analytic Functions

Problem #5 Integration in the complex plane

In the following questions, you'll be asked to integrate $F(s) = u(\sigma, \omega) + iv(\sigma, \omega)$ around the contour \mathcal{C} for complex $s = \sigma + i\omega$,

$$\oint_{\mathcal{C}} F(s)ds.$$

Follow the directions carefully for each question. When asked to state where the function is and is not analytic, you are not required to use the Cauchy–Riemann equations (but you should if you can't answer the question "by inspection").

- -5.1: $F(s) = \sin(s)$ -5.2: Given function $F(s) = \frac{1}{s}$
- 1. State where the function is and is not analytic.
- 2. Explicitly evaluate the integral when $\mathcal C$ is the unit circle, defined as $s=e^{i\theta}$, $0<\theta<2\pi$.
- 3. Evaluate the same integral using Cauchy's theorem and/or the residue theorem.

$$-5.3$$
: $F(s) = \frac{1}{s^2}$

- 1. State where the function is and is not analytic.
- 2. Explicitly evaluate the integral when $\mathcal C$ is the unit circle, defined as $s=e^{i\theta}$, $0\leq\theta\leq2\pi$.
- 3. What does your result imply about the residue of the second-order pole at s = 0?

$$-5.4$$
: $F(s) = e^{st}$

- 1. State where the function is and is not analytic.
- 2. Explicitly evaluate the integral when C is the square $(\sigma, \omega) = (1, 1) \rightarrow (-1, 1) \rightarrow (-1, -1) \rightarrow (1, -1) \rightarrow (1, 1)$.
- 3. Evaluate the same integral using Cauchy's theorem and/or the residue theorem.

$$-5.5$$
: $F(s) = \frac{1}{s+2}$

- 1. State where the function is and is not analytic.
- 2. Let C be the unit circle, defined as $s = e^{i\theta}$, $0 \le \theta \le 2\pi$. Evaluate the integral using Cauchy's theorem and/or the residue theorem.
- 3. Let C be a circle of radius 3, defined as $s = 3e^{i\theta}$, $0 \le \theta \le 2\pi$. Evaluate the integral using Cauchy's theorem and/or the residue theorem.

$$-5.6$$
: $F(s) = \frac{1}{2\pi i} \frac{e^{st}}{(s+4)}$

- 1. State where the function is and is not analytic.
- 2. Let C be a circle of radius 3, defined as $s = 3e^{i\theta}$, $0 \le \theta \le 2\pi$. Evaluate the integral using Cauchy's theorem and/or the residue theorem.

4.6 Problems DE-2 211

3. Let C contain the entire left half s plane. Evaluate the integral using Cauchy's theorem and/or the residue theorem. Do you recognize this integral?

$$-5.7$$
: $F(s) = \pm \frac{1}{\sqrt{s}} (e.g., F^2 = \frac{1}{s})$

- 1. State where the function is and is not analytic.
- 2. This function is multivalued. How many Riemann sheets do you need in the domain (s) and the range (f) to fully represent this function? Indicate (e.g., using a sketch) how the sheet(s) in the domain map to the sheet(s) in the range.
- 3. Explicitly evaluate the integral

$$\int_{\mathcal{C}} \frac{1}{\sqrt{z}} dz$$

when C is the unit circle, defined as $s = e^{i\theta}$, $0 \le \theta \le 2\pi$. Is this contour closed? State why or why not.

4. Explicitly evaluate the integral

$$\int_{\mathcal{C}} \frac{1}{\sqrt{z}} dz$$

when C is *twice* around the unit circle, defined as $s = e^{i\theta}$, $0 \le \theta \le 4\pi$. Is this contour closed? State why or why not. Hint: Note that]

$$\sqrt{e^{i(\theta+2\pi)}} = \sqrt{e^{i2\pi}e^{i\theta}} = e^{i\pi}\sqrt{e^{i\theta}} = -1\sqrt{e^{i\theta}}.$$

- 5. What does your result imply about the residue of the (twice-around $\frac{1}{2}$ order) pole at s = 0?
- 6. Show that the residue is zero. Hint: Apply the definition of the residue.

4.6.5 Laplace Transform Applications

Problem #6 A two-port network application for the Laplace transform




Fig. 4.6 This three-element electrical circuit is a system that acts to low-pass filter the signal voltage $V_1(\omega)$, to produce signal $V_2(\omega)$. It is convenient to define the dimensionless ratio $s/s_c = RCs$ in terms of a time constant $\tau = RC$ and cutoff frequency $s_c = 1/\tau$

- -6.1: Find the 2×2 ABCD matrix representation of Fig. 4.6. Express the results in terms of the dimensionless ratio s/s_c , where $s_c = 1/\tau$ is the cutoff frequency and $\tau = RC$ is the time constant.
 - -6.2: Find the eigenvalues of the 2×2 ABCD matrix. Hint: See Appendix B.3.
- -6.3: Assuming that $I_2 = 0$, find the transfer function $H(s) \equiv V_2/V_1$. From the results of the ABCD matrix you determined in questions 6.1 and 6.2, show that

$$H(s) = \frac{s_c}{s + s_c}.$$
 (DE-2.6)

- -6.4: The transfer function H(s) has one pole. Where is the pole and residue?
- -6.5: Find h(t), the inverse Laplace transform of H(s).
- -6.6: Assuming that $V_2 = 0$, find $Y_{12}(s) \equiv I_2/V_1$.
- -6.7: Find the input impedance to the right-hand side of the system $Z_{22}(s) \equiv V_2/I_2$ for two cases: (1) $I_1 = 0$ and (2) $V_1 = 0$.
 - -6.8: Compute the determinant of the ABCD matrix. Hint: It is always ± 1 .
- -6.9: Given the result of the previous problem Eq. DE-2.6, compute the derivative of $H(s) = \frac{V_2}{V_1}\Big|_{I_2=0}$.

4.6.6 Computer Exercises with Matlab/Octave

Problem #7 With the help of a computer

Now we look at a few important concepts using Matlab/Octave's syms commands or Wolfram Alpha's symbolic math toolbox.¹¹

For example, to find the Taylor series expansion about s = 0 of

$$F(s) = -\log(1-s).$$

we first consider the derivative and its Taylor series (about s = 0)

$$F'(s) = \frac{1}{1-s} = \sum_{n=0}^{\infty} s^n.$$

Then, we integrate this series term by term:

$$F(s) = -\log(1-s) = \int_{s}^{s} F'(s)ds = \sum_{n=0}^{\infty} \frac{s^n}{n}.$$

Alternatively we can use Matlab/Octave commands:

syms s

¹¹ https://www.wolframalpha.com/.

4.6 Problems DE-2 213

```
taylor(-log(1-s), 'order', 7)
```

-7.1: Use Octave's taylor $(-\log(1-s))$ to the seventh order, as in the example above.

- Try the above Matlab/Octave commands. Give the first seven terms of the Taylor series (confirm that Matlab/Octave agrees with the formula derived above).
- What is the inverse Laplace transform of this series? Consider the series term by term.
- -7.2: The function $1/\sqrt{z}$ has a branch point at z=0; thus it is singular there.
 - 1. Can you apply Cauchy's integral theorem when integrating around the unit circle?
- 2. This Matlab/Octave code computes $\int_0^{4\pi} \frac{dz}{\sqrt{z}}$ using Matlab's/Octave's symbolic analysis package:

```
syms z
I=int(1/sqrt(z))
J = int(1/sqrt(z),exp(-j*pi),exp(j*pi))
eval(J)
```

Run this script. What answers do you get for I and J?

- 3. Modify this code to integrate $f(z) = 1/z^2$ once around the unit circle. What answers do you get for I and J?
- -7.3: Bessel functions can describe waves in a cylindrical geometry. The Bessel function has a Laplace transform with a branch cut

$$J_0(t)u(t) \leftrightarrow \frac{1}{\sqrt{1+s^2}}.$$

Draw a hand sketch showing the nature of the branch cut. Hint: Use zviz.

-7.4: Try the following Matlab/Octave commands, and then comment on your findings.

```
%Take the inverse LT of 1/sqrt(1+s^2)
syms s
I=ilaplace(1/(sqrt((1+s^2))));
disp(I)

%Find the Taylor series of the LT
T = taylor(1/sqrt(1+s^2),10); disp(T);
```

```
%Verify this
syms t
J=laplace(besselj(0,t));
disp(J);

%plot the Bessel function
t=0:0.1:10*pi;
b=besselj(0,t);
plot(t/pi,b);
grid on;
```

- *–7.5:* When did Friedrich Bessel live?
- -7.6: What did he use Bessel functions for?
- -7.7: Use zviz for each of the following:

- 1. Describe the plot generated by zviz S=Z.
- 2. Are the functions that follow legal Brune impedances? [Do they obey $\Re Z(\sigma > 0) \ge 0$?] Hint: Consider the phase (color). Plot zviz Z for a reminder of the color map.
- 1. zviz 1./sqrt(1+S.^2)
- 2. zviz 1./sqrt(1-S.^2)
- 3. zviz 1./(1+sqrt(S))

4.6.7 Inverse of Riemann $\zeta(s)$ Function

Problem #8 *Inverse zeta function (This problem is for extra credit).*

-8.1: Find the LT⁻¹ of one factor of the Riemann zeta function $\zeta_p(s)$, where $\zeta_p(s) \leftrightarrow z_p(t)$. Describe your results in words. Hint: See Eq. AE-1.7. Hint: Consider the geometric series representation

$$\zeta_p(s) = \frac{1}{1 - e^{-sT_p}} = \sum_{k=0}^{\infty} e^{-skT_p},$$
(DE-2.7)

for which you can look up the LT^{-1} of each term.

Problem #9 *Inverse transform of products:*

The time-domain version of Eq. DE-2.7 may be written as the convolution of all the $z_k(t)$ factors:

$$z(t) \equiv z_2(t) \star z_3(t) \star z_5(t) \star z_7(t) \star \cdots \star z_p(t) \star \cdots,$$
 (DE-2.8)

where \star represents time convolution.

Explain what this means in physical terms. Start with two terms (e.g., $z_1(t) \star z_2$). Hint: The input admittance of this cascade may be interpreted as the analytic continuation $of \zeta(s)$ by defining a cascade of eigenfunctions with eigenvalues derived from the primes. For a discussion of this idea see Sects. 3.2.3 and C.1.1.

Physical interpretation: Such functions may be generated in the time domain, as shown in Fig. 4.7, using a feedback delay of T_p seconds, described by the two equations in the Fig. 4.7 with a unity feedback gain $\alpha = -1$. Taking the Laplace transform of the system equation, we see that the transfer function between the state variable q(t) and the input x(t) is given by $\zeta_p(s)$, which is an all-pole function, since

$$Q(s) = e^{-sT_n}Q(s) + V(s), \text{ or } \zeta_p(s) \equiv \frac{Q(s)}{V(s)} = \frac{1}{1 - e^{-sT_p}}.$$
 (DE-2.9)

Closing the feed-forward path gives a second transfer function Y(s) = I(s)/V(s)—namely,

4.6 Problems DE-2 215




Fig. 4.7 This feedback network, described by a time-domain difference equation with delay T_p , has an all-pole transfer function $\zeta_p(s) \equiv Q(s)/I(s)$ given by Eq. DE-2.9, which physically corresponds to a stub of a transmission line, with the input at one end and the output at the other. To describe the $\zeta(s)$ function we must take $\alpha = -1$. A transfer function Y(s) = V(s)/I(s) that has the same poles as $\zeta_p(s)$, but with zeros as given by Eq. DE-2.11, is the input admittance Y(s) = I(s)/V(s) of the transmission line, defined as the ratio of the Laplace transform of the current $i(t) \leftrightarrow I(s)$ to the voltage $v(t) \leftrightarrow V(s)$

$$Y(s) \equiv \frac{I(s)}{V(s)} = \frac{1 - e^{-sT_p}}{1 + e^{-sT_p}}.$$
 (DE-2.10)

If we take i(t) as the current and v(t) as the voltage at the input to the transmission line, then $y_p(t) \leftrightarrow \zeta_p(s)$ represents the input impedance at the input to the line. The poles and zeros of the impedance interleave along the $j\omega$ axis. By a slight modification, $\zeta_p(s)$ may alternatively be written as

$$Y_p(s) = \frac{e^{sT_p/2} + e^{-sT_p/2}}{e^{sT_p/2} - e^{-sT_p/2}} = j \tan(sT_p/2).$$
 (DE-2.11)

Every impedance Z(s) has a corresponding *reflectance* function given by a Möbius transformation, which may be read off of Eq. DE-2.11 as

$$\Gamma(s) \equiv \frac{1 + Z(s)}{1 - Z(s)} = e^{-sT_p},$$
(DE-2.12)

since impedance is also related to the round-trip delay T_p on the line. The inverse Laplace transform of $\Gamma(s)$ is the round-trip delay T_p on the line

$$\gamma(t) = \delta(t - T_p) \leftrightarrow e^{-sT_p}.$$
 (DE-2.13)

Working in the time domain provides a key insight, as it allows us to parse out the best analytic continuation of the infinity of possible continuations that are not obvious in the frequency domain (See Sect. 3.2.3). Transforming to the time domain is a form of analytic continuation of $\zeta(s)$ that depends on the assumption that $\operatorname{Zeta}(t) \leftrightarrow \zeta(s)$ is one-sided in time (causal).

4.6.8 Quadratic Forms

A matrix that has positive eigenvalues is said to be positive-definite. The eigenvalues are real if the matrix is symmetric, so this is a necessary condition for the matrix to be positive-definite. This condition is related to conservation of energy, since the power is the voltage times the current. Given an impedance matrix

$$\mathbf{V} = z\mathbf{I}$$
.

the power \mathcal{P} is

$$\mathcal{P} = \mathbf{I} \cdot \mathbf{V} = \mathbf{I} \cdot \mathbf{Z} \mathbf{I},$$

which must be positive-definite for the system to obey conservation of energy.

Problem #10 In this problem, consider the 2×2 impedance matrix

$$Z = \begin{bmatrix} 2 & 1 \\ 1 & 4 \end{bmatrix}.$$

-10.1: Solve for the power $\mathcal{P}(i_1, i_2)$ by multiplying out this matrix equation (which is a quadratic form):

$$\mathcal{P}(i_1, i_2) = \mathbf{I}^T \begin{bmatrix} 2 & 1 \\ 1 & 4 \end{bmatrix} \mathbf{I}.$$

- -10.2: Is the impedance matrix positive-definite? Show your work by finding the eigenvalues of the matrix **Z**.
 - -10.3: Should an impedance matrix always be positive-definite? Explain.

4.7 The Laplace Transform and Its Inverse

The Laplace transforms $\not\in \mathcal{F}$ take causal time functions into the complex analytic frequency domain s. The inverse Laplace transform $\mathcal{L}\mathcal{T}^{-1}$ (Eq. 3.10.1) transforms a function of complex frequency F(s) and returns a causal function of time f(t),

$$f(t)u(t) \leftrightarrow F(s)$$
,

where u(t) = 0 for t < 0. Examples are provided in Sect. 3.10, Table 3.9. The forward transform is typically a relatively simple set of integrals to find F(s). However the inverse transform is the key to understanding this powerful tool. Here we discuss the details of finding the inverse transform by using CT-3, and we see how the causal requirement f(t < 0) = 0 comes about.

As shown in Fig. 4.8, the integrand of the inverse transform is $F(s)e^{st}$ and the limits of integration are $\sigma_o \mp \omega_J$ with $\sigma_o > 0$. To find the inverse using CT-3 we must close the curve at $\omega \to \infty$, and specify that the integral converges. There are two ways to close the integral: to the right $\sigma > 0$ (RHP), and to the left $\sigma \leq 0$ (LHP). But there must be some logical reason for this choice. That logic is determined by the sign of t. For the integral to converge, the term $|e^{st}| = e^{\sigma t}$ must go to zero as $\omega \to \infty$. Note that both t and ω go to ∞ . Thus it is the interaction between these two limits that determines how we pick the closure, RHP or LHP.




Fig. 4.8 When computing the LT^{-1} we must take advantage of the powerful Cauchy residue integral theorem (CT-3). To use CT-3 we must close the integral at $s \to \infty$. Furthermore this closure integral must go to zero as $\{t, \sigma\} \to \infty$. For t < 0, the convergence of the residue $e^{-\sigma t}$ depends on $\sigma t < 0$, since the product st must have a negative real part. For convergence for t < 0, $\sigma > 0$ so that $\sigma t < 0$. Thus the integral must be close in the RHP. Likewise, for t > 0, $\sigma < 0$, so that $\sigma t < 0$. Thus the integral must be close in the LHP. Following these guidelines based on CT-3, poles in the LHP lead to causal stable solutions, since there $\sigma < 0$ and $t \to \infty$, while poles in the RHP will lead to causal unstable solutions, each the form $e^{\sigma t}u(t)$

4.7.1 Case for Negative Time (t < 0) and Causality

Let us first consider negative time, including $t \to -\infty$. If we were to close $\mathcal C$ in the LHP ($\sigma < 0$), then the product σt is positive ($\sigma < 0$, t < 0, thus $\sigma t > 0$). In this case, as $\omega \to \infty$, the closure integral $|s| \to \infty$ will diverge. If we close in the RHP ($\sigma > 0$), then the product $\sigma t < 0$ and e^{st} will go to zero as $\omega \to \infty$. Thus we may not close in the LHP for negative time. This then justifies closing the contour, allowing for the use of Cauchy CT-3.

4.7.2 Case for Zero Time (t = 0)

When the time is zero, the integral does not, in general, converge, which leaves f(t) undefined. This is most obvious in the case of the step function $u(t) \leftrightarrow 1/s$, where the integral may not be closed because the convergence factor $e^{st} = 1$ fails for t = 0.

The fact that u(t) does not exist at t=0 helps to explain the Gibbs phenomenon in the inverse Fourier transform. At the time where a jump occurs, the derivative of the function does not exist, and thus the time response function is not analytic. The Fourier expansion does not point-wise converge where the function is not analytic. A low-pass filter may be used to smooth the function, but at the cost of temporal resolution.

4.7.3 Case for Positive Time (t > 0)

Next we investigate the convergence of the integral for positive time t>0. In this case we must close the integral in the LHP ($\sigma<0$) for convergence, so that st<0 ($\sigma\leq0$ and t>0). When there are poles on the $\omega J=0$ axis, $\sigma_o>0$ assures convergence by keeping the on-axis poles inside the contour. At this point, CT-3 is relevant. If we restrict ourselves to simple poles (as required for a Brune impedance), the residue theorem may be directly applied.

Unstable poles: An important but subtle point arises: If F(s) has a pole in the RHP, then the above argument still applies if we pick σ_o to be to the right of the RHP pole. This means that the inverse transform may still be applied to unstable poles (those in the RHP). This then explains the need for the σ_o in the limits. If F(s) has no RHP poles in the extended RHP ($\sigma \ge 0$), we may take $\sigma_o = 0$.

The simplest example is the step function, for which F(s) = 1/s, thus

$$u(t) = \oint_{I \text{ HP}} \frac{e^{st}}{s} \frac{ds}{2\pi I} \leftrightarrow \frac{1}{s},$$

which is a direct application of CT-3. The forward transform of u(t) is straightforward, as discussed in Appendix D. This is true of most of the elementary forward Laplace transforms. In these cases, causality may be built into the integral by the limits. An interesting problem is how to prove that u(t) is not defined at t = 0.

The inverse Laplace transform of F(s) = 1/(s+1) has a residue of 1 at s=-1, thus that is the only contribution to the integral. More demanding cases are Laplace transform pairs

$$\frac{1}{\sqrt{t}}u(t) \leftrightarrow \sqrt{\frac{\pi}{s}} \text{ and } J_o(t)u(t) \leftrightarrow \frac{1}{\sqrt{s^2+1}},$$

as shown in Fig. 4.9 (right), and more in Table C.2. Many of these are easily proved in the forward direction but are much more difficult in the inverse direction due to the properties at t = 0, unless CT-3 is invoked.

Along the *x*-axis of Fig. 4.9, $\cos(\pi x)$ is periodic with a period of π . The dark spots are at the zeros at $\pm \pi/2$, $\pm 3\pi/2$, Along the jy-axis, the function goes to either zero (black) or ∞ (white). This behavior carries the same π periodicity as on the x=0 line.




Fig. 4.9 Left: Colorized plot of w(z) = sin(z). Right: Colorized plot of $w(z) = J_o(\pi z)$. Note the similarity of the two functions. The first Bessel zero is at 2.405 and thus appears at 0.7655 = $2.405/\pi$, about 1.53 times larger than the root of $\cos(\pi z)$ at 1/2. Other than this minor distortion of the first few roots, the two functions are basically identical. It follows that their $\mathcal{L}T$ s must have similar characteristics, as documented in Table C.2. These colorized plots show that these two functions become the same for $x = \Re z > 0$. The black lines indicate where the function has a constant real part




Fig. 4.10 Left: The Bessel function $J_0(\pi z)$, which is similar to $\cos(\pi z)$, except the zeros are distorted away from s=0 by a small amount, due to the cylindrical geometry. Right: The related Hankel function $H_0^{(1)}(\pi z/2)$. The Hankel function $H_0^{(1)}(\pi z/2)$ has a branch cut and a complex zero at $z_{0,1}2/\pi=-1.5-0.1_J$, as may be seen in the plot

The last $\mathcal{L}T$ example of Fig. 4.10 gives an important insight into the properties of the Hankel function $H_0^{(1)}(\pi z/2)$, which has a branch cut along the negative real axis. On the right is the Hankel function $H_0^{(1)}(\pi z/2)$, which is a mixed and distorted version of $\cos(\pi z)$ with the zeros pushed downward, and $e^{\pi z}$. Note how the white and black contour lines of the colorized maps are always perpendicular where they cross.

4.7.4 Properties of the LT

As shown in Table 3.8 of Laplace transforms, there are integral (i.e., integration, not integer) relationships, or properties, that are helpful to identify. The first of these is a definition, not a property:

$$f(t) \leftrightarrow F(s)$$
.

Causality: When we take the LT, the time-domain response is in lowercase (e.g., f(t)) and the frequency-domain transform is in uppercase (e.g., F(s)). It is required, but not always explicitly specified, that f(t < 0) = 0; that is, the time function must be causal, as stated by Postulate P1 (Sect. 3.10.2).

Linearity: The most basic property is the linearity (superposition) property of the LT, stated by Postulate P2 (Sect. 3.10.2).

Convolution property: The product of two $\mathcal{LT}s$ in frequency results in convolution in time:

$$F(s)G(s) \leftrightarrow f(t) \star g(t) = \int_0^t f(\tau)g(t-\tau)d\tau,$$

where we use \star to indicate the convolution of two time functions.

A key application of convolution is filtering, which takes many forms. The most basic filter is the moving average, the moving sum of data samples, normalized by the number of samples. Such a filter has very poor performance. It also introduces a delay of half the length of the average, which may or may not constitute a problem, depending on the application. Other important examples are a low-pass filter that removes high-frequency noise and a notch filter that removes line noise (i.e., 60 [Hz] in the United States, and its second and third harmonics, 120 and 180 [Hz]). Such noise is typically a result of poor grounding and ground loops. It is better to solve the problem at its root than to remove it with a notch filter. Still, filters are very important in engineering.

By taking the LT of the convolution we can derive this relationship:

$$\int_0^\infty [f(t) \star g(t)] e^{-st} dt = \int_{t=0}^\infty \left[\int_0^t f(\tau) g(t-\tau) d\tau \right] e^{-st} dt$$

$$= \int_0^t f(\tau) \left(\int_{t=0}^\infty g(t-\tau) e^{-st} dt \right) d\tau$$

$$= \int_0^t f(\tau) \left(e^{-s\tau} \int_{t'=0}^\infty g(t') e^{-st'} dt' \right) d\tau$$

$$= G(s) \int_0^t f(\tau) e^{-s\tau} d\tau$$

$$= G(s) F(s).$$

We first encountered this relationship in Sect. 3.4 in the context of multiplying polynomials, which is the same as convolving their coefficients. The parallel should be obvious. In the case of polynomials, the convolution is discrete in the coefficients, and here it is continuous in time. But the relationships are the same.

Time-shift property: When a function is time-shifted by time T_o , the $\mathcal{L}\mathcal{T}$ is modified by e^{-sT_o} , leading to the property

$$f(t-T_o) \leftrightarrow e^{-sT_o} F(s).$$

This is easily shown by applying the definition of the LT to a delayed time function.

Time derivative: The key to the eigenfunction analysis provided by the \mathcal{LT} is the transformation of a time derivative on a time function—that is,

$$\frac{d}{dt}f(t) \leftrightarrow sF(s).$$

Here s is the eigenvalue corresponding to the time derivative of e^{st} . Given the definition of the derivative of e^{st} with respect to time, this definition seems trivial. Yet that definition was not obvious to Euler. It needed to be extended to the space of the complex analytic function e^{st} , which did not happen before Cauchy's key results.

Given a differential equation of order K, the $\mathcal{L}T$ results in a polynomial in s of degree K. It follows that this $\mathcal{L}T$ property is the cornerstone of why the $\mathcal{L}T$ is so important to scalar differential equations, as it was to the early analysis of Pell's equation and the Fibonacci sequence, presented in Chap. 2. While the relation $e^{J\theta} = \cos\theta + J\sin\theta$ was first uncovered by Euler. By the time of his death the formula's significance would have been clear to him. Who first coined the terms eigenvalue and eigenfunction? The word eigen is a German word meaning of one.

Initial and final value theorems: There are much more subtle relationships between f(t) and F(s) that characterize $f(0^+)$ and $f(t \to \infty)$, which are known as initial value theorems. If the system under investigation has potential energy at t = 0, then the voltage (velocity) need not be zero for negative time. An example is a charged capacitor or a moving mass. These are important concepts, but best explored in a more in-depth treatment. They are not violations of causality.

4.7.5 Solving Differential Equations

Many differential equations may be solved by assuming a power series (i.e., Taylor series) solution of the form

$$y(x) = x^r \sum_{n=0}^{\infty} c_n x^n,$$
 (4.7.1)

with $r \in \mathbb{Z}$ and coefficients $c_n \in \mathbb{C}$. This method of Frobenius is quite general (Greenberg 1988, p. 193).

Example: When a solution of this form is substituted into the differential equation, a recursion relationship in the coefficients results. For example, if the equation is

$$y''(x) = \lambda^2 y(x),$$

the recursion is $c_n = c_{n-1}/n$. The resulting equation is

$$y(x) = e^{\lambda x} = x^0 \sum_{n=0}^{\infty} \frac{1}{n!} x^n,$$

namely, $c_n = 1/n!$, thus $nc_n = 1/(n-1)! = c_{n-1}$.

Exercise #3 Find the recursion relationship for $y(x) = J_{\nu}(x)$ of order ν that satisfies Bessel's equation

 $x^{2}y''(x) + xy'(x) + (x^{2} - \nu^{2})y(x) = 0.$

Solution: If we assume a complex analytic solution of the form of Eq. 4.7.1, we find the Bessel recursion relationship for coefficients c_k (Greenberg 1988, p. 231):

$$c_k = -\frac{1}{k(k+2\nu)}c_{k-2}.$$

4.8 Problems DE-3

4.8.1 Topics of This Homework: Brune Impedance

lattice transmission line analysis

4.8.2 Brune Impedance

Problem #1 Residue form

A Brune impedance is defined as the ratio of the force F(s) to the flow V(s) and may be expressed in residue form as

$$Z(s) = c_0 + \sum_{k=1}^{K} \frac{c_k}{s - s_k} = \frac{N(s)}{D(s)}$$
 (DE-3.1)

with

$$D(s) = \prod_{k=1}^{K} (s - s_k) \text{ and } c_k = \lim_{s \to s_k} (s - s_k) D(s) = \prod_{n'=1}^{K-1} (s - s_n).$$

The prime on the index n' means that n = k is not included in the product.

- -1.1: Find the Laplace transform (LT) of a (1) spring, (2) dashpot, and (3) mass. Express these in terms of the force F(s) and the velocity V(s), along with the electrical equivalent impedance: (1) Hooke's law f(t) = Kx(t), (2) dashpot resistance f(t) = Rv(t), and (3) Newton's law for mass f(t) = Mdv(t)/dt.
- -1.2: Take the Laplace transform (LT) of Eq. DE-3.2 and find the total impedance Z(s) of the mechanical circuit.

$$M\frac{d^2}{dt^2}x(t) + R\frac{d}{dt}x(t) + Kx(t) = f(t) \Leftrightarrow (Ms^2 + Rs + K)X(s) = F(s).$$
(DE-3.2)

-1.3: What are N(s) and D(s) (see Eq. DE-3.1)?

-1.4: Assume that M=R=K=1 and find the residue form of the admittance Y(s)=1/Z(s) (see Eq. DE-3.1) in terms of the roots s_{\pm} . Hint: Check your answer with Octave's/Matlab's residue command.

-1.5: By applying Eq. 4.5.3, find the inverse Laplace transform (LT⁻¹). Use the residue form of the expression that you derived in question #1.

4.8.3 Transmission Line Analysis

Problem #2 Train-mission-line We wish to model the dynamics of a freight train that has N such cars and study the velocity transfer function under various load conditions.

As shown in Fig. 4.11, the train model consists of masses connected by springs. Use the ABCD method (see the discussion in Appendix B.3) to find the matrix representation of the system of Fig. 4.11. Define the force on the *n*th train car $f_n(t) \leftrightarrow F_n(\omega)$ and the velocity $v_n(t) \leftrightarrow V_n(\omega)$.

Break the model into cells consisting of three elements: a series inductor representing half the mass (M/2), a shunt capacitor representing the spring (C=1/K), and another series inductor representing half the mass (L=M/2), transforming the model into a cascade of symmetric $(\mathcal{A}=\mathcal{D})$ identical cell matrices $\mathcal{T}(s)$.




Fig. 4.11 Depiction of a train consisting of cars treated as masses M and linkages treated as springs of stiffness K or compliance C = 1/K. Below it is the electrical equivalent circuit for comparison. The masses are modeled as inductors and the springs as capacitors to ground. The velocity is analogous to a current and the force $f_n(t)$ to the voltage $\phi_n(t)$. The length of each cell is Δ [m]. The train may be accurately modeled as a transmission line (TL), since the equivalent electrical circuit is a lumped model of a TL. This method, called a *Cauer synthesis*, is based on the ABCD transmission line method of Sect. 3.8

4.8 Problems DE-3 225

-2.1: Find the elements of the ABCD matrix \mathcal{T} for the single cell that relate the input node 1 to output node 2]

$$\begin{bmatrix} F \\ V \end{bmatrix}_{1} = \mathcal{T} \begin{bmatrix} F(\omega) \\ -V(\omega) \end{bmatrix}_{2}.$$
 (DE-3.3)

-2.2: Express each element of T(s) in terms of the complex Nyquist ratio $s/s_c < 1$ ($s = 2\pi j f$, $s_c = 2\pi j f_c$). The Nyquist wavelength sampling condition is $\lambda_c > 2\Delta$. It says the critical wavelength $\lambda_c > 2\Delta$. Namely it is defined in terms the minimum number of cells 2Δ , per minimum wavelength λ_c .

The Nyquist wavelength sampling theorem says that there are at least two cars per wavelength.

Proof: From the figure, the distance between cars $\Delta = c_o T_o$ [m], where

$$c_o = \frac{1}{\sqrt{MC}} \quad [m/s].$$

The cutoff frequency obeys $f_c \lambda_c = c_o$. The Nyquist critical wavelength is $\lambda_c = c_o/f_c > 2\Delta$. Therefore the Nyquist sampling condition is

$$f < f_c \equiv \frac{c_o}{\lambda_c} = \frac{c_o}{2\Delta} = \frac{1}{2\Delta\sqrt{MC}}$$
 [Hz]. (DE-3.4)

Finally, $s_c = j2\pi f_c$.

-2.3: Use the property of the Nyquist sampling frequency $\omega < \omega_c$ (Eq. DE-3.4) to remove higher order powers of frequency

$$1 + \left(\frac{s}{s_c}\right)^0 \approx 1$$
 (DE-3.5)

to determine a band-limited approximation of $\mathcal{T}(s)$.

Problem #3 Now consider the cascade of N such T(s) matrices and perform an eigenanalysis.

-3.1: Find the eigenvalues and eigenvectors of T(s) as functions of s/s_c .

Problem #4 Find the velocity transferfunction $H_{12}(s) = V_2/V_1|_{F_2=0}$.

-4.1: Assuming that N=2 and $F_2=0$ (two half-mass problem), find the transfer function $H(s) \equiv V_2/V_1$. From the results of the \mathcal{T} matrix, find]

$$H_{21}(s) = \left. \frac{V_2}{V_1} \right|_{F_2 = 0}$$

Express H_{12} in terms of a residue expansion.

-4.2: Find $h_{21}(t) \leftrightarrow H_{21}(s)$.

- -4.3: What is the input impedance $Z_2 = F_2/V_2$, assuming $F_3 = -r_0V_3$?
- -4.4: Simplify the expression for \mathbb{Z}_2 as follows:
- 1. Assuming the *characteristic impedance* $r_0 = \sqrt{M/C}$,
- 2. terminate the system in r_0 : $F_2 = -r_0V_2$ (i.e., $-V_2$ cancels).
- 3. Assume higher order frequency terms are less than 1 ($|s/s_c| < 1$).
- 4. Let the number of cells $N \to \infty$. Thus $|s/s_c|^N = 0$.

When a transmission line is terminated in its characteristic impedance r_0 , the input impedance $Z_1(s) = r_0$. Thus, when we simplify the expression for $\mathcal{T}(s)$, it should be equal to r_0 . Show that this is true for this setup.

- -4.5: State the ABCD matrix relationship between the first and Nth nodes in terms of the cell matrix. Write out the transfer function for one cell, H_{21} .
 - -4.6: What is the velocity transfer function $H_{N1} = \frac{V_N}{V_1}$?

Appendix A Notation

A.1 Number Systems

The notation used in this book is defined in this appendix so that it may be quickly accessed. Where the definition is sketchy, page numbers are provided where these concepts are fully explained, along with many other important and useful definitions. For example, a discussion of \mathbb{N} may be found on Sect. 2.1. Math symbols such as \mathbb{N} may be found at the top of the index, since they are difficult to alphabetize.

A.1.1 Units

Strangely, or not, classical mathematics, as taught today in schools, does not seem to acknowledge the concept of physical units. Units seem to have been abstracted away. This makes mathematics distinct from physics, where almost everything has units. Presumably this makes mathematics more general (i.e., abstract). But for the engineering mind, this is not ideal, or worse, as it necessarily means that important physical meaning, by design, has been surgically removed. We shall use SI units whenever possible, which means this book is not a typical book on mathematics. Spatial coordinates are quoted in meters [m], and time in seconds [s]. Angles in degrees have no units, whereas radians have units of inverse-seconds [s⁻¹]. A complete list of SI units may be found at https://physics.nist.gov/cuu/pdf/sp811.pdf and Graham et al. (1994) for a discussion of basic math notation.

When writing a complex number we shall adopt 1_J to indicate $\sqrt{-1}$. MAT-LAB/Octave allows either 1_I or 1_J .

Units are SI; angles are in degrees [deg] unless otherwise noted. The units for π are always radians [rad]. For example $\sin(\pi)$, $e^{J^{90^{\circ}}} = e^{J^{\pi/2}}$.

¹https://en.wikipedia.org/wiki/List_of_mathematical_symbols_by_subject#Definition_symbols.

[©] Springer Nature Switzerland AG 2020

²⁹¹

A.1.2 Symbols and Functions

We use ln as the log function base e, log as base 2, and π_k to indicate the kth prime (e.g., $\pi_1 = 2, \pi_2 = 3$).

It is helpful to know where the letters of the alphabet are. Everyone knows the first letter is /a/ and the last /z/, but what is the 10th or 20th letter? The table below shows that /j/ is the 10th letter, /t/ the 20th, /o/ the 15th, and /z/ the 26th.

index:	1	10	20	+1
+0	a	j	t	_
+5	e	0	у	Z

This is helpful for quickly moving around the alphabet, when looking up words in the dictionary or an alphabetized list. If you forget how many letters there are in the English alphabet, this will help you recall it is 26.

When working with Fourier $\mathcal{F}\mathcal{T}$ and Laplace $\mathcal{L}\mathcal{T}$ transforms, lowercase symbols are in the time domain while uppercase indicates the frequency domain, as $f(t) \leftrightarrow F(\omega)$. An important exception is Maxwell's equations because they are so widely used as uppercase bold letters (e.g., $E(x, \omega)$). It would seem logical to change this to $e(x, t) \leftrightarrow E(x, \omega)$, to conform.

A.1.3 Common Mathematical Symbols

There are many pre-defined symbols in mathematics, too many to summarize here. We shall only use a small subset, defined here.

- \forall set is a collection of objects that have a common property, defined by braces. Ed: A For example, if set $P = \{a, b, c\}$ such that $a^2 + b^2 = c^2$, then members of P obey the Pythagorean theorem. Thus we could say that $\{1, 1, \sqrt{2}\} \in P$.
- Number sets: \mathbb{N} , \mathbb{P} , \mathbb{Z} , \mathbb{Q} , \mathbb{F} , \mathbb{I} , \mathbb{R} , \mathbb{C} are briefly discussed below, and in greater detail in Sect. 2.1.
- One can define sets of sets and subsets of sets, and this is prone (in my experience) to error. For example, what is the difference between the number 0 and the null set Ø = {0}? Is 0 ∈ Ø? Ask a mathematician. This seems a lackluster construction in the world of engineering.
- A vector is a column n-tuple. For example $[3, 5]^T = \begin{bmatrix} 3 \\ 5 \end{bmatrix}$.
- The symbol \perp is used in different ways to indicate two things are perpendicular, orthogonal, or in disjoint sets. In set theory $A \perp B$ is equivalent to $A \cap B = \emptyset$. If two vectors E, H are perpendicular $E \perp H$, then their inner product $E \cdot H = 0$ is zero. One must infer the meaning of \perp from its context.

^{*} The symbol \$\forall\$ is read as ``for all."

Appendix A: Notation 293

A	A	α	alpha	N	N	ν	nu
В	В	β	beta	Ξ	Ξ	ξ	xi
Γ	Γ	γ	gamma	О	О	О	omicron
Δ	<u>\(\sigma \) \(\lambda \) \(\lambda \) \(\lambda \)</u>	δ	delta	П	П	π	pi
Е	E	ε	epsilon	P	P	ρ	rho
Z	Z	ζ	zeta	Σ	Σ	σ	sigma
Н	Н	η	eta	T	Т	τ	tau
Θ	Θ	θ	theta	Υ	Υ	v	upsilon
I	I	ι	iota	Φ	Φ	ϕ	phi
K	K	κ	kappa	X	X	χ	chi
Λ	Λ	λ	lambda	Ψ	Ψ	$ \psi $	psi
M	M	μ	mu	Ω	Ω	ω	omega

Table A.1 List of all upper- and lowercase Greek letters used in the text

A.1.3.1 Greek Letters

Frequently Greek letters, as provided in Table A.1, are associated in engineering and physics with a specific physical meaning. For example, ω [rad] is the radian frequency $2\pi f$, ρ [kgm/m³] is commonly the density. ϕ , ψ are commonly used to indicate angles of a triangle, and $\zeta(s)$ is the Riemann zeta function. Many of these are so well established it makes no sense to define new terms, so we will adopt these common terms (and define them).

Likely you do not know all of these Greek letters, commonly used in mathematics. Some of them are pronounced in strange ways. The symbol ξ is pronounced "see," ζ is "zeta," β is "beta," and χ is "kie" (rhymes with pie and sky). I will assume you know how to pronounce the others, which are more phonetic in English. One advantage of learning LATEX the powerful open-source math-oriented word-processing system used to write this book is that math symbols are included, making then easily learned.

A.1.3.2 Double-Bold Notation

Table A.2 indicates the symbol followed by a page number indication where it is discussed, and the Genus (class) of the number type. For example, $\mathbb{N} > 0$ indicates the infinite set of *counting numbers* $\{1, 2, 3, \cdots \}$, not including zero. Starting from any counting number, you get the next one by adding 1. Counting numbers are sometimes called the natural or cardinal numbers.

We say that a number is in the set with the notation $3 \in \mathbb{N} \subset \mathbb{R}$, which is read as "3 is in the set of counting numbers, which in turn is in the set of real numbers," or in vernacular language "3 is a real counting number."

Prime numbers $(\mathbb{P}\subset\mathbb{N})$ are taken from the counting numbers, but do not include 1.

point, e.g., $j \in C$			
Symbol (Section)	Genus	Examples	Counter examples
N (Sect. 2.1)	Counting	1,2,17,3, 10 ²⁰	$-5, 0, \pi, -10.3, 5j$
P (Sect. 2.1)	Prime	2, 3, 17, 199, 23993	0, 1, 4, 3 ² , 12
\mathbb{Z} (Sect. 2.1)	Integer	-1, 0, 17, 5j, -10 ²⁰	$1/2,\pi,\sqrt{5}$
Q (Sect. 2.1)	Rational	2/1, 3/2, 1.5, 1.14	$\sqrt{2}$, $3^{-1/3}$, π
F (Sect. 2.1)	Fractional	1/2, 7/22	$1/\sqrt{2}$
I (Sect. 2.1)	Irrational	$\sqrt{2}$, $3^{-1/3}$, π , e	Vectors
ℝ (Sect. 2.1)	Reals	$\sqrt{2}$, $3^{-1/3}$, π	$2\pi j$
ℂ (Sect. 2.1)	Complex	$1, \sqrt{2}j, 3^{-j/3}, \pi^j$	Vectors
G	Gaussian integers	$3-2j\in\mathbb{Z}\cup\mathbb{C}$	Complex integers

Table A.2 Double-bold notation for the types of numbers. (#) is a page number. Symbol with an exponent denote the dimensionality. Thus \mathbb{R}^2 represents the real plane. An exponent of 0 denotes point, e.g., $j \in \mathbb{C}^0$

The signed integers $\mathbb Z$ include 0 and negative integers. Rational numbers $\mathbb Q$ are historically defined to include $\mathbb Z$, a somewhat inconvenient definition, since the more interesting class are the *fractionals* $\mathbb F$, a subset of rationals $\mathbb F \in \mathbb Q$ that exclude the integers (i.e., $\mathbb F \perp \mathbb Z$). This is a useful definition because the rationals $\mathbb Q = \mathbb Z \cup \mathbb F$ are formed from the union of integers and fractionals.

The rationals may be defined, using set notation (a very sloppy notation with an incomprehensible syntax), as

$$\mathbb{Q} = \{p/q : q \neq 0 \ \& \ p, q \in \mathbb{Z}\},\$$

which may be read as "the set ' $\{\cdots\}$ ' of all p/q such that ":' $q \neq 0$, 'and' $p, q \in \mathbb{Z}$." The translation of the symbols is in single (' \cdots ') quotes.

Irrational numbers \mathbb{I} are very special: They are formed by taking a limit of fractionals, as the numerator and denominator $\to \infty$, and approach a limit point. It follows that irrational numbers must be approximated by fractionals.

The reals (\mathbb{R}) include complex numbers (\mathbb{C}) having a zero imaginary part (i.e., $\mathbb{R} \subset \mathbb{C}$).

The *size* of a set is denoted by taking the absolute value (e.g., $|\mathbb{N}|$). Normally in mathematics this symbol indicates the cardinality, so we are defining it differently from the standard notation.

A.1.4 Classification of Numbers

From the above definitions there exists a natural hierarchical structure of numbers:

$$\mathbb{P} \subset \mathbb{N}$$
, $\mathbb{Z} : \{\mathbb{N}, 0, -\mathbb{N}\}$, $\mathbb{F} \perp \mathbb{Z}$, $\mathbb{Q} : \mathbb{Z} \cup \mathbb{F}$, $\mathbb{R} : \mathbb{Q} \cup \mathbb{I} \subset \mathbb{C}$

- 1. The primes are a subset of the counting numbers: $\mathbb{P} \subset \mathbb{N}$.
- 2. The signed integers \mathbb{Z} are composed of $\pm \mathbb{N}$ and 0, thus $\mathbb{N} \subset \mathbb{Z}$.
- 3. The fractionals \mathbb{F} do not include of the signed integers \mathbb{Z} .
- 4. The rationals $\mathbb{Q} = \mathbb{Z} \cup \mathbb{F}$ are the union of the signed integers and fractionals.
- 5. Irrational numbers \mathbb{I} have the special properties $\mathbb{I} \perp \mathbb{Q}$.
- 6. The reals $\mathbb{R}: \mathbb{O}$, \mathbb{I} are the union of rationals and *irrationals* \mathbb{I} .
- 7. Reals \mathbb{R} may be defined as a subset of those complex numbers \mathbb{C} having zero imaginary part.

A.1.5 Rounding Schemes

In MATLAB/Octave there are five different rounding schemes (i.e., mappings): $\mathtt{round}(\mathtt{x})$, $\mathtt{fix}(\mathtt{x})$, $\mathtt{floor}(\mathtt{x})$, $\mathtt{ceil}(\mathtt{x})$, $\mathtt{roundb}(\mathtt{x})$, with input $\mathtt{x} \in \mathbb{R}$ and $\mathtt{output}\,k \in \mathbb{N}$. For example $\mathtt{3} = \lfloor \pi \rceil$, $\mathtt{3} = \lfloor e^1 \rceil = \lfloor 2.7183 \rceil$ rounds to the nearest integer, whereas $\mathtt{3} = \mathtt{floor}(\pi)$ rounds down while $\mathtt{3} = \mathtt{ceil}(e^1) = \lceil e^1 \rceil$ rounds up. Rounding schemes are used for quantizing a number and generating a remainder. For example: $\mathtt{y} = \mathtt{rem}(\mathtt{x})$ is equivalent to $\mathtt{y} = \mathtt{x} - \lfloor \mathtt{x} \rceil$. Note $\mathtt{round}(\pi) \equiv \lfloor \pi \rceil$ introduces negative remainders whenever a number rounds up $(\pi = \lceil \pi \rceil - 0.8541)$.

The *continued fraction algorithm* (CFA), Sect. 2.4.4 is a recursive rounding scheme, operating on the reciprocal of the remainder. For example:

$$\exp(1) = 3 + 1/(-4 + 1/(2 + 1/(5 + 1/(-2 + 1/(-7))))) - o(1.75 \times 10^{-6}),$$

= [3; -4, 2, 5, -2, -7] - o(1.75 \times 10^{-6}).

The expressions in square brackets is a notation for the CFA integer coefficients. The Octave/MATLAB function having $x \in \mathbb{R}$ is either rat (x) with output $\in \mathbb{N}$, or rats (x), with output $\in \mathbb{F}$.

A.1.6 Periodic Functions

Fourier series tells us that periodic functions are discrete in frequency, with frequencies given by nT_s , where T_s is the sample period. The discrete $\mathcal{F}\mathcal{T}$ (DFT) is a good example. When using the DFT, the sample period is $T_s = 1/2F_{max}$ and the minimum and maximum frequencies are given by $F_{min} = F_{max}/NFT$, where NFT is the size of the DFT.

This concept is captured by the *Fourier series*, which is a frequency expansion of a periodic function. This concept is quite general. Periodic in frequency implies discrete in time. Periodic and discrete in time requires periodic and discrete in frequency (the case of the DFT). The modulo function $x = \mod(x, y)$ is periodic with period y (x, $y \in \mathbb{R}$).

A periodic function may be conveniently indicated using double-parentheses notation. This is sometimes known as modular arithmetic. For example,

$$f((t))_T = f(t) = f(t \pm kT)$$

is periodic on $t, T \in \mathbb{R}$ with a period of T and $k \in \mathbb{Z}$. This notation is useful when dealing with Fourier series of periodic functions such as $\sin(\theta)$, where $\sin(\theta) = \sin((\theta))_{2\pi} = \mod(\sin(\theta), 2\pi)$.

When a discrete valued (e.g., time $t \in \mathbb{N}$) sequence is periodic with period $N \in \mathbb{Z}$, we use square brackets

$$f[[n]]_N = f[n] = f[n \pm kN],$$

with $k \in \mathbb{Z}$. This notation will be used with discrete-time signals that are periodic, such as the case of the DFT.

It is common for fractions to repeat. For example 1/7 = 0.((142857)) where the double brackets indicates this number repeats. That is 1/7 = 0.142857, 142857, 142857, 142857,

A.2 Differential Equations Versus Polynomials

A polynomial has *degree N* defined by the largest power. A quadratic equation is degree 2, and a cubic has degree 3. We shall indicate a polynomial by the notation

$$P_N(z) = z^N + a_{N-1}z^{N-1} \cdots a_0.$$

It is a good practice to normalize the polynomial so that $a_N = 1$. This will not change the roots, defined by Eq. 3.1.7 (Sect. 3.1.1). The coefficient on z^{N-1} is always the sum of the roots z_n ($a_{N-1} = \sum_{n=1}^{N} z_n$), and a_0 is always their product ($a_0 = \prod_{n=1}^{N} z_n$). Polynomials with $a_N = 1$ are denoted *monic polynomials*. Because that is a mouthful, it is helpful to call $M_N(s) = P_N(s)/a_N$ a monic.

Differential equations have *order* (polynomials have degree). If a second-order differential equation is Laplace transformed (Sect. 3.10), one is left with a degree 2 polynomial. For example,

$$\frac{d^2}{dt^2}y(t) + b\frac{d}{dt}y(t) + cy(t) = \alpha \left(\frac{d}{dt}x(t) + \beta x(t)\right) \Leftrightarrow$$
 (A.2.1)

$$(s^2 + bs + c)Y(s) = \alpha(s + \beta)X(s). \tag{A.2.2}$$

$$\frac{Y(s)}{X(s)} = \alpha \frac{s+\beta}{s^2 + bs + c} \equiv H(s) \leftrightarrow h(t). \tag{A.2.3}$$

As with monics, the lead coefficient must always be 1. The complex variable $s \in \mathbb{C}$ is the *Laplace frequency*.

The ratio of the output Y(s) over the input X(s) is called the system *transfer* function H(s). The coefficient $\alpha \in \mathbb{R}$ is called the gain. The roots of the numerator are called the zeros and those of the denominator, the poles. When H(s) is the ratio of two degree 1 monics, the transfer function is said to be bilinear, since it is linear in both the input and output. In such cases H(s) has only one pole and one zero. The inverse Laplace transform of the transfer function is called the system inpulse response, which describes the system's output signal y(t) for any given input signal x(t), via convolution (i.e., $y(t) = h(t) \star x(t)$).

A.3 Matrix Algebra: Systems

A.3.1 Vectors

Vectors as columns of ordered sets of scalars $\in \mathbb{C}$. When we write them out in text, we typically use row notation, with the *transpose* symbol:

$$[a, b, c]^T = \begin{bmatrix} a \\ b \\ c \end{bmatrix}.$$

This is strictly to save space on the page. The notation for *conjugate transpose* is \dagger , for example

$$\begin{bmatrix} a \\ b \\ c \end{bmatrix}^{\dagger} = \begin{bmatrix} a^* \ b^* \ c^* \end{bmatrix}.$$

The above example is said to be a *three-dimensional* vector because it has three components.

A.3.2 Vector Products

A *scalar product* (aka dot product) is defined to "weight" vector elements before summing them, resulting in a scalar. The transpose of a vector (a *row-vector*) is typically used as a *scale factor* (i.e., weights) on the elements of a vector. For example,

$$\begin{bmatrix} 1 \\ 2 \\ -1 \end{bmatrix} \cdot \begin{bmatrix} 1 \\ 2 \\ 3 \end{bmatrix} = \begin{bmatrix} 1 \\ 2 \\ -1 \end{bmatrix}^T \begin{bmatrix} 1 \\ 2 \\ 3 \end{bmatrix} = \begin{bmatrix} 1 & 2 & -1 \end{bmatrix} \begin{bmatrix} 1 \\ 2 \\ 3 \end{bmatrix} = 1 + 2 \cdot 2 - 3 = 2.$$

A more interesting example is

$$\begin{bmatrix} 1 \\ 2 \\ 4 \end{bmatrix} \cdot \begin{bmatrix} 1 \\ s \\ s^2 \end{bmatrix} = \begin{bmatrix} 1 \\ 2 \\ 4 \end{bmatrix}^T \begin{bmatrix} 1 \\ s \\ s^2 \end{bmatrix} = \begin{bmatrix} 1 & 2 & 4 \end{bmatrix} \begin{bmatrix} 1 \\ s \\ s^2 \end{bmatrix} = 1 + 2s + 4s^2.$$

Polar scalar product: The vector-scalar product in polar coordinates is (Fig. 3.4, Sect. 3.5.1)

$$\mathbf{B} \cdot \mathbf{C} = \|\mathbf{B}\| \|\mathbf{C}\| \cos \theta \in \mathbb{R},$$

where $\cos \theta \in \mathbb{R}$ is called the *direction-cosine* between **B** and **C**.

Polar wedge-product: The vector wedge-product in polar coordinates is (Fig. 3.4, Sect. 3.5.1)

$$\mathbf{B} \wedge \mathbf{C} = \mathbf{J} \| \mathbf{B} \| \| \mathbf{C} \| \sin \theta \in \mathbb{R},$$

where $\sin \theta \in \mathbb{R}$ is therefore the *direction-sine* between **B** and **C**.

Complex polar vector product: From these two polar definitions and $e^{J\theta} = \cos \theta + J \sin \theta$,

$$\mathbf{B} \cdot \mathbf{C} + \mathbf{J} \mathbf{B} \wedge \mathbf{C} = ||\mathbf{B}|| ||\mathbf{C}|| e^{s}$$
.

Hence

$$\|\boldsymbol{B} \cdot \boldsymbol{C}\|^2 + \|\boldsymbol{B} \wedge \boldsymbol{C}\|^2 = \|\|\boldsymbol{B}\|^2 \|\boldsymbol{C}\|^2 \cos^2 \theta \| + \|\|\boldsymbol{B}\|^2 \|\boldsymbol{C}\|^2 \sin^2 \theta \| = \||\boldsymbol{B}||^2 \|\boldsymbol{C}\|^2.$$

This relationship holds true in any vector space, of any number of dimensions, containing vectors \mathbf{B} and \mathbf{C} . In this case $s = \sigma + \omega_J \in \mathbb{C}$ can be the Laplace frequency. Jaynes (1991) has an relevant discussion about this type of vector product.

A.3.3 Norms of Vectors

The norm of a vector is the scalar product of the vector with itself

$$\|A\| = \sqrt{A \cdot A} \ge 0,$$

forming the Euclidean length of the vector.

Euclidean distance between two points in \mathbb{R}^3 : The scalar product of the difference between two vectors $(A - B) \cdot (A - B)$ is the Euclidean distance between the points they define

$$\|\mathbf{A} - \mathbf{B}\| = \sqrt{(a_1 - b_1)^2 + (a_2 - b_2)^2 + (a_3 - b_3)^2}.$$

Triangle inequality

$$\|\mathbf{A} + \mathbf{B}\| = \sqrt{(a_1 + b_1)^2 + (a_2 + b_2)^2 + (a_3 + b_3)^2} \le \|\mathbf{A}\| + \|\mathbf{B}\|.$$

In terms of a right triangle this says the sum of the lengths of the two sides is greater to the length of the hypotenuse, and equal when the triangle degenerates into a line.

Vector cross product: The *vector product* (aka cross product) $A \times B = ||A|| ||B|| \sin \theta$ is defined between the two vectors A and B. In Cartesian coordinates

$$\mathbf{A} \times \mathbf{B} = \det \begin{vmatrix} \hat{\mathbf{x}} & \hat{\mathbf{y}} & \hat{\mathbf{z}} \\ a_1 & a_2 & a_3 \\ b_1 & b_2 & b_3 \end{vmatrix}.$$

The triple product: This is defined between three vectors as

$$\mathbf{A} \cdot (\mathbf{B} \times \mathbf{C}) = \det \begin{vmatrix} a_1 & a_2 & a_3 \\ b_1 & b_2 & b_3 \\ c_1 & c_2 & c_3 \end{vmatrix}.$$

This may be indicated without the use of parentheses, since there can be no other meaningful interpretation. However for clarity, parentheses should be used. The triple product is the volume of the parallelepiped (3D-crystal shape) outlined by the three vectors, as shown in Fig. 3.4 Sect. 3.5.1.

Dialects of vector notation: Physical fields are, by definition, functions of space x [m], and in the most general case, time t[s]. When Laplace transformed, the fields become functions of space and complex frequency (e.g., $E(x,t) \leftrightarrow E(x,s)$). As before, there are several equivalent vector notations. For example, $E(x,t) = \begin{bmatrix} E_x, E_y, E_z \end{bmatrix}^T = E_x(x,t)\hat{\mathbf{x}} + E_y(x,t)\hat{\mathbf{y}} + E_z(x,t)\hat{\mathbf{z}}$ is "in-line," to save space. The same equation may written in "displayed" notation as:

$$\boldsymbol{E}(\boldsymbol{x},t) = \begin{bmatrix} E_x(\boldsymbol{x},t) \\ E_y(\boldsymbol{x},t) \\ E_z(\boldsymbol{x},t) \end{bmatrix} = \begin{bmatrix} E_x \\ E_y \\ E_z \end{bmatrix} (\boldsymbol{x},t) = \begin{bmatrix} E_x, E_y, E_z \end{bmatrix}^T \equiv E_x \hat{\boldsymbol{x}} + E_y \hat{\boldsymbol{y}} + E_z \hat{\boldsymbol{z}}.$$

Note the three notations for vectors, bold font, element-wise columns, element-wise transposed rows and dyadic format. These are all shorthand notations for expressing the vector. Such usage is similar to a dialect in a language.

Complex elements: When the elements are complex $(\in \mathbb{C})$, the transpose is defined as the complex conjugate of the elements. In such complex cases the transpose conjugate may be denoted with a \dagger rather than T

$$\begin{bmatrix} -2J \\ 3J \\ 1 \end{bmatrix}^{\dagger} = \begin{bmatrix} 2J - 3J & 1 \end{bmatrix} \in \mathbb{C}.$$

For this case when the elements are complex, the dot product is a real number

$$\mathbf{a} \cdot \mathbf{b} = \mathbf{a}^{\dagger} \mathbf{b} = \begin{bmatrix} a_1^* \ a_2^* \ a_3^* \end{bmatrix} \begin{bmatrix} b_1 \\ b_2 \\ b_3 \end{bmatrix} = a_1^* b_1 + a_2^* b_2 + a_3^* b_3 \in \mathbb{R}.$$

Norm of a complex vector: The dot product of a vector with itself is called the *norm* of *a*

$$||a|| = \sqrt{a^{\dagger}a} \ge 0.$$

which is always nonnegative.

Such a construction is useful when a and b are related by an impedance matrix

$$V(s) = Z(s)I(s)$$

and we wish to compute the power. For example, the impedance of a mass is ms and a capacitor is 1/sC. When given a system of equations (a mechanical or electrical circuit) one may define an impedance matrix.

Complex power: In this special case, the *complex power* $\mathcal{P}(s) \in \mathbb{R}(s)$ is defined, in the complex frequency domain (s), as

$$\mathcal{P}(s) = \mathbf{I}^{\dagger}(s)\mathbf{V}(s) = \mathbf{I}^{\dagger}(s)\mathbf{Z}(s)\mathbf{I}(s) \leftrightarrow p(t)$$
 [W].

The real part of the complex power must be positive. The imaginary part corresponds to available stored energy.

The case of three dimensions is special, allowing definitions that are not easily defined in more than three dimensions. A vector in \mathbb{R}^3 labels the point having the coordinates of that vector.

A.3.4 Matrices

When working with matrices, the role of the weights and vectors can change, depending on the context. A useful way to view a matrix is as a set of column-vectors, weighted by the elements of the column-vector of weights multiplied from the right. For example,

$$\begin{bmatrix} a_{11} & a_{12} & a_{13} & \cdots & a_{1M} \\ a_{21} & a_{22} & a_{23} & \cdots & a_{2M} \\ & \ddots & & & \\ a_{N1} & a_{N2} & a_{N3} & \cdots & a_{NM} \end{bmatrix} \begin{bmatrix} w_1 \\ w_2 \\ w_3 \\ \vdots \\ w_M \end{bmatrix} = w_1 \begin{bmatrix} a_{11} \\ a_{21} \\ a_{31} \\ \vdots \\ a_{N1} \end{bmatrix} + w_2 \begin{bmatrix} a_{12} \\ a_{22} \\ a_{32} \\ \vdots \\ a_{N2} \end{bmatrix} + \cdots + w_M \begin{bmatrix} a_{1M} \\ a_{2M} \\ a_{3M} \\ \vdots \\ a_{NM} \end{bmatrix},$$

where the weights are $[w_1, w_2, ..., w_M]^T$. Alternatively, the matrix is a set of row vectors of weights, each of which is applied to the column-vector on the right $([w_1, w_2, ..., W_M]^T)$.

The determinant of a matrix is denoted as either det A or simply |A| (as in the absolute value). The inverse of a square matrix is A^{-1} or invA. If |A| = 0, the inverse does not exist. $AA^{-1} = A^{-1}A$.

MATLAB/Octave's notional convention for a row-vector is [a,b,c] and a column-vector is [a;b;c]. A prime on a vector takes the complex conjugate transpose. To suppress the conjugation, place a period before the prime. The argument converts the array into a column-vector, without conjugation. A tacit notation in MATLAB is that *vectors* are columns and the index to a vector is a row vector. MATLAB defines the notation 1:4 as the "row-vector" (Ambaum, 2010; Apte, 2009; Arnold and Rogness, 2019; Batchelor, 1967), which is unfortunate as it leads users to assume that the default vector is a row. This can lead to serious confusion later, as MATLAB's default vector is a column. I have not found the above convention explicitly stated, and it took me years to figure this out for myself.

When writing a complex number we shall adopt 1_J to indicate $\sqrt{-1}$. MAT-LAB/Octave allows either 1_I or 1_J .

Units are SI; angles are in degrees [deg] unless otherwise noted. The units for π are always radians [rad]. For example $\sin(\pi)$, $e^{j90^{\circ}} = e^{j\pi/2}$.

$A.3.5 \quad 2 \times 2$ Complex Matrices

Here are some definitions to learn:

- 1. Scalar: A number— for example, $\{a, b, c, \alpha, \beta, \ldots\} \in \{\mathbb{Z}, \mathbb{Q}, \mathbb{I}, \mathbb{R}, \mathbb{C}\}$
- 2. Vector: A quantity having direction as well as magnitude, often denoted by a bold letter \mathbf{x} , or with an arrow over the top \vec{x} . In matrix notation, this is typically represented as a single row $[x_1, x_2, x_3, \ldots]$ or single column $[x_1, x_2, x_3, \ldots]^T$ (where T indicates the transpose). In this text we will typically use column-vectors. The vector may also be written out using unit vector notation to indicate direction. For example: $\mathbf{x}_{3\times 1} = x_1\hat{\mathbf{x}} + x_2\hat{\mathbf{y}} + x_3\hat{\mathbf{z}} = [x_1, x_2, x_3]^T$, where $\hat{\mathbf{x}}, \hat{\mathbf{y}}, \hat{\mathbf{z}}$ are unit vectors in the x, y, z Cartesian directions (here the vector's subscript 3×1 indicates its dimensions). The type of notation used may depend on the engineering problem you are solving.
- 3. *Matrix:* $A = [\mathbf{a}_1, \mathbf{a}_2, \mathbf{a}_3, \dots, \mathbf{a}_M]_{N \times M} = \{a_{n,m}\}_{N \times M}$ can be a non-square matrix if the number of elements in each of the vectors (N) is not equal to the number of vectors (M). When M = N, the matrix is square. It may be inverted if its determinant $|A| = \prod \lambda_k \neq 0$ (where λ_k are the eigenvalues). In this text we work only with 2×2 and 3×3 square matrices.
- 4. Linear system of equations: $A\mathbf{x} = \mathbf{b}$, where \mathbf{x} and \mathbf{b} are vectors and matrix A is a square.

- (a) *Inverse*: The solution of this system of equations may be found by finding the inverse $\mathbf{x} = A^{-1}\mathbf{b}$.
- (b) *Equivalence*: If two systems of equations $A_0\mathbf{x} = \mathbf{b}_0$ and $A_1\mathbf{x} = \mathbf{b}_1$ have the same solution (i.e., $\mathbf{x} = A_0^{-1}\mathbf{b}_0 = A_1^{-1}\mathbf{b}_1$), they are said to be equivalent.
- (c) Augmented matrix: The first type of augmented matrix is defined by combining the matrix with the right-hand side. For example, given the linear system of equations of the form $A\mathbf{x} = \mathbf{y}$

$$\begin{bmatrix} a & b \\ c & d \end{bmatrix} \begin{bmatrix} x_1 \\ x_2 \end{bmatrix} = \begin{bmatrix} y_1 \\ y_2 \end{bmatrix},$$

the augmented matrix is

$$[A|y] = \begin{bmatrix} a & b & y_1 \\ c & d & y_2 \end{bmatrix}.$$

A second type of augmented matrix may be used for finding the inverse of a matrix (rather than solving a specific instance of linear equations Ax = b). In this case the augmented matrix is

$$[A|I] = \begin{bmatrix} a & b & 1 & 0 \\ c & d & 0 & 1 \end{bmatrix}.$$

Performing Gaussian elimination on this matrix, until the left side becomes the identity matrix, yields A^{-1} . This is because multiplying both sides by A^{-1} gives $A^{-1}A|A^{-1}I = I|A^{-1}$.

5. *Permutation matrix* (*P*): A matrix that is equivalent to the identity matrix, but with scrambled rows (or columns). Such a matrix has the properties $\det(P) = \pm 1$ and $P^2 = I$. For the 2 × 2 case, there is only one permutation matrix:

$$P = \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix} \qquad P^2 = \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix} \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix} = \begin{bmatrix} 1 & 0 \\ 0 & 1 \end{bmatrix}.$$

A permutation matrix P swaps rows or columns of the matrix it operates on. For example, in the 2×2 case, pre-multiplication swaps the rows,

$$PA = \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix} \begin{bmatrix} a & b \\ \alpha & \beta \end{bmatrix} = \begin{bmatrix} \alpha & \beta \\ a & b \end{bmatrix},$$

whereas post-multiplication swaps the columns,

$$AP = \begin{bmatrix} a & b \\ \alpha & \beta \end{bmatrix} \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix} = \begin{bmatrix} b & a \\ \beta & \alpha \end{bmatrix}.$$

For the 3×2 case there are $3 \cdot 2/2 = 3$ such matrices (swap a row with the other 2, then swap the remaining two rows).

6. Gaussian elimination (GE) operations G_k : There are three types of elementary row operations, which may be performed without fundamentally altering a system of equations (e.g., the resulting system of equations is *equivalent*). These operations are (1) swap rows (e.g., using a permutation matrix), (2) scale rows, or (3) perform addition/subtraction of two scaled rows. All such operations can be performed using matrices.

For lack of a better term, we'll describe these as "Gaussian elimination" or "GE" matrices.² We will categorize any matrix that performs only elementary row operations (but any number of them) as a "GE" matrix. Therefore, a cascade of GE matrices is also a GE matrix.

Consider the GE matrix

$$G = \begin{bmatrix} 1 & 0 \\ 1 & -1 \end{bmatrix}.$$

(a) This pre-multiplication scales and subtracts row (1) from (2) and returns it to row (2).

$$GA = \begin{bmatrix} 1 & 0 \\ 1 & -1 \end{bmatrix} \begin{bmatrix} a & b \\ \alpha & \beta \end{bmatrix} = \begin{bmatrix} a & b \\ a - \alpha & b - \beta \end{bmatrix}.$$

The shorthand for this Gaussian elimination operation is $(1) \leftarrow (1)$ and $(2) \leftarrow (1) - (2)$.

(b) Post-multiplication adds and scales columns.

$$AG = \begin{bmatrix} a & b \\ \alpha & \beta \end{bmatrix} \begin{bmatrix} 1 & 0 \\ -1 & 1 \end{bmatrix} = \begin{bmatrix} a - b & b \\ \alpha - \beta & \beta \end{bmatrix}.$$

Here the second column is subtracted from the first, and placed in the first. The second column is untouched. This operation is *not* a Gaussian elimination. Therefore, to put Gaussian elimination operations in matrix form, we form a cascade of pre-multiply matrices.

Here $\det(G) = 1$, $G^2 = I$, which won't always be true if we scale by a number greater than 1. For instance, if $G = \begin{bmatrix} 1 & 0 \\ m & 1 \end{bmatrix}$ (scale and add), then we have $\det(G) = 1$, $G^n = \begin{bmatrix} 1 & 0 \\ n \cdot m & 1 \end{bmatrix}$.

A.3.6 Derivation of the Inverse of a 2×2 Matrix

1. Step 1: To derive (ii) starting from (i), normalize the first column to 1.

²The term "elementary matrix" may also be used to refer to a matrix that performs an elementary row operation. Typically, each elementary matrix differs from the identity matrix by a single row operation. A cascade of elementary matrices could be used to perform Gaussian elimination.

$$\begin{bmatrix} 1 & \frac{b}{a} \\ 1 & \frac{d}{c} \end{bmatrix} \begin{bmatrix} x_1 \\ x_2 \end{bmatrix} = \begin{bmatrix} \frac{1}{a} & 0 \\ 0 & \frac{1}{c} \end{bmatrix} \begin{bmatrix} y_1 \\ y_2 \end{bmatrix}.$$

2. Step 2: Subtract row (1) from row (2): $(2) \leftarrow (2)-(1)$

$$\begin{bmatrix} 1 & \frac{b}{a} \\ 0 & \frac{d}{c} - \frac{b}{a} \end{bmatrix} \begin{bmatrix} x_1 \\ x_2 \end{bmatrix} = \begin{bmatrix} \frac{1}{a} & 0 \\ -\frac{1}{a} & \frac{1}{c} \end{bmatrix} \begin{bmatrix} y_1 \\ y_2 \end{bmatrix}.$$

3. Step 3: Multiply row (2) by ca and express result in terms of the determinate $\Delta = ad - bc$.

$$\begin{bmatrix} 1 & \frac{b}{a} \\ 0 & \Delta \end{bmatrix} \begin{bmatrix} x_1 \\ x_2 \end{bmatrix} = \begin{bmatrix} \frac{1}{a} & 0 \\ -c & a \end{bmatrix} \begin{bmatrix} y_1 \\ y_2 \end{bmatrix}.$$

- 4. Step 4: Solve row (2) for x_2 : $x_2 = -\frac{c}{\Lambda}y_1 + \frac{a}{\Lambda}y_2$.
- 5. Step 5: Solve row (1) for x_1 :

$$x_1 = \frac{1}{a}y_1 - \frac{b}{a}x_2 = \left[\frac{1}{a} + \frac{b}{a}\frac{c}{\Delta}\right]y_1 - \frac{b}{a}\frac{a}{\Delta}y_2.$$

Rewriting in matrix format, in terms of $\Delta = ad - bc$, gives

$$\begin{bmatrix} x_1 \\ x_2 \end{bmatrix} = \begin{bmatrix} \frac{1}{a} + \frac{bc}{a\Delta} - \frac{b}{\Delta} \\ -\frac{c}{\Delta} & \frac{a}{\Delta} \end{bmatrix} \begin{bmatrix} y_1 \\ y_2 \end{bmatrix} = \frac{1}{\Delta} \begin{bmatrix} \frac{\Delta + bc}{a} - b \\ -c & a \end{bmatrix} \begin{bmatrix} y_1 \\ y_2 \end{bmatrix} = \frac{1}{\Delta} \begin{bmatrix} d & -b \\ -c & a \end{bmatrix} \begin{bmatrix} y_1 \\ y_2 \end{bmatrix},$$

since $d = (\Delta + bc)/a$.

Summary: This is a lot of messy algebra, so it is essential that you memorize the final result:

(1) swap the diagonal, (2) change the off-diagonal signs, and (3) normalize by the determinant Δ .

Appendix B **Eigenanalysis**

Eigenanalysis is ubiquitous in engineering applications. It is useful in solving differential and difference equations, data-science applications, numerical approximation and computing, and linear algebra applications. Typically one must take a course in linear algebra to become knowledgeable in the inner workings of this method. In this appendix we intend to provide sufficient basics to allow one to read the text.

B.1 The Eigenvalue Matrix (Λ)

Given 2×2 matrix A, the related matrix eigenequation is

$$AE = E\Lambda. (B.1.1)$$

Pre-multiplying by E^{-1} diagonalizes A, resulting in the *eigenvalue matrix*

$$\Lambda = \mathbf{E}^{-1} \mathbf{A} \mathbf{E} \tag{B.1.2}$$

$$= \begin{bmatrix} \lambda_1 & 0 \\ 0 & \lambda_2 \end{bmatrix}. \tag{B.1.3}$$

Post-multiplying by E^{-1} recovers A

$$\mathbf{A} = \mathbf{E} \Lambda \mathbf{E}^{-1} = \begin{bmatrix} a_{11} & a_{12} \\ a_{21} & a_{22} \end{bmatrix}.$$
 (B.1.4)

Matrix product formula:

This last relation is the entire point of the eigenvector analysis, since it shows that any power of A may be computed from powers of the eigenvalues. Specifically,

$$\mathbf{A}^n = \mathbf{E} \Lambda^n \mathbf{E}^{-1}. \tag{B.1.5}$$

[©] Springer Nature Switzerland AG 2020

³⁰⁵

For example, $A^2 = AA = E\Lambda (E^{-1}E)^{-1}AE^{-1} = E\Lambda^2E^{-1}$.

Equations B.1.1, B.1.3, and B.1.4 are the key to eigenvector analysis, and you need to memorize them. You will use them repeatedly throughout this text.

$A - \lambda_{\pm} I_2$ is singular:

If we restrict Eq. B.1.1 to a single eigenvector (one of e_{\pm}), along with the corresponding eigenvalue λ_{\pm} , we obtain the two matrix equations

$$Ae_+ = e_+\lambda_+ = \lambda_+e_+.$$

Note the swap in the order of E_{\pm} and λ_{\pm} . Since λ_{\pm} is a scalar, this is legal (and critically important), since this allows us to factor out e_{\pm}

$$(\mathbf{A} - \lambda_{\pm} \mathbf{I}_2) \mathbf{e}_{\pm} = 0. \tag{B.1.6}$$

The matrix $A - \lambda_{\pm} I_2$ must be singular because when it operates on e_{\pm} , having nonzero norm, it must be zero.

It follows that its determinant (i.e., $|(A - \lambda_{\pm} I_2)| = 0$) must be zero. This equation uniquely determines the eigenvalues λ_{\pm} .

B.1.1 Calculating the Eigenvalues λ_{\pm}

The eigenvalues λ_{\pm} of A may be determined from $|(A - \lambda_{\pm}I_2)| = 0$. As an example we let A be Pell's equation (Eq. 2.6.9, Sect. 2.5.2). In this case the eigenvalues may be found from

$$\begin{vmatrix} 1 - \lambda_{\pm} & N \\ 1 & 1 - \lambda_{\pm} \end{vmatrix} = (1 - \lambda_{\pm})^{2} - N = 0,$$

thus $\lambda_{\pm} = (1 \mp \sqrt{N})^3$.

B.1.2 Calculating the Eigenvectors e±

Once the eigenvalues have been determined, they are substituted into Eq. B.1.6, which determines the eigenvectors $E = [e_+, e_-]$, by solving

$$(\mathbf{A} - \lambda_{\pm})\mathbf{e}_{\pm} = \begin{bmatrix} 1 - \lambda_{\pm} & 2\\ 1 & 1 - \lambda_{\pm} \end{bmatrix} \mathbf{e}_{\pm} = 0, \tag{B.1.7}$$

³It is a convention to order the eigenvalues from largest to smallest.

where $1 - \lambda_{\pm} = 1 - (1 \mp \sqrt{N}) = \pm \sqrt{N}$, thus the Pell equation eigenvalues are

$$\lambda_{\pm} = 1 \mp \sqrt{N}$$
.

Recall that Eq. B.1.6 is singular because we are using an eigenvalue, and each eigenvector is pointing in a unique direction (this is why it is singular). You might expect that this equation has no solution. In some sense you would be correct. When we solve for e_{\pm} , the two equations defined by Eq. B.1.6 are *co-linear* (the two equations describe parallel lines so their scalar-product is one). This follows from the fact that there is only one eigenvector for each eigenvalue.

Since there is only one eigenvalue we are expecting trouble, yet we may proceed to solve for $e_+ = [e_1^+, e_2^+]^T$ with eigenvalue $+\sqrt{N}$

$$\begin{bmatrix} \sqrt{N} & N \\ 1 & \sqrt{N} \end{bmatrix} \begin{bmatrix} e_1^+ \\ e_2^+ \end{bmatrix} = 0.$$

If we divide the top row by \sqrt{N} the two rows are identical, since the matrix must be singular. Thus this matrix equation gives two identical equations. This is the price of an over-specified equation (the singular matrix is degenerate).

We can determine each eigenvectors direction, but not their magnitudes.

Following the same procedure for $\lambda_{-} = -\sqrt{N}$, the equation for e_{-} is

$$\begin{bmatrix} -\sqrt{N} & N \\ 1 & -\sqrt{N} \end{bmatrix} \begin{bmatrix} e_1^- \\ e_2^- \end{bmatrix} = 0.$$

As before, this matrix is singular. Here $e_1^- - \sqrt{N}e_2^- = 0$, thus the eigenvector is $e^- = c [\sqrt{N}, 1]^T$, where c is a normalization constant.

Thus the *unnormalized* eigenmatrix is

$$\boldsymbol{E} = \begin{bmatrix} e_1^+ & e_2^- \\ e_2^+ & e_2^- \end{bmatrix} = \begin{bmatrix} \sqrt{N} & -\sqrt{N} \\ 1 & 1 \end{bmatrix}.$$

B.1.3 Normalization of the Eigenvectors

The constant c may be determined by normalizing the eigenvectors to have unit length. Since we cannot determine the length, we set it to 1. Thus the degeneracy may be resolved by the one degree of freedom normalization

$$\left(\pm\sqrt{N}\right)^2 + 1^2 = N + 1 = 1/c^2.$$

Thus the normalization factor to force each eigen vector to have length 1 is $c = 1/\sqrt{N+1}$.

B.2 Pell Equation Solution Example

Section 2.6.2 showed that the solution $[x_n, y_n]^T$ to Pell's equation is given by powers of the Pell matrix A. For N = 2, in Sect. 2.6.2 we found the explicit formula for $[x_n, y_n]^T$, based on powers of the Pell matrix

$$A = 1_J \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix}. \tag{B.2.1}$$

This recursive solution to Pell's equation (Eq. 2.6.7) is Eq. 2.6.9 (Sect. 2.5.2). Thus we need powers of A, that is A^n , which gives an explicit expression for $[x_n, y_n]^T$. By the diagonalization of A, its powers are simply the powers of its eigenvalues.

From MATLAB/Octave with N=2 the eigenvalues of Eq. B.2.1 are $\lambda_{\pm}\approx [2.4142_J, -0.4142_J]$ (i.e., $\lambda_{\pm}=1_J(1\pm\sqrt{2})$). The solution for N=3 is shown on Sect. B.2.1.

Once the matrix has been diagonalized, one may compute powers of that matrix as powers of the eigenvalues. This results in the general solution given by

$$\begin{bmatrix} x_n \\ y_n \end{bmatrix} = 1 j^n \mathbf{A}^n \begin{bmatrix} 1 \\ 0 \end{bmatrix} = 1 j^n \mathbf{E} \Lambda^n \mathbf{E}^{-1} \begin{bmatrix} 1 \\ 0 \end{bmatrix}.$$

The eigenvalue matrix D is diagonal with the eigenvalues sorted, largest first. The MATLAB/Octave command [E,D]=eig(A) is helpful to find D and E given any A. As we saw above,

$$\Lambda = 1_J \begin{bmatrix} 1 + \sqrt{2} & 0 \\ 0 & 1 - \sqrt{2} \end{bmatrix} \approx \begin{bmatrix} 2.414_J & 0 \\ 0 & -0.414_J \end{bmatrix}.$$

B.2.1 Pell Equation Eigenvalue–Eigenvector Analysis

Here we show how to compute the eigenvalues and eigenvectors for the 2×2 Pell matrix for N=2

$$A = \begin{bmatrix} 1 & 2 \\ 1 & 1 \end{bmatrix}.$$

The MATLAB/Octave command [E,D] = eig(A) returns the eigenvector matrix E

$$E = [e_+, e_-] = \frac{1}{\sqrt{3}} \begin{bmatrix} \sqrt{2} - \sqrt{2} \\ 1 & 1 \end{bmatrix} = \begin{bmatrix} 0.8165 - 0.8165 \\ 0.5774 & 0.5774. \end{bmatrix}$$

and the eigenvalue matrix Λ (Matlab/Octave's D)

Table B.1 Summary of the solution of Pell's equation due to the Pythagoreans using matrix recursion, for the case of N=3. The integer solutions are shown on the right. Note that $x_n/y_n \to \sqrt{3}$, in agreement with the Euclidean algorithm. The MATLAB/Octave program for generating this data is PellSol3.m. It seems likely that the powers of β_0 could be absorbed in the starting solution, and then be removed from the recursion

Pell's Equation for
$$N=3$$

Case of $N=3$ & $[x_0,y_0]^T=[1,0]^T$, $\beta_0=\jmath/\sqrt{2}$
Note: $x_n^2-3y_n^2=1$, $x_n/y_n \longrightarrow \sqrt{3}$

$$\begin{bmatrix} x_1 \\ y_1 \end{bmatrix} = \beta_0 \begin{bmatrix} 1 \\ 1 \end{bmatrix} = \beta_0 \begin{bmatrix} 1 & 3 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 1 \\ 0 \end{bmatrix}$$

$$\begin{bmatrix} x_2 \\ y_2 \end{bmatrix} = \beta_0^2 \begin{bmatrix} 4 \\ 2 \end{bmatrix} = \beta_0^2 \begin{bmatrix} 1 & 3 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 1 \\ 1 \end{bmatrix}$$

$$\begin{bmatrix} x_3 \\ y_3 \end{bmatrix} = \beta_0^3 \begin{bmatrix} 10 \\ 6 \end{bmatrix} = \beta_0^3 \begin{bmatrix} 1 & 3 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 4 \\ 2 \end{bmatrix}$$

$$\begin{bmatrix} x_3 \\ y_4 \end{bmatrix} = \beta_0^4 \begin{bmatrix} 28 \\ 16 \end{bmatrix} = \beta_0^4 \begin{bmatrix} 1 & 3 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 10 \\ 6 \end{bmatrix}$$

$$\begin{bmatrix} x_4 \\ y_4 \end{bmatrix} = \beta_0^4 \begin{bmatrix} 28 \\ 16 \end{bmatrix} = \beta_0^5 \begin{bmatrix} 76 \\ 44 \end{bmatrix} = \beta_0^5 \begin{bmatrix} 1 & 3 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 28 \\ 16 \end{bmatrix}$$

$$\begin{bmatrix} x_5 \\ y_5 \end{bmatrix} = \beta_0^5 \begin{bmatrix} 76 \\ 44 \end{bmatrix} = \beta_0^5 \begin{bmatrix} 1 & 3 \\ 1 & 1 \end{bmatrix} \begin{bmatrix} 28 \\ 16 \end{bmatrix}$$

$$\begin{bmatrix} 28 \\ 16 \end{bmatrix}$$

$$\begin{bmatrix} 76 \\ 6 \\ 5 \end{bmatrix}^2 - 3 (44 \\ 6 \end{bmatrix}^2 = 1$$

$$\Lambda \equiv \begin{bmatrix} \lambda_+ & 0 \\ 0 & \lambda_- \end{bmatrix} = \begin{bmatrix} 1 + \sqrt{2} & 0 \\ 0 & 1 - \sqrt{2} \end{bmatrix} = \begin{bmatrix} 2.4142 & 0 \\ 0 & -0.4142 \end{bmatrix}.$$

The factor $\sqrt{3}$ on E normalizes each eigenvector to 1 (i.e., MATLAB/Octave's command norm([$\sqrt{2}$, 1]) gives $\sqrt{3}$).

In the following discussion we show how to determine E and D (i.e., Λ), given A.

B.2.2 Pell's Equation for N = 3

In Table B.1, Pell's equation for N=3 is given, with $\beta_0=j/\sqrt{2}$. Perhaps try other trivial solutions such as $[-1,0]^T$ and $[\pm j,0]^T$, to provide clues to the proper value of β_0 for cases where N>3.⁴

Example: I suggest that you verify $E\Lambda \neq \Lambda E$ and $AE = E\Lambda$ with MATLAB/Octave. Here is the MATLAB/Octave program which does this:

⁴My student Kehan found the general formula for β_0 .

A = [1 2; 1 1]; %define the matrix [E,D] = eig(A); %compute the eigenvector and eigenvalue matrices A*E-E*D %This should be \$\approx 0\$, within numerical error. E*D-D*E %This is not zero

Summary:

Thus far we have shown that for the case of Pell matrix with N=2, the normalized eigenmatrix and its inverse is

$$E = [e_+, e_-] = \frac{1}{\sqrt{3}} \begin{bmatrix} \sqrt{2} - \sqrt{2} \\ 1 & 1 \end{bmatrix} \qquad E^{-1} = \frac{\sqrt{6}}{4} \begin{bmatrix} 1 & \sqrt{2} \\ -1 & \sqrt{2} \end{bmatrix}$$

and the eigenmatrix is

$$\Lambda = \begin{bmatrix} \lambda_+ & 0 \\ 0 & \lambda_- \end{bmatrix} = \begin{bmatrix} 1 + \sqrt{2} & 0 \\ 0 & 1 - \sqrt{2} \end{bmatrix}.$$

Note that when working with numeric data it is not necessary to normalize E. For example, the form of $\mathbf{e}_1^{\pm} = [1 \pm \lambda^+, 1]^T$ is very simple, and easy to work with. Once normalize it becomes $(N=2) [\sqrt{2}/\sqrt{3}, 1/\sqrt{3}]^T = [0.8165, 0.57735]^T$, obscuring its natural simplicity. The normalization buys little in terms of function.

B.3 Symbolic Analysis of $TE = E\Lambda$

B.3.1 The 2×2 Transmission Matrix

Here we assume

$$\mathcal{T} = \begin{bmatrix} \mathcal{A} & \mathcal{B} \\ \mathcal{C} & \mathcal{D} \end{bmatrix}$$

with $\Delta_{\mathcal{T}} = 1$.

The eigenvectors e_{\pm} of T are

$$\boldsymbol{e}_{\pm} = \begin{bmatrix} \frac{1}{2C} \left[(\mathcal{A} - \mathcal{D}) \mp \sqrt{(\mathcal{A} - \mathcal{D})^2 + 4\mathcal{B}C} \right] \\ 1 \end{bmatrix}$$
(B.3.1)

and eigenvalues are

$$\lambda_{\pm} = \frac{1}{2} \left[(\mathcal{A} + \mathcal{D}) \mp \sqrt{(\mathcal{A} - \mathcal{D})^2 + 4\mathcal{B}C} \right]. \tag{B.3.2}$$

Thus the expression under the radical may be rewritten in terms of the determinant of \mathcal{T} (i.e., $\Delta_{\mathcal{T}} = \mathcal{AD} - \mathcal{BC}$) since

$$(\mathcal{A} - \mathcal{D})^2 - (\mathcal{A} + \mathcal{D})^2 = -4\mathcal{A}\mathcal{D}.$$

Thus for the ABCD matrix the expression under the radical becomes

$$(\mathcal{A} - \mathcal{D})^2 + 4\mathcal{B}\mathcal{C} = \mathcal{A}^2 + \mathcal{D}^2 - 4\mathcal{A}\mathcal{D} + 4\mathcal{B}\mathcal{C}$$
$$= \mathcal{A}^2 + \mathcal{D}^2 - 4\Delta_{\mathcal{T}}.$$

Rewriting the eigenvectors and eigenvalues in terms of $\Delta_T = \pm 1$, we find

$$\boldsymbol{e}_{\pm} = \begin{bmatrix} \frac{1}{c} \left[\frac{\mathcal{A} - \mathcal{D}}{2} \mp \sqrt{\left(\frac{\mathcal{A} + \mathcal{D}}{2}\right)^2 \mp \Delta_{\mathcal{T}}} \right] \\ 1 \end{bmatrix}$$
(B.3.3)

and

$$\lambda_{\pm} = \left\lceil \frac{\mathcal{A} + \mathcal{D}}{2} \mp \sqrt{\left(\frac{\mathcal{A} + \mathcal{D}}{2}\right)^2 \mp \Delta_{\mathcal{T}}} \right\rceil. \tag{B.3.4}$$

Note this may be further simplified since the radical is the same.

B.3.2 Matrices with Symmetry

For the case of the ABCD matrix the eigenvalues depend on reciprocity, since $\Delta_T = 1$ if T(s) is reciprocal, and $\Delta_T = -1$ if it is antireciprocal. Thus it is helpful to display the eigenfunctions and values in terms of Δ_T so this distinction is explicit.

B.3.2.1 Reversible Systems

When $\mathcal{A} = \mathcal{D}$

$$\boldsymbol{E} = \begin{bmatrix} -\sqrt{\frac{g}{C}} + \sqrt{\frac{g}{C}} \\ 1 & 1 \end{bmatrix} \qquad \qquad \Lambda = \begin{bmatrix} \mathcal{A} - \sqrt{\mathcal{B}C} & 0 \\ 0 & \mathcal{A} + \sqrt{\mathcal{B}C} \end{bmatrix} \qquad (B.3.5)$$

the transmission matrix is said to be reversible, and the properties greatly simplify. Note that $r_o = \sqrt{\mathcal{B}/\mathcal{C}}$ is the characteristic impedance and $\kappa(s) = 1/\sqrt{\mathcal{B}\mathcal{C}}$ is the propagation function.

B.3.2.2 Reciprocal Systems

When the matrix is symmetric ($\mathcal{B} = \mathcal{C}$), the corresponding system is said to be *reciprocal*. Most physical systems are reciprocal. The determinant of the transmission matrix of a reciprocal network $\Delta_T = \mathcal{AD} - \mathcal{BC} = 1$. For example, electrical networks composed of inductors, capacitors, and resistors are always reciprocal. It follows that the complex impedance matrix is symmetric (Van Valkenburg 1964a).

Magnetic systems such as dynamic loudspeakers are antireciprocal, and correspondingly $\Delta_T = -1$. The impedance matrix of these loudspeakers is skew symmetric (Kim and Allen 2013). All impedance matrices are either symmetric or antisymmetric, depending on whether they are reciprocal (LRC networks) or antireciprocal (magnetic networks). These systems have complex eigenvalues with negative real parts, corresponding to damped (lossy) systems. This follows from conservation of energy. The impedance matrix cannot be Hermitian, or the losses would be zero, because Hermitian matrices have real eigenvalues. Thus a physical system having loss cannot be Hermitian because the eigenvalues must have a negative real parts.

In summary, given a reciprocal system, the \mathcal{T} matrix has $\Delta_{\mathcal{T}} = 1$, and the corresponding impedance matrix is symmetric (*not* Hermitian).

B.3.3 Impedance Matrix

As previously discussed in Sect. 3.8, the $\mathcal T$ matrix corresponding to an impedance matrix is

$$\begin{bmatrix} V_1 \\ V_2 \end{bmatrix} = \mathbf{Z}(s) \begin{bmatrix} I_1 \\ I_2 \end{bmatrix} = \frac{1}{C} \begin{bmatrix} \mathcal{A} \ \Delta_T \\ 1 \ \mathcal{D} \end{bmatrix} \begin{bmatrix} I_1 \\ I_2 \end{bmatrix}.$$

Reciprocal systems have skew-symmetric impedance matrices, namely, $z_{12} = z_{21}$ (i.e., $\Delta_T = 1$). This condition is best understood using the T form of the impedance matrix, as shown in Fig. 3.9 (Sect. 3.8.2). When the system is both reversible $\mathcal{A} = \mathcal{D}$ and reciprocal, the impedance matrix simplifies to

$$\mathbf{Z}(s) = \frac{1}{\mathcal{C}} \begin{bmatrix} \mathcal{A} & 1 \\ 1 & \mathcal{A} \end{bmatrix}.$$

For such systems there are only two degrees of freedom, \mathcal{A} and \mathcal{C} . As discussed previously in Sect. 3.8, each of these has a physical meaning: $1/\mathcal{A}$ is the Thévenin source voltage given a voltage drive and \mathcal{B}/\mathcal{A} is the Thévenin impedance (Sect. 3.8.3).

Impedance is not Hermitian: By definition, when a system is Hermitian its matrix is conjugate symmetric

$$\mathbf{Z}(s) = \mathbf{Z}^{\dagger}(s),$$

a stronger condition than reciprocal, but not the symmetry of the Brune impedance matrix. A reciprocal Brune impedance is symmetric (not Hermitian).

Appendix E Thermodynamic Systems

Many people find thermodynamics difficult to understand. Here we explore the reasons behind this lack of transparency, and propose a solution. To understand the problem it is helpful to compare the nonlinear energy-equilibrium methods used in thermodynamic, to linear impedance methods, used in acoustics, mechanics, and electrical circuit theory.

Acoustics, mechanics, and electrical circuits are explained in terms of linear systems of equations, such as as Kirchhoff's and Ohm's laws, as discussed in Appendix D. The linear impedance formulation leads to a system of equations that is easily solved, using standard methods of linear algebra. Thermodynamics, on the other hand, is formulated in terms of equilibrium energies, resulting in nonlinear systems of equations. This explains the difficulty in understanding the relationships. A second issue is that these equations are frequently over-specified.

Traditionally thermodynamics has been formulated with two types of variables, those that are proportional to the mass, called *extensive* such as volume and mass, and the those that are independent of mass, called *intensive* variables, such as temperature and density (Ambaum 2010).

A more modern and transparent notation is to work with two *conjugate* variables (CV), ¹³ force density and flux. Examples of the CV force density include pressure \mathcal{P} , temperature T, the Nernst potential, and electrical voltage. Fluxes CVs include mass flux and its area integral, volume velocity \mathcal{V} , heat flux, called entropy S, and electrical current.

Impedance is the ratio of CV, and the power is their product. For example, in electrical network theory, the impedance is the voltage over the current and the power is the product. Working with impedance always results in systems of linear equations. *linear conjugate variables* (LCV) are a generalization of force, the gradient of a potential, and flow. Namely, the formulation in terms of LCV simplifies the thermodynamic system of nonlinear equations.

¹³https://en.wikipedia.org/wiki/Conjugate_variables_(thermodynamics).

[©] Springer Nature Switzerland AG 2020

E.1 Summary of the Thermodynamic Relations

To reduce the number of variables we remove mass from the system by working with *specific* variables (those that are normalized by the mass). The ratio of the volume \mathcal{V} and mass M defines the specific volume $\nu \equiv \mathcal{V}/M = 1/\rho$, where ρ is the density. Throughout this discussion we shall use SI units, with \mathcal{V} [m³], M [kgm], $\rho = 1/\nu$ [kg/m³].

Four classical thermodynamic energies are defined:

- 1. internal energy u,
- 2. specific enthalpy $h = u + P\nu$,
- 3. Helmholtz free energy f = u TS, and
- 4. Gibbs function $q = u TS + \mathcal{P}\nu$.


The Gibbs function is a linear combination of the other three (Ambaum 2010, Sect. 3.1). As explained by Tolman (1948), Gibbs viewed a phase transition as a membrane separating two states of a gas. These four relations could be combined into a 3×3 nonlinear energy matrix relating $[h, f, g]^T$ to $[u, \mathcal{P}\nu, TS]^T$. The entries of the matrix elements would all be either [0, 1, -1].

When many variables are used to describe a system, as in the case of thermodynamics, a matrix formulation is more compact representation. Here traditional thermodynamic relations are reformulated using linear 2×2 matrix algebra. Starting from the state equation and the Helmholtz expression for the free energy, we rewrite the system as a linear two-port network. By evaluating the impedance matrix elements, we may obtain the standard thermodynamic relations in terms of the two heat capacities c_p and c_v . Due to this unification of variables, the 2×2 formulation, such a formulation manipulation of thermodynamic relations becomes transparent.

In acoustics, the gradient of the pressure $-\nabla \mathcal{P}$ is the acoustic force density, which is proportional to the volume velocity \mathcal{V} (the acoustic flux, or mass flow). Thus the potential and its corresponding mass flux are linear conjugate variables, the ratio of which defines the specific acoustic impedance, which for air is ρc_o . When working with impedances it is standard practice to work with the Laplace complex frequency domain s. The \mathcal{LT} transforms differential equations in time into algebraic relations (i.e., polynomials). In thermodynamics the term *potential* has a very different meaning. Here we shall not refer to energies as potentials. When speaking of conjugate variables, pressure, voltage and temperature are potentials, and velocity, current and entropy are flows.

^aAn alternative approach is to use a 3×3 scattering matrix in more than 2 variables (Bilbao 2004).

Fig. E.1 Diagram showing the PVT diagram for an ideal gas. The axes are volume (v), pressure (p), and temperature (T). Shown are the definitions for the two latent heat capacities c_p and c_v . From this figure we can more easily identify the meanings of the various matrix elements. Figure 3.1 from Ambaum (2010, p. 45)



Using modern engineering terminology, the gradient of every potential is a generalized force F, which according to Ohm's law, is proportional to a generalized flow J. Working with LCV \mathcal{P} and the volume velocity $s \mathcal{V}$ gives

$$-\nabla \mathcal{P} = \rho c_o s \mathcal{V}.$$

Here ρc_o is the impedance of air, defined as the ratio of the generalized force $F = -\nabla \mathcal{P}$ over the volume velocity (flow) $s \mathcal{V}$ (Fig. E.1).

Ohm's law defines a linear relation, with the impedance being the complex proportional factor. The power is the product of LCV, which is a nonlinear relation, since it is quadratic in the conjugate variables. It follows from linear algebra that linear systems of equations are more transparent, compared, say, to the thermodynamic energy-based nonlinear of equations.

In terms of the four basic energy definitions, the force-flow relations for the four power relations are defined by four differentials (Ambaum 2010).

$$du = TdS - pd\nu$$

$$dh = TdS + \nu d \mathcal{P}$$

$$df = -SdT - \mathcal{P}d\nu$$

$$dg = -SdT + \nu d \mathcal{P}$$

Linear 2×2 **systems of equations:** The LCV thermodynamic variables are the mechanical (acoustical) pressure \mathcal{P} , volume velocity \mathcal{V} and the heat variables, temperature T, and entropy rate $\dot{\mathcal{S}}$.

The linear transmission and impedance matrices \mathcal{T} and \mathcal{Z} relate the acoustic variables \mathcal{P} , \mathcal{V} to the thermodynamic variables T, $\dot{\mathcal{S}}$ in two very different ways:

$$\begin{bmatrix} T \\ \dot{\mathcal{S}} \end{bmatrix} = \mathcal{T} \begin{bmatrix} \mathcal{P} \\ -\mathcal{V} \end{bmatrix} = \begin{bmatrix} \mathcal{A} & \mathcal{B} \\ \mathcal{C} & \mathcal{D} \end{bmatrix} \begin{bmatrix} \mathcal{P} \\ -\mathcal{V} \end{bmatrix} \quad \text{ and } \quad \begin{bmatrix} \mathcal{P} \\ T \end{bmatrix} = \mathcal{Z} \begin{bmatrix} \mathcal{V} \\ \dot{\mathcal{S}} \end{bmatrix} = \begin{bmatrix} z_{11} & z_{12} \\ z_{21} & z_{22} \end{bmatrix} \begin{bmatrix} \mathcal{V} \\ \dot{\mathcal{S}} \end{bmatrix}.$$

On the left is the *transmission matrix* \mathcal{T} and on the right is the corresponding *impedance matrix* \mathcal{Z} . By inspection, the \mathcal{T} and \mathcal{Z} matrix elements are

$$\mathcal{T} = \begin{bmatrix} \frac{T}{T} \middle| v = 0 & \frac{T}{V} \middle| v = 0 \\ \frac{\dot{S}}{T} \middle| v = 0 & \frac{\dot{S}}{V} \middle| v = 0 \end{bmatrix}, \qquad \mathcal{Z} = \begin{bmatrix} \frac{\underline{v}}{V} \middle| \dot{S} = 0 & \frac{\underline{v}}{\dot{S}} \middle| v = 0 \\ \frac{T}{V} \middle| \dot{S} = 0 & \frac{T}{\dot{S}} \middle| v = 0 \end{bmatrix}.$$

Due to reciprocity, the determinant of $\mathcal{T} = 1$ and $z_{12} = z_{21}$ (Postulate P8). When using this matrix representation, any algebra is explicit. The transmission matrix \mathcal{T} and impedance matrix \mathcal{Z} are related by Eq. 3.8.6, as discussed on Sect. 3.8.2.

Summary of Maxwell relations

There are six variants on the transmission matrix (Van Valkenburg 1964a). The most common are the transmission \mathcal{T} and the impedance \mathcal{Z} matrices. Others, such as the admittance matrix \mathcal{Y} is simply the inverse of \mathcal{Z} . But other variants are also used for special applications, such scattering matrices.

All the matrices used in thermodynamics are reciprocal, meaning $z_{12}=z_{21}$ or $\Delta_T=1$. Each matrix form show reciprocity in a different way. These expressions for reciprocity were first worked out by Maxwell, where they are called Maxwell relations (Ambaum 2010). From the Maxwell relations, it may be shown that the specific heat capacities are equal to $c_v=y_{22}=z_{11}/\Delta_Z$ and $c_p=g_{22}=1/y_{22}=\Delta_Z/z_{11}$.

E.1.1 Physical Meaning of the Matrix Elements

The utility of the \mathcal{T} and \mathcal{Z} representations are very different. The impedance matrix \mathcal{Z} always has a physically measurable interpretation. The diagonal elements z_{11} , z_{22} represent the input impedance looking into the two ports, while the off-diagonal elements are transfer impedances, related to the transfer function between input and output fluxes and potentials. If the system is reciprocal they are equal ($z_{12} = z_{21}$).

The transmission matrix plays a theoretical and modeling role. Thus \mathcal{Z} is used for experiments and \mathcal{T} for calculations. Other important matricides are the admittance matrix \mathcal{Y} and \mathcal{G} . There are simple relationships between all these matrices (Van Valkenburg 1964a, p. 310), a few of which are

$$\mathcal{T} = \frac{1}{z_{21}} \begin{bmatrix} z_{11} \ \Delta z \\ 1 \ z_{22} \end{bmatrix}, \qquad \mathcal{Z} = \frac{1}{\mathcal{C}} \begin{bmatrix} \mathcal{A} \ \Delta_{\mathcal{T}} \\ 1 \ \mathcal{D} \end{bmatrix}, \qquad \mathcal{Y} = \frac{1}{\Delta_{\mathcal{T}}} \begin{bmatrix} z_{22} \ -z_{12} \\ -z_{21} \ z_{11} \end{bmatrix}, \qquad \mathcal{G} = \frac{1}{z_{11}} \begin{bmatrix} 1 \ -z_{12} \\ z_{21} \ \Delta_{\mathcal{Z}} \end{bmatrix}.$$

Physical description of the 2x2 conjugate variables

To determine the physical meanings of the matrix elements we must start with the equation of state for the ideal gas $\mathcal{P} \mathcal{V} = RT$, where R is the specific gas constant. Two key thermodynamic constants are

$$c_v \equiv \left. \frac{\partial u}{\partial T} \right|_{v} = \left. \frac{\partial S}{\partial T} \right|_{v} \qquad c_p \equiv \left. \frac{\partial h}{\partial T} \right|_{\varphi} = \left. \frac{\partial S}{\partial T} \right|_{\varphi}.$$

To identify c_p and c_v in terms of these matrix elements we need to do some algebra. The equations need to be reformulated as

$$\begin{bmatrix} \mathcal{P} \\ \dot{\mathcal{S}} \end{bmatrix} = \begin{bmatrix} z_{11} \ \beta \\ \gamma \ \delta \end{bmatrix} \begin{bmatrix} \mathcal{V} \\ T \end{bmatrix} \quad \text{and} \quad \begin{bmatrix} \mathcal{V} \\ \dot{\mathcal{S}} \end{bmatrix} = \begin{bmatrix} y_{11} \ y_{12} \\ sc_v \ sc_p \end{bmatrix} \begin{bmatrix} \mathcal{P} \\ T \end{bmatrix}. \tag{E.1.1}$$

Here $s = \sigma + \omega J$ is the Laplace frequency, common to the Laplace transform. Both c_p and c_v have units of Farads.

For incompressable liquids these are equal, thus we may define $c_l = c_p = c_v$. In this case the internal energy u and enthalpy h are given by

$$u \approx h = u_o + c_l T$$
,

which means that any volume change is driven only by temperature rather than by work (Ambaum 2010).

For water in the vapor state they are distinct with $c_p = c_v + R$ and $c_v = 5R/2$. It follows that a mixture of dry air with 5% water vapor is mainly diatomic

$$(c_v/c_p)^2 = 1.4 = (5+2)/5.$$

From Eq. E.1.1, z_{11} is the reciprocal of the *bulk modulus*, defined as ratio of the volume over the pressure compliance for constant entropy (iso-thermal). Likewise, z_{22} is the ratio of $\mathcal{T}/\dot{\mathcal{S}}$ for constant volume (i.e., isobaric).

E.1.2 SI Units

The pressure \mathcal{P} [Pa] is a potential and the volume velocity \mathcal{V} [kgm/m²] is a flux having power \mathcal{P} \mathcal{V} . The corresponding thermal power is $Q = T \dot{\mathcal{S}}$ where $\dot{\mathcal{S}}$ is the entropy-rate (Q is the absorbed heat power) in Watts. Since the temperature T is a potential, analogous to a voltage, then $d \mathcal{S}/dt$ must be a flux, analogous to the current in an electrical system.

The total internal energy of a substance is defined by the enthalpy H = PV - Q, where Q = T S is the energy due to heat and PV is the mechanical energy. If H is constant and we vary the heat by a small amount, then $0 = \delta H \delta Q - \delta(PV) = \delta Q - P \delta V - V \delta P$. The thermodynamic constant c_p is defined as $\partial Q/\partial T|_{\mathcal{P}_o}$ (constant \mathcal{P}) and c_v is defined as $\partial Q/\partial T|_{\mathcal{P}_o}$ (constant \mathcal{P}).

Ambaum, M. H. (2010). Thermal physics of the atmosphere. Wiley Online Library.

Apte, S. (2009). The genius germs hypothesis: Were epidemics of leprosy and tuberculosis responsible in part for the great divergence? Hypothesis, 7(1):e3. https://www.hypothesisjournal.com/ wp-content/uploads/2011/09/vol7no1-hj003.pdf.

Arnold, D., & Rogness, J. (2019). Möbius transformations revealed. Youtube.com. video explaining the Riemann sphere: https://www.youtube.com/watch?v=0z1fIsUNhO4.

Batchelor, G. (1967). An introduction to fluid dynamics. Cambridge, UK: Cambridge University Press.

Beranek, L. L. (1954). Acoustics (451 pages). McGraw-Hill, New York.

Beranek, L. L., & Mellow, T. J. (2012). Acoustics: Sound fields and transducers. Waltham, MA: Elsevier: Academic.

Bilbao, S. (2004). Wave and scattering methods for numerical simulation (398 pages). London:

Boas, R. (1987). Invitation to complex analysis. New York: The Random House.

Bode, H. (1945). Network analysis and feedback amplifier design. New York: Van Nostrand.

Bohr, N. (1954). Rydberg's discovery of the spectral laws. Gleerup, Sweden: C.W.K.

Bombieri, E. (2000). Problems of the millennium: The Riemann hypothesis. In Publications of the Clay institute (pp. 1–11). Clay institute. "RiemannZeta-ClayDesc.pdf".

Boyer, C., & Merzbach, U. (2011). A history of mathematics. Hoboken, NJ: Wiley. https://books. google.com/books?id=BokVHiuIk9UC.

Brillouin, L. (1953). Wave propagation in periodic structures. London: Dover. Updated 1946 edition with corrections and added appendix.

Brillouin, L. (1960). Wave propagation and group velocity. Pure and applied physics (Vol. 8, 154 pages). Cambridge, MA: Academic.

Britannica, (2004). Encyclopædia Britannica Online. Britannica Online. https://en.wikipedia.org/ wiki/Pierre-Simon_Laplace.

Brune, O. (1931a). Synthesis of a finite two-terminal network whose driving point impedance is a prescribed function of frequency. Journal of Mathematics and Physics, 10, 191–236.

Brune, O. (1931b). Synthesis of a finite two-terminal network whose driving point impedance is a prescribed function of frequency. PhD thesis. Cambridge, MA: MIT. https://dspace.mit.edu/ handle/1721.1/10661.

Burton, D. M. (1985). The history of mathematics: An introduction. *Group*, 3(3):35.

Calinger, R. S. (2015). Leonhard Euler: Mathematical genius in the enlightenment. Princeton, NJ: Princeton University Press.

© Springer Nature Switzerland AG 2020

J. Allen, An Invitation to Mathematical Physics and Its History,

Campbell, G. (1937). *The collected papers of George Ashley Campbell*. AT&T, Archives, 5 Reiman Rd, Warren, NJ. Forward by Vannevar Bush; Introduction by E.H. Colpitts.

- Campbell, G. A. (1903). On loaded lines in telephonic transmission. *Philosophical Magazine*, 5(27), 313–30.
- Campbell, G. A. (1910). Telephonic intelligibility. *Philosophical Magazine*, 19(6), 152–59.
- Campbell, G. A. (1922). Physical theory of the electric wave-filter. *Bell System Technical Journal*, *1*(2), 1–32.
- Carlin, H. J., & Giordano, A. B. (1964). Network theory, an introduction to reciprocal and nonreciprocal circuits. Englewood Cliffs, NJ: Prentice Hall.
- Cauer, W. (1932). The Poisson integral for functions with positive real part. *Bulletin of the American Mathematical Society*, 38(1919), 713–717. https://www.ams.org/bull/1932-38-10/S0002-9904-1932-05510-0/S0002-9904-1932-05510-0.pdf.
- Cauer, W. (1958). Synthesis of linear communication networks (Vols. 1 and 2). New York: McGraw-Hill.
- Cauer, W., Klein, W., Pelz, F., Knausenberger, G., & Warfield, J. (1958). Synthesis of linear communication networks. New York: McGraw-Hill.
- Condon, E., & Morse, P. (1929). Quantum mechanics. New York: McGraw-Hill.
- Crandall, I. B. (1926). *Theory of vibrating systems and sound (272 pages)*. New York: Van Nostrand. D'Angelo, J. P. (2017). *Linear and complex analysis for applications*. Boca Raton, FL: CRC Press, Taylor & Francis Group.
- Einstein, A. (1905). Über die von der molekularkinetischen theorie der wärme geforderte bewegung von in ruhenden flüssigkeiten suspendierten teilchen. *Annalen der Physik*, 322(8), 549–60.
- Eisner, E. (1967). Complete solutions of the Webster horn equation. *Journal of the Acoustical Society of America*, 41(4B), 1126–46.
- Fagen, M. (Ed.). (1975). A history of engineering and science in the bell system the early years (1875–1925). Murray Hill, NJ, Cambridge, MA: Bell Telephone Laboratories.
- Fermi, E. (1936). Thermodynamics. New York, NY: Dover.
- Fettweis, A. (1986). Wave digital filters: Theory and practice. *Proceedings of the IEEE*, 74, 270–327.
- Feynman, R. (1968). The character of physical law. Cambridge, MA: MIT press.
- Feynman, R. (1970a). Feynman lectures on physics. Boston, MA: Addison-Wesley.
- Feynman, R. (1970b). Feynman lectures on physics (Vol. II). Boston, MA: Addison-Wesley.
- Feynman, R. (1970c). Feynman lectures on physics (Vol. III). Boston, MA: Addison-Wesley.
- Feynman, R. (1970d). Feynman lectures on physics (Vol. I). Boston, MA: Addison-Wesley.
- Feynman, S. O. L. (2019). Youtube citation. *Youtube*. How the speed of light was first measured: https://en.wikipedia.org/wiki/Speed_of_light On the speed of light: https://www.youtube.com/watch?v=b9F8Wn4vf5Y How to measure the speed of light: https://www.youtube.com/watch?v=rZ0wx3uD2wo "Greek" versus "Babylonian" math; Mathematical deduction (8:41): https://www.youtube.com/watch?v=YaUlqXRPMmY Take another point of view (2/4): https://www.youtube.com/watch?v=xnzB_IHGyjg.
- Fick, A. (1855). Ueber diffusion. Annalen der Physik, 170(1), 59-86.
- Fitzpatrick, R. (2008). Maxwell's equations and the principles of electromagnetism. Jones & Bartlett
- Flanders, H. (1973). Differentiation under the integral sign. *American Mathematical Monthly*, 80(6), 615–27.
- Fletcher, N., & Rossing, T. (2008). *The physics of musical instruments*. New York: Springer. https://books.google.com/books?id=9CRSRYQIRLkC.
- Fry, T. (1928). Probability and its engineering uses. Princeton NJ: Van Nostrand.
- Galileo, (1638). *Two new sciences* 1914. New York: Macmillan & Co. https://files.libertyfund.org/files/753/0416_Bk.pdf.
- Gallagher, T. F. (2005). Rydberg atoms (Vol. 3). Cambridge: Cambridge University Press.
- Garber, D. (2004). On the frontlines of the scientific revolution: How mersenne learned to love galileo. *Perspectives on Science*, 12(2), 135–63.

Goldsmith, A. N., & Minton, J. (1924). The performance and theory of loud speaker horns. Proceedings of the Institute of Radio Engineers, 12(4), 423–78.

- Goldstein, L. (1973). A history of the prime number theorem. *American Mathematical Monthly*, 80(6), 599–615.
- Graham, R. L., Knuth, D. E., & Patashnik, O. (1994). Concrete mathematics: A foundation for computer science (2n ed.). Boston, MA: Addison-Wesley Longman.
- Greenberg, M. D. (1988). Advanced engineering mathematics. Upper Saddle River, NJ: Prentice Hall.
- Grosswiler, P. (2004). Dispelling the alphabet effect. *Canadian Journal of Communication*, 29(2), Hahn, W. (1941). A new method for the calculation of cavity resonators. *Journal of Applied Physics*, 12, 62–68.
- Hamming, R. W. (2004). *Methods of mathematics applied to calculus, probability, and statistics*. North Chelmsford, MA: Courier Corporation.
- Hanna, C. R., & Slepian, J. (1924). The function and design of horns for loud speakers. *Transactions of the American Institute of Electrical Engineers, XLIII*, 393–411.
- Heaviside, O. (1892). On resistance and conductance operators, and their derivatives inductance and permittance, especially in connection with electric and magnetic energy. *Electrical Papers*, 2, 355–74.
- Helmholtz, H. (1858). Ueber integrale der hydrodynamichen gleichungen welche den wirelbewegungen entsprechen (on integrals of the hydrodynamic equations that correspond to vortex motions). *Journal fur die reine und angewandte Mathematik*, 55, 25–55.
- Helmholtz, H., & (1863a). On the sensations of tone. 1954 (300 pages), New York: Dover.
- Helmholtz, H. (1863b). Ueber den einfluss der reibung in der luft auf die schallbewegung (on the influence of friction in the air on the sound movement). *Verhandlungen des naturhistorischmedicinischen Vereins zu Heildelberg, III*(17), 16–20. Sitzung vom 27.
- Helmholtz, H. (1978). On integrals of the hydrodynamic equations that correspond to vortex motions. *International Journal of Fusion Energy*, *1*(3–4), 41–68. English translation of Helmholtz's 1858 paper, translated by Uwe Parpart (1978). The image of Helmholtz is on page 41. https://www.wlym.com/archive/fusion/fusionarchive_ijfe.html.
- Heras, R. (2016). The Helmholtz theorem and retarded fields. *European Journal of Physics*, 37(6), 065204. https://stacks.iop.org/0143-0807/37/i=6/a=065204.
- Hestenes, D. (2003). Spacetime physics with geometric algebra. *American Journal of Physics*, 71(7), 691–714.
- Hill, J. M. (2007). Laplace transforms and the riemann zeta function. *Integral Transforms and Special Functions*, 18(3), 193–205. jhill@uow.edu.au.
- Horn, R., & Johnson, C. (1988). *Matrix analysis*. Cambridge, England: Cambridge University Press. Hunt, F. V. (1952). *Electroacoustics, the analysis of transduction, and its historical background* (260 pages). Woodbury, NY: The Acoustical Society of America. 11797.
- Jaynes, E. (1991). Scattering of light by free electrons as a test of quantum theory. In *The electron* (pp. 1–20). Berlin: Springer.
- Johnson, D. H. (2003). Origins of the equivalent circuit concept: The voltage-source equivalent. *Proceedings of the IEEE*, 91(4), 636–640. https://www.ece.rice.edu/~dhj/paper1.pdf.
- Johnson, F. S., Cragin, B. L., & Hodges, R. R. (1994). Electromagnetic momentum density and the poynting vector in static fields. *American journal of physics*, 62(1), 33–41.
- Karal, F. C. (1953). The analogous acoustical impedance for discontinuities and constrictions of circular cross section. *Journal of the Acoustical Society of America*, 25(2), 327–334.
- Kelley, C. T. (2003). Solving nonlinear equations with Newton's method (Vol. 1). Siam.
- Kennelly, A. E. (1893). Impedance. Transactions of the American Institute of Electrical Engineers, 10, 172–232.
- Kim, N., & Allen, J. B. (2013). Two-port network analysis and modeling of a balanced armature receiver. *Hearing Research*, 301, 156–167.
- Kim, N., Yoon, Y.-J., & Allen, J. B. (2016). Generalized metamaterials: Definitions and taxonomy. *Journal of the Acoustical Society of America*, 139, 3412–3418.

Kirchhoff, G. (1868). On the influence of heat conduction in a gas on sound propagation. *Annual Review of Physical Chemistry*, 134, 177–193.

- Kirchhoff, G. (1974). On the influence of heat conduction in a gas on sound propagation (*English*). In Lindsay, R. B., (Ed.), *Physical acoustics, benchmark papers in acoustics* (Vo. 4, pp. 7–19). Stroudsburg, Pennsylvania: Dowden, Hutchinson & Ross, Inc.
- Kleiner, M. (2013). *Electroacoustics*. Boca Raton, FL, USA: CRC Press, Taylor & Francis Group. https://www.crcpress.com/authors/i546-mendel-kleiner.
- Kuhn, T. (1978). Black-body theory and the quantum discontinuity, 1894–1912; (371 pages). Oxford University Press (1978) & University of Chicago Press (1987), Oxford, Oxfordshire; Chicago, IL.
- Kusse, B. R., & Westwig, E. A. (2010). *Mathematical physics: Applied mathematics for scientists and engineers*. New Jersey: Wiley.
- Lamb, H. (1932). Hydrodynamics. New York: Dover Publications.
- Lighthill, S. M. J. (1978). Waves in fluids. England: Cambridge University Press.
- Lin, J. Y. (1995). The Needham Puzzle: Why the Industrial Revolution did not originate in China. *Economic Development and Cultural Change*, 43(2), 269–292.
- Lundberg, K. H., Miller, H. R., & Trumper, R. L. (2007). Initial conditions, generalized functions, and the laplace transform: Troubles at the origin. *IEEE Control Systems Magazine*, 27(1), 22–35.
- Mason, W. (1927). A study of the regular combination of acoustic elements with applications to recurrent acoustic filters, tapered acoustic filters, and horns. *Bell System Technical Journal*, 6(2), 258–294.
- Mason, W. (1928). The propagation characteristics of sound tubes and acoustic filters. *Physical Review*, 31, 283–295.
- Mawardi, O. K. (1949). Generalized Solutions of Webster's Horn Theory. *Journal of the Acoustical Society of America*, 21(4), 323–30.
- Maxwell, J. C. (1865). Viii. a dynamical theory of the electromagnetic field. *Philosophical transactions of the Royal Society of London*, 32(155), 459–512.
- Mazur, J. (2014). Enlightening symbols: A short history of mathematical notation and its hidden powers. Princeton, NJ: Princeton University Press.
- McMillan, E. M. (1946). Violation of the reciprocity theorem in linear passive electromechanical systems. *Journal of the Acoustical Society of America*, 18, 344–347.
- Menzies, G. (2004). 1421: The year China discovered America. NYC: HarperCollins.
- Menzies, G. (2008). 1434: The year a magnificent Chinese fleet sailed to Italy and ignited the renaissance. NYC: HarperCollins.
- Miles, J. W. (1948). The coupling of a cylindrical tube to a half-infinite space. *Journal of the Acoustical Society of America*, 20(5), 652–664.
- Miller, D. A. (1991). Huygens's wave propagation principle corrected. *Optics Letters*, 16(18), 1370–2.
- Montgomery, C., Dicke, R., & Purcell, E. (1948). *Principles of microwave circuits*. New York: McGraw-Hill Inc.
- Moralee, D. (1974, 1980, 1995). The first ten years. Cambridge University Physics Society, Cambridge, UK.
- Morse, P. M. (1948). Vibration and sound (468 pages). New York, NY: McGraw-Hill.
- Morse, P. M., & Feshbach, H. (1953). *Methods of theoretical physics* (Vols. I, II). New York: McGraw-Hill Inc.
- Nyquist, H. (1924). Certain factors affecting telegraph speed. *Bell System Technical Journal*, 3, 324.
- Olson, H. F. (1947). *Elements of acoustical engineering* (2nd ed., 539 pages). D. Van Nostrand Company.
- O'Neill, M. E. (2009). The genuine sieve of eratosthenes. *Journal of Functional Programming*, 19(1), 95–106.
- Palmerino, C. (1999). Infinite degrees of speed: Marin mersenne and the debate over Galileo's law of free fall. *Early Science and Medicine*, 4(4), 269–328. www.jstor/stable/4130144.

Papasimakis, N., Raybould, T., Fedotov, V. A., Tsai, D. P., Youngs, I., & Zheludev, N. I. (2018). Pulse generation scheme for flying electromagnetic doughnuts. *Physical Review B*, 97, 201409.

- Papoulis, A. (1962). The Fourier integral and its applications. New York: McGraw-Hill Book Co.
- Papoulis, A., & Pillai, S. U. (2002). *Probability, random variables, and stochastic processes*. Tata McGraw-Hill Education.
- Pierce, A. D. (1981). Acoustics: An introduction to its physical principles and applications (678 pages). New York: McGraw-Hill.
- Pipes, L. A. (1958). Applied mathematics for engineers and physicists. New York, NY: McGraw-Hill.
- Ramo, S., Whinnery, J. R., & Van Duzer, T. (1965). Fields and waves in communication electronics. New York: Wiley.
- Rasetshwane, D. M., Neely, S. T., Allen, J. B., & Shera, C. A. (2012). Reflectance of acoustic horns and solution of the inverse problem. *The Journal of the Acoustical Society of America*, 131(3), 1863–1873.
- Rayleigh, J. W. (1896). Theory of sound (Vol. I 480 pages, Vol. II 504 pages). New York: Dover.
- Riemann, B. (1859). On the number of primes less than a given magnitude. *Monatsberichte der Berliner Akademie* (pp. 1–10). Translated by David R. Wilkins-1998.
- Rotman, J. J. (1996). A first course in abstract algebra. Prentice-Hall.
- Salmon, V. (1946). Generalized plane wave horn theory. Journal of the Acoustical Society of America, 17(3), 199–211.
- Schelkunoff, S. (1943). Electromagnetic waves (6th ed.). Toronto, New York and London: Van Nostrand Co., Inc.
- Schwinger, J. S., & Saxon, D. S. (1968). Discontinuities in waveguides: Notes on lectures by Julian Schwinger. New York: Gordon and Breach.
- Scott, A. (2002). *Neuroscience: A mathematical primer*. Berlin: Springer Science & Business Media. Shaw, E. (1970). Acoustic horns with spatially varying density or elasticity. *Journal of the Acoustical Society of America*, 50(3), 830–840.
- Sommerfeld, A. (1949). Partial Differential Equations in Physics, Lectures on Theoretical Physics (Vol. I). New York: Academic Press INC.
- Sommerfeld, A. (1952). *Electrodynamics, Lectures on Theoretical Physics* (Vol. III). New York: Academic Press INC.
- Sondhi, M. and Gopinath, B. (1971). Determination of vocal-tract shape from impulse responses at the lips. *Journal of the Acoustical Society of America*, 49(6:2), 1867–1873.
- Stewart, G. W. (1922). Acoustic wave filters. *Physical Review*, 20(6), 528.
- Stewart, G. W., & Lindsay, R. B. (1930). *Acoustics: A text on theory and applications*. New Jersey, NJ: D. Van Nostrand Company Incorporated.
- Stewart, J. (2012). Essential calculus: Early transcendentals. Boston, MA: Cengage Learning. https://books.google.com/books?id=AcQJAAAAQBAJ.
- Stillwell, J. (2002). Mathematics and its history; Undergraduate texts in mathematics (2d ed.). New York: Springer.
- Stillwell, J. (2010). Mathematics and its history; Undergraduate texts in mathematics (3d ed.). New York: Springer.
- Strang, G., Strang, G., Strang, G., & Strang, G. (1993). *Introduction to linear algebra* (Vol. 3). Cambridge, MA: Wellesley-Press.
- Tisza, L. (1966). Generalized thermodynamics (Vol. 1). Cambridge: MIT Press.
- Tolman, R. C. (1948). Consideration of the Gibbs theory of surface tension. *The Journal of Chemical Physics*, 16(8), 758–774.
- Van Valkenburg, M. (1960). Introduction to modern network synthesis. New York: Wiley Inc.
- Van Valkenburg, M. (1964a). Network analysis (2nd ed.). Englewood Cliffs, N.J.: Prentice-Hall.
- Van Valkenburg, M. E. (1964b). Modern network synthesis. New York, NY: Wiley Inc.
- Vanderkooy, J. (1989). A model of loudspeaker driver impedance incorporating eddy currents in the pole structure. *JAES*, 37(3), 119–128.

Webster, A. G. (1919). Acoustical impedance, and the theory of horns and of the phonograph. *Proceedings National Academe of Science*, 5, 275–282.

- White, M. (1999). Isaac Newton: The last sorcerer. Basic Books (AZ).
- Wikipedia: Speed of Light (2019). Wikipedia citation. *Wikipedia*. How speed of light was first measured: https://en.wikipedia.org/wiki/Speed_of_light.
- Winchester, S. (2009). The man who loved China: The fantastic story of the eccentric scientist who unlocked the mysteries of the middle kingdom. Harper Collins.
- Youla, D. (1964). Analysis and synthesis of arbitrarily terminated lossless nonuniform lines. *IEEE Transactions on Circuit Theory*, 11(3), 363–372.

Symbols	ceil(x), 295
$\nabla \times$ (): see curl, 230	compan, 87
$\nabla \cdot$ (): see divergence, 230	conv(A,B), 87, 112
F: see fractional numbers, 22	deconv(), 112
∇ (): see gradient, 230, 245	deconv(A,B),87
$\nabla(\phi(x))$, 265	fix(x), 295
∇^2 (): see Laplacian, 37, 230	floor(x), 44, 295
N: see counting numbers, 20, 291	mod(x,y), 49
\mathbb{P} : see primes, $\frac{20}{20}$	poly(), 86, 112
Q: see rational numbers, 21	polyder(),87
T(s): see transmission matrix, 143	polyval(), 86, 112
∇^2 (): see vector Laplacian, 230	rem(x,y),49
\mathcal{Y}_r : see characteristic admittance, 257	residue(N,D),87,112
Y_{in} input admittance, 189	roots(), 86, 108, 112
\mathbb{Z} : see integers, 21	round(x), 295
\mathcal{Z}_r : see characteristic impedance, 257	roundb(x), $\frac{295}{}$
$\kappa(s)$ propagation vector, 73	DoG , 230, 276
$\kappa(s)$, definition, 188	gOd, 230, 275
$A_{\parallel}, A_{\perp}, 140$	1-port, 164
δ_k Dirac pulse, 318	2-port, 144, 164
$\delta(t)$: Dirac impulse, 159	
<i>E</i> , <i>D</i> , <i>H</i> , <i>B</i> : Definitions, 277	
E, D, H, B: Units, 279	A
$\ln \zeta(s)$, 314	abacus, 19
$\kappa(s)$ propagation function, 73	ABCD: see transmission matrix, 149
⊥: see perp Appendix A.1.3, 21	acoustic properties of air (Mason 1928), 326
$\rho_o = 1.2 [\text{kg/m}^3]$ (air density), 251	acoustic properties of air (Mason, 1928), 72
\land (): see wedge, 230	adiabatic expansion, speed of sound, 72, 247
$\zeta(s)$ function: See zeta function, 322	adiabatic process, 72
$\zeta(s)$, Riemann zeta function, 39	admittance, characteristic, 189
$\zeta(x)$, Euler zeta function, 39	admittance, input, 189
$c_o = 343$ [m/s] (air sound speed), 247	admittance: see impedance, 150
u(t) Heaviside step, 159	analytic continuation, 94, 108, 214
u(t) step function, 160	analytic continuation and the LT^{-1} , 215,
u_k step function, 318	320
z-transform, 84, 151, 152	analytic functions, 29, 98, 178, 181, 227
gOd : ∇^2 (aka Little god), 276	analytic geometry, 114, 121
© Springer Nature Switzerland AG 2020	371
J. Allen, An Invitation to Mathematical Physics and	Its History,
https://doi.org/10.1007/978-3-030-53759-3	

analytic, complex, 102, 162	Cauchy's residue theorem, 90, 161, 177, 204,
analytic, evolution operator, 73	205, 218, 237
antireciprocal, see reciprocity, 163	Cauchy, Augustin-Louis, 14, 37, 69
Assignments: AE-1, 103	Cauchy–Riemann conditions, 16, 17 182
Assignments: AE-2, 135	Cauer synthesis, 50
Assignments: AE-3, 173	causality, 152
Assignments: DE-1, 184	causality: P1, 339
Assignments: DE-2, 206	CFA matrix, 336
Assignments: DE-3, 223	CFA: see continued fractions, 46
Assignments: NS-1, 30	characteristic admittance, 189, 257
Assignments: NS-2, 51	Characteristic impedance, in vacuum, r_o ,
Assignments: NS-3, 62	$\frac{284}{}$
Assignments: VC-1, 252	Chebyshev, 36
Assignments: VC-2, 285	Chinese four stone problem: see puzzles, 30
atmospheres [atm] definition, 72	
augmented matrix, 128	chord-tangent methods, 171
augmented matrix, 126	CoC, 275, 276
	codomain, 102
_	CoG, 275, 276
В	colorized plots: see <i>plots, colorized</i> , 168
Bardeen, John, 103	companion matrix, 60, 61, 84, 86–88
Beranek, Leo, 290	companion matrix, roots and eigenvalues,
Bernoulli, Daniel, 69	84, 95
Bernoulli, Jakob, 12	completing the square, 75, 115
Bernoulli, Johann, 12	complex analytic, 99, 181, 194–196
Bessel function, 201, 220, 223	complex analytic admittance, 187
Bessel function roots, 250	complex analytic derivative, 180
Bethe, Hans, 103	complex analytic function, 72, 73, 99, 101,
Bhâskara II, 69	102, 163, 167, 170, 172, 179–183,
Bhâskara II, early calculus, x	188, 191–193, 195, 197, 199–201,
bilinear transformation, 113, 172, 297, 342	203, 205, 216, 218, 220, 222, 239,
Boas, Ralph, 290	242, 246
Bode, Hendrik, 69, 290	complex analytic function, calculus, 193
Bombelli, 4, 8, 25, 179	complex analytic function: history, 180, 181
Brahmagupta, 4, 20, 57, 58, 62, 70, 93	complex analytic functions, 16, 17
branch cut, 102, 170, 195–197, 200, 281	complex analytic scalar product, 120
branch index, 170	complex analytic: definition, 101
branch point, 197, 198, 200, 281	complex analytic: see causal, 163
Brillouin zones, 188	complex frequency, 38, 73, 182, 188, 205,
Brillouin, Léon, 69, 73, 103, 250, 262, 290	237
Brune condition, 101, 183, 192	complex frequency plane, 192
Brune impedance, 100, 114, 191, 204, 218	complex frequency, see Laplace frequency,
Bull-Dog, 274	216
Bull Bog, 274	complex numbers, 23
	complex numbers, Newton's view, 179
\mathbf{C}	=
Č .	complex numbers: history, 25
calendar, human, 10	complex numbers: polar representation, 24
Campbell's electrical wave filters, 324	complex scalar product, 124
Campbell, George Ashley, 250, 262, 349	composition, 37, 58, 112, 115, 121, 143, 149,
Cantor, 22	171, 172
Cardano, 74	composition: line and sphere, 171
Cauchy, 102, 170, 195, 222	compressible, 270
Cauchy's integral formula, 177, 205	conjugate of a complex number, 24
Cauchy's integral theorem, 38, 177, 203, 205	conjugate variables, 148, 206

conservation of energy, 9, 70, 100, 114, 147, 180, 191, 192 conservative field, 184, 241, 272 continued fractions, 42, 46, 47, 49, 50, 54, 60 convex hull, See Gauss–Lucas, 82, 94 convolution, 83, 87, 108, 110, 154, 221 convolution: continuous time definition, 147, 221	DoF: degrees of freedom, 273 DoG, 274, 276 domain, 102 domain-coloring: see <i>plots, colorized</i> , 168 driving-point impedance, 340 DTFT, 151, 152 dynamic stiffness of air, 72
convolution: discrete-time definition, 83 coprimes, 21, 22, 42, 44, 46 counting numbers, 20 CRT: Cauchy's residue theorem, 177 cryptography, 29 cubic, 74 curl $\nabla \times$ (), 38, 230, 245, 274	E eigenanalysis, 6 eigenanalysis: $2x2$ matrix, 310 eigenanalysis: Pell's equation, 59 eigenanalysis: reciprocal system, 312 eigenfunction of d/dt , 222 eigenmodes, 33
D d'Alembert, 10, 13, 187, 235, 257, 263, 264, 280 d'Alembert's solution to the wave equation, 72 d'Alembert, Jean le Rond, 69, 72, 108 da Vinci, Leonardo, 9	eigenmodes: physical explanation, 238 eigenspace, see vector space, 249 eigenvalues, 60, 61, 62, 85, 87–89, 306 eigenvalues of the companion matrix, 84 eigenvalues, Fibonacci sequence, 89 eigenvalues, Pell's equation, 89, 306 Einstein, Albert, 69, 73, 323 elimination, 115 elliptic differential equation, 242
day: seconds in, 10 deconvolution, 87, 111 degree vs. order, 200, 201 degree, fractional F, 297 degree, irrational I, 297 degree, polynomials, 74, 109, 296 degrees of freedom, 273	emf, 278 energy, 9, 70, 148, 206, 341–343 energy conservation, 9 entire functions, 97 entropy, 41 epicycle, 70
derivative, fractional \mathbb{F} , 201 derivative, half, 314 derivative, order, 201 Descartes, René, 8, 69, 108 determinant, 123, 127, 130, 132, 299, 301 Deterministic, 344	equations, linear, 93 Eratosthenes, 39, 40, 315, 316 error function, 314 essential singularity, 197 Euclid, 22 Euclid's formula, 2, 4, 56, 142, 359 Euclid's formula, derivation: DE-2, 56
Deterministic: P9, 339 DFT, 151, 152 Diaphanous, 2 diffusion equation, 243, 244, 262 digital filter, 83 Diophantus, 4, 56 Dirac pulse, 318	Euclidean algorithm, 42 Euclidean length, 117 Euler, 13, 322 Euler product formula, 82 Euler product formula: see Riemann ζ function, 82
dispersion relation, 188 dispersion relation, see propagation function, 188 dispersive wave propagation, 73 divergence, 230 divergence $\nabla \cdot ()$, 38, 245, 274 division with rounding, 44 DoC, 275, 276	Euler's equation, 247 Euler's functional zeta equation, 320 Euler, Leonhard, 69, 82, 170 evanescent modes, 261 evolution, 244 evolution operator $\kappa(s)$, 73 extended complex plane, Riemann, 170, 171 exterior product, 119

F	G
factoring, 74	Galileo, Galilei, 8, 9, 70, 102, 238, 241
Fermat, 8	Gamma function, 320
Fermat, Pierre de, 69, 108	Gauss, 195
Feshbach, Herman, 290	Gauss's law, 267, 278
Feynman, Richard, 290	Gauss, Carl Friedrich, 37, 69
FFT, 151, 152	Gauss, CFA vs. GCD, 46, 338
Fibonacci recursion formula, 19	Gauss, GCD versus CFA, 338
Fibonacci sequence, 60, 85, 122	Gauss-Lucas theorem, 81, 82, 94
Fibonacci sequence eigenanalysis, 66	Gaussian elimination, 115, 126
Fletcher, Harvey, 69	GCD, 42, 43
flux-flow relation, 149	GCD vs. CFA, Gauss, 46
Fourier Series, 151, 152	GCD: see greatest common divisor, 29
Fourier transform, 152	generalized admittance, 189
Fourier transform properties, 155	generalized complex scalar product, 124
Fourier transform table, 156	generalized force and flow, 147
fractional numbers: \mathbb{F} , 22	generalized impedance, 147, 189, 245
fractional-degree \mathbb{F} , 201	generalized vector product, 233
freight-train, 262	generating function, 287, 316
freight-train problem, 224, 262	geometric series, 96
frequency domain, 72, 152, 193, 194	Gibbs ringing, 119, 154, 160
frequency, complex: Laplace frequency, 73,	gOd, 276
216	gradient ∇ (), 38, 230, 274, 274
Fry, Thorton Carle, 290	gravity, 9, 70, 73, 121, 231, 241
FTC: fundamental theorem of calculus, 177	gravity waves, 73
FTCC: fundamental theorems of complex	greatest common divisor, 29, 42, 43, 45, 46,
calculus, 181	335
FTVC, 272	Green, 290
FTVC: fundamental theorem of vector cal-	Greens Theorem, 183
culus, 241	group delay, 188
function, causal, 162	gyrator, 151, 163, 340
function, circular, 102	
function, inverse, 102	
function, periodic, 102, 162	Н
functions: see complex analytic, 101	Halley, x
fundamental theorem of arithmetic, 315	Hankel function, 256
fundamental theorem: algebra, 37, 38, 109,	harmonic functions, 184
111	harmonic series, 160, 172
fundamental theorem: arithmetic, 22, 26, 35,	Heaviside step function, 160
38, 39	Heaviside, Oliver, 69
fundamental theorem: calculus, 180	Heisenberg, Werner, 57, 90, 103
fundamental theorem: calculus (Leibniz), 38	Helmholtz, 271
fundamental theorem: complex calculus	Helmholtz portrait, 271
(Cauchy), 38, 69, 171, 181, 207	Helmholtz's decomposition theorem, 14, 35,
fundamental theorem: mathematics, 70	229, 241, 270, 272
fundamental theorem: prime numbers, 35	Helmholtz's decomposition: see FTVC, 270
fundamental theorem: real calculus (Leib-	Helmholtz, Hermann von, 11, 69, 290, 323
niz), 206	Hilbert space, 118, 123, 152
fundamental theorem: scalar vs. vector, 177	Hilbert space, see vector space, 249
fundamental theorem: vector calculus, 14,	Hilbert, David, 69
229, 241, 270–272, 276	Homework, see Assignments, 30
fundamental theorem: vector calculus	horn equation, 235, 248–250, 257, 261, 266
(Helmholtz), 38	horn equation, derivation, 347
fundamental theorems: table of, 177	horn, conical, 259
	. ,,

horn, exponential, 260	Kirchhoff, Gustav, 37, 69, 323
horn, uniform, 257	Klein, Felix, ix
Hunt, Fredrick, 290	
Huygens, 248	
Huygens principle, 264	L
Huygens, Christiaan, 69	Lagrange, Joseph-Louis, 7, 69
Hydrogen spectrum, 359	Lamb, Willis, 290
hyperbolic differential equation, 242	Laplace and the speed of sound, 11
	Laplace frequency, 73, 149, 152, 158, 192, 193, 216
I	Laplace frequency plane, 192
IEEE-754, 22, 28, 74, 87	Laplace transform, 157, 216
immittance, 189	Laplace transform, impedance, 192
impedance, 16, 17, 100, 113, 114, 147, 149,	Laplace transforms: Functional properties,
151, 158, 183, 187, 189, 191, 193,	158
206, 217, 218	Laplace transforms: Properties I, 158
impedance composition, 150	Laplace transforms: Table II, 159
impedance matrix, 145	Laplace transforms: Table III, 314
impedance network, 146	Laplace's equation, 243
impedance, Brune, 113, 114	Laplace, Pierre-Simon, 72
impedance, generalized, 147, 245	Laplacian ∇^2 , 205, 230, 233, 242, 245, 248,
impedance, Kirchhoff's laws, 148	274
impedance, Ohm's law, 148	Laplacian, scalar: ∇^2 , 38
impedance, Thévenin, 145	Laplacian, scalar. $\sqrt{58}$ Laplacian, vector ∇^2 , 38
implicit function theorem, 99	Laplacian, vector \mathbf{V} , 38 Laplacian, vector: ∇^2 , 276
•	
impulse function, 159	Laplacian: <i>N</i> dimensional, 234
impulse response, 297	laws of gravity, 71
incompressible, 272	Lec20: zeta function, Euler, 322
inner product: see scalar product, 117	Lec20: zeta function, Riemann, 322
integers, 21	Leibniz, x
integers, utility of, 26	length, Euclidean, 117
integral definition of $\nabla \phi(\mathbf{x})$, 265	Leonardo da Vinci, 8
integral definition of $\nabla \cdot D(x)$, 267	light, speed of, 276
integral definition of $\nabla \times \boldsymbol{H}(\boldsymbol{x})$, 269	Lighthill, ames, 290
integral formula, Cauchy, 205	linear equations, 109
integral theorem, Cauchy, 205	linearity: P2, 339
integration by parts, 251	log function, 170, 203
integration, half, 314	logarithmic derivative, 78, 81, 197, 201, 202
intensity, 189	logarithmic derivative: definition, 78
internet security, 29	Lord Kelvin, 15
intersection, 115, 123	Lord Kelvin: William Thompson, 69
intersection of curves, 116, 121, 122, 126	Lord Rayleigh, 69, 290
intersection of sets, 116	Lord Rayleigh: John William Strutt, 69
intersection point, 123	Lorentz force, 164, 281, 282
Inverse Laplace transform, 217	
irrational poles, 197	
irrotational, 232, 270, 272	M
	Möbius transformation, see bilinear, 113
	matrix algebra, 114
K	matrix composition, 150
Kepler's theory of planetary motion, 71	matrix inverse, 24, 122, 127
Kepler, Johannes, 70	matrix inverse, derivation, 135
Kirchhoff's laws, 148, 246	matrix: non-square inverse, 91
Kirchhoff's portrait, 271	Maxwell's equation: matrix form, 278

Maxwell's equations, 17, 38, 177, 276, 277,	Olson, Harry, 290
279, 280	order vs. degree, 200, 201
Maxwell's equations, potential solutions,	order, derivatives, 296
283	order, fractional \mathbb{F} , 201
Maxwell's equations: d'Alembert solution,	
280	
Maxwell's equations: variable names and	P
units, 277	P10: quasistatic, 164
Maxwell's matrix wave equation, 280	P11: periodic ↔ discrete, 164
Maxwell, James, 37, 69	P1: causality, 162
ME: Maxwell's equations, 278	P2: linearity, 163
meromorphic function, 197	P3: passive, 163
Mersenne, 8, 189, 238	P4: real, 163
Mersenne and the speed of sound, 71	P4: time-invariant, 163
Mersenne primes, 11	P6: reciprocal, 163
minimum phase, 189, 192	
modal-analysis, 90, 249	P7: reversible, 163
modulo, 295	P8: space-invariant, 163
	P9: deterministic, 163
monic polynomial, 37, 74, 85–87	parabolic differential equation, 242
Morse, Phillip, 290	partial fraction expansion, 98, 201, 204
music, 1–3, 8, 33, 71	Pascal, Blaise, 69, 72
	Pascals [Pa] definition, 72
NI .	passive, 341
N	passive: P3, 339
Natural numbers: see counting numbers, 20	passwords, 29
Needham, Joseph, 2	Pauli, Wolfgang, 103
network postulates, 339	Pell's equation, 57, 58
network, algebraic, see Transmission matrix,	Pell's equation, Heisenberg's view, 19, 57
158	Periodic ↔ discrete, 346
networks, algebraic, 341	periodic ↔ discrete: P11, 339
Newton, x, 8, 13, 69–72, 76–80, 82, 102, 170,	Pipes, L.A., 290
241, 248	Plimpton-322, 58
Newton and the speed of sound, 72	plots, colorized, 199
Newton's laws, 246	plots, colorized: log(), 170
Newton's laws of motion, 71	plots, colorized: $\log \frac{1-z_J}{1+z_J}$, 179
Newton's root-finding method, 76–78, 80,	plots, colorized: \log_{1+z_J} , 179 plots, colorized: $\log z$, 169
82, 87, 88	plots, colorized: $\log 2$, 100 plots, colorized: $\frac{1}{1-e^{-s\pi}}$, 318
non-reciprocal, see reciprocity, 163	
nonlinear algebra, 163	plots, colorized: $\sqrt{s^2 + 1}$, 201
norm, see scalar product, 117	plots, colorized: e^z , 169
Norton parameters, 279	plots, colorized: $J_0(), H_0^{(1)}(), 220$
NOVA, fusion experiment, 281	plots, colorized: $J_o(\pi z)$ vs. $\cos(\pi z)$, 219
NS-1, 31	plots, colorized: s^2 , \sqrt{s} , 198
NS-2, 51	plots, colorized: $atan(z)$, 179
NS-3, 64	plots, colorized: reference condition, 168
Nyquist sampling, 153, 164, 262	plots: see Time Line, 2
Nyquist sampling of lumped-element mod-	PNT: prime number theorem, 35
els, 262	Poincare, Henri, 69
Nyquist, Harry, 69, 153, 164, 262	point at infinity, 171–173
11, January, 11, 100, 1007, 202	Poisson's equation, 243
	Poisson, Siméon Denis, 243
0	poles, 160, 297
octave, 1, 36	poles, degree, 201
Ohm's law, 148, 149, 151, 246	poles, fractional \mathbb{F} , 201
Omi 5 iaw, 170, 177, 131, 270	poics, fractional ±, 201

poles, fractional \mathbb{F} , 297	quartic, 74
poles, simple, 204	quasistatics, 164, 344, 345
polynomials, 6, 74	quasistatics: P10, 339
polynomials, long division, 111	quintic, 74
positive definite operator, 192, 342	
positive-real, 101, 163, 189, 192, 193, 198,	
342	R
postulates, 72, 158, 162–164, 339	Ramo, Simon, 290
postulates, Feynman's view, 158	Rankine, William, 72
potential, 70, 148, 227–229, 231, 239	rational function, 112, 113, 197
power, 148, 189, 191, 206, 342	rational function: see partial fraction expan-
Poynting scalar product, complex, 120	sion, 112
Poynting vector, 281	rational numbers, 21
PR: see positive-real functions, 101	Rayleigh reciprocity, see reciprocity, 163
prime, 20, 29, 35, 322	real: P4, 339
prime number theorem, 20, 21, 35, 36, 42	reciprocal system: eigenanalysis, 312
prime sieve, 39	reciprocal, see reciprocity, 163
primes, Eratosthenes, 39	reciprocity, 145, 146, 163, 312, 343
primes, Mersenne, 11	reciprocity: P6, 339
Principia, x, 11, 72, 178	reduced form, 21, 44
probability: average, 166	reflectance, 114, 190
probability: event, 165	region of convergence: see RoC, 100, 162
probability: expected value, 166	relatively prime, coprime, 21
probability: experiment, 166	removable singularity, 197
probability: observable, 166	residue, 87, 98, 197, 201, 205
probability: random variable, 166	residue expansion, 50, 86
probability: sampling noise $\sqrt{2/N}$, 166	residue theorem, Cauchy, 205
probability: the mean of many trials, 166	residue, definition, 204
probability: the number of events, 166	reversible system, eigenanalysis, 311
probability: trial, 165	reversible systems, 163, 344
probability: uncertainty, 166	reversible: P7, 339
propagation function, 150, 188	RHP, 183
propagation function, conical horn, 259	Riemann, 195
propagation function, exponential horn, 260	Riemann sheet, 102, 195, 196
propagation function, uniform horn, 257	Riemann sphere, 170
propagation function, with losses, 188, 323,	Riemann zeta function, 39, 313
328	Riemann, Bernard, 69
propagation of waves, 245	right half-plane, see RHP, 183
propagation vector, 72, 238	RoC, 29, 81, 100, 160, 178, 183, 195
public-key security, 29	RoC, RoD: definition, 95, 162 roots of Bessel functions, 250
public-key, see cryptography, 29	roots Of polynomials, 74
puzzles, 30	± *
Pythagoras, 1	roots of the companion matrix, 84 Rydberg atom, 88, 248, 359
Pythagorean triplets, 4, 19, 56	Rømer, Ole, 11, 57
Pythagoreans, 1, 8, 22, 26, 29, 57, 69, 93	Rømer, Oic, 11, 37
Pythagoreans, fate, 8	
	S
	Salmon, Vince, 33
Q	sampling noise: $\sqrt{2/N}$, 167
quadratic, 109	sampling theorem, 153, 164, 262
quadratic equation, solution, 75	scalar field, 228
quantum eigenstates, 94	scalar product, 110, 116, 117, 119, 156, 273
quantum mechanics, 33, 90	scalar product, generalized complex, 119

scalar product, see norm, 117	surge impedance: characteristic impedance,
scalar product, triple, 119	191
Schrödinger's equation, 33	SVD: singlar value decomposition, 91
Schrödinger, Erwin, 33, 90	symmetry, causality, 162
Schwarz inequality, 118, 123–125	symmetry, conjugate, 343
seconds in a day, 10	symmetry, matrix, 346
semiinductor, 199	symmetry, periodic, 160, 346
semitone, 1	symmetry, periodicity, 162 symmetry, time-frequency, 155
separation of variables, 261	symmetry, various, 153, 157
set theory, 22	system postulates, 192
set theory symbols defined, 292	system postulates, 172 system postulates, summary, 166
Shannon entropy, 41	systems, 157
sheet index, 198	systems, 137
sieve, 39	
sieve of Eratosthenes, 315	T
signal processing, digital, 62	Taylor series, 93, 97–99, 181, 194, 195, 266
signals, 151, 152	Taylor series, see analytic functions, 193
simple pole, 81	telegraph equation, 245
singlar value decomposition (SVD), 91	telephone equation, 245
singular circular: see RoC definition, 162	tesla, 277
singularity, 197	Thévenin parameters, 145, 278, 279, 312,
solenoidal, see incompressible, 272	340
solenoidal, see irrotational, 272	thermal admittance, 244
Sommerfeld, 103	thermal conductivity, 244
Sommerfeld, Arnold, 69, 290	thermodynamics: development of, 72
spatial invariant, 344	thermodynamics, speed of sound, 328
spatial invariant: P8, 339	time domain, 152
spectrum: see eigenvalues, 238	Time Line: 16 BCE-17 CE, 2
speed of light, 73, 276	Time Line: 16–19 CE, 13
speed of light, first measurements, 11	Time Line: 17–19 CE, 7
speed of light, in vacuum c_o , 284	Time Line: 17–20 CE, 70
speed of light: Feynman's view, 11	time travel, 187
speed of sound, 11, 72, 326	time-invariant, 343
speed of sound with losses, 188, 323	time-invariant: P5, 339
speed of sound: adiabatic expansion, 72	train problem: See DE3, 223 train-mission-line problem, 224, 262
speed of sound: Mersenne measures of, 71	transmission line, 114, 150, 179, 250
speed of sound: Newton's first calculation,	transmission line, generalization, 248
72	transmission matrix, 143, 145, 149, 151, 163,
speeds of sound, two, 72	257, 339, 340, 346
spiral of Fibonacci, 60	trapdoor function, 29
spiral of Theodorus, 29, 30	triangle inequality, 118, 130, 175, 299
step function, 159, 318	triple product, scalar, 116
step function, Heaviside, 160	triple product, vector, 119
Stokes theorem, 278	1 1
Stokes, George, 37, 290	
stream 1, 16, 19, 35	\mathbf{U}
stream 2, 16, 17, 35, 37, 38, 69	Units: <i>E</i> , <i>D</i> , <i>H</i> , <i>B</i> , 279
stream 3, 35, 37, 38, 62	
stream 3a, 17, 177	
stream 3b, 17, 227	V
Sturm-Liouville, 252, 261	vacuum, 72
surge admittance/impedance, 189	VC-1, 252

VC-2, 285	wave equation, acoustics, 246
vector cross-product, 119	wave evolution, 73, 244
vector exterior-product, 119	wave filters, 324
vector identity: $\nabla \cdot \nabla \times$, 273	wave number: see propagation function, 72
vector identity: $\nabla \times \nabla$, 273	wavelength, 188
vector identity: $\nabla \times \nabla \times$, 273	webers, 277
vector identity: Laplacian, 273	Webster horn equation, derivation, 347
vector identity: gOd , 276	Webster horn equation, see horn equation,
vector identity: DoG , 230	248
vector identity: gOd , 230	Webster Laplacian, 248
vector inner product: see scalar product, 119	wedge-product: see vector wedge-product,
vector Laplacian ∇^2 (), 230, 234	119
vector operator mnemonics, definitions, 274	
vector operator mnemonics: DoG, gOd,	
DoG, CoC, 229	Y
vector product, 116, 119, 273	year: days in, 10
vector product, generalized, 116	year: improved composite definition, 10
vector product, triple, 119	
vector space, 115, 117, 273	
vector space, Fourier transform, 125	Z
vector triple product, 119	z-transform, 60
vector wedge-product, 116, 119, 120, 230,	Zeno's paradox, 177
307	zeros, 160, 297
vector, three, 119	zeta function poles, 318
vector, unit, 119	zeta function RoC, 108, 317
vectors, 115	zeta function, Euler, 39
visco-thermal loss, 72, 188, 250, 323, 328	zeta function, poles, 108
viscosity of air, 326	zeta function, product formula, 108, 315
	zeta function, Riemann, 39
	zeta function: definition, 315
W	Zhang, Yiming, 336
wave equation, 72, 248	zviz.m, see plots, colorized, 168